Concurrency (Part IV): Mutual Exclusion, **Synchronization (Finish)**, **Deadlock, and Starvation**

Professor Travis Peters
CSCI 460 Operating Systems
Fall 2019

Some slides & figures adapted from Stallings instructor resources.

Some slides adapted from Adam Bates's F'18 CS423 course @ UIUC
https://courses.engr.illinois.edu/cs423/sp2018/schedule.html



–http://www.datamation.com/news/tech-comics-quantum-physics-2.html

Monitors

- A SW module consisting of…
  - an initialization sequence
  - 1+ procedures *—the only way for a process to enter the monitor*
  - local data *—accessible only by monitor's procedures; similar to objects in OOP*

- Eqivalent to semaphores, but easier!
  - Only one process may execute within the monitor at a time;
    all other processes are blocked until it becomes available again
    => Mutual Exclusion by design!
  - Synchronization achieved via **condition variables**.
    - Used to represent a condition that needs to be waited on until the condition is True
    - No "value"
    - Think of it as a waiting queue (initial "non-value" = Empty)



Monitors *(cont.)*

- Hoare-Style
  - Block caller (signaller) *immediately* and run the next waiting proc
  - Operations for condition variables (cvar):
    - `cwait( cvar )` *//suspend caller on condition `cvar`*
    - `csignal ( cvar )` *//resume some process waiting on condition `cvar`*
  - **Questions:** Advantages? Limitations? Drawbacks? Potential improvements?
- Mesa-Style
  - Called (signaller) keeps running and retains access to the monitor
  - Waiter placed on ready queue
  - *On resume, need to re-check conition!*
  - Operations for condition variables (cvar):
    - `notify( cvar )` *//resume the next waiting process at some convenient time (later)*
    - `broadcast ( cvar )` *//all procs waiting on cvar get moved to a ready state/queue*
  - **Questions:** Advantages? Limitations? Drawbacks? Potential improvements?



Message Passing



- Operations
  - `send( dest, msg )`
  - `receive ( src, msg )`
- Operations come in diffferent flavors…
  - blocking send, blocking receive *(a.k.a. "rendezvous")*
  - nonblocking send, blocking receive *(most common)*
  - nonblocking send, nonblocking receive
- Addressing
  - direct addressing (e.g., specific process ID known)

    vs.

    indirect addresses (msgs sent to shared mailbox)



Examples?

Be sure to review solutions for, e.g., Produce/Consmer with different styles of monitors, message passing schemes, etc.

Readers/Writers Problem

- Each process is either a ***reader*** or a ***writer***
- Both readers and writers share access to a data object
  (e.g., file, database)
- Multiple readers can access the data object simultaneously
- Each writer must have exclusive access
  (i.e., cannot share w/ readers OR any other writer)

Readers/Writers Problem

```
/* program readersandwriters */
int readcount;
semaphore x = 1, wsem = 1;
void reader()
{
    while (true) {
      semWait (x);
      readcount++;
      if (readcount == 1) semWait (wsem);
      semSignal (x);
      READUNIT();
      semWait (x);
      readcount--;
      if (readcount == 0) semSignal (wsem);
      semSignal (x);
    }
 }
void writer()
{
    while (true) {
      semWait (wsem);
      WRITEUNIT();
      semSignal (wsem);
    }
}

void main()
{
    readcount = 0;
    parbegin (reader, writer);
}
```

Priority goes to readers…

```
/* program readersandwriters */
int  readcount, writecount;
semaphore x = 1, y = 1, z = 1, wsem = 1, rsem = 1;
void reader()
{
    while (true) {
      semWait (z);
           semWait (rsem);
                semWait (x);
                     readcount++;
                     if (readcount == 1) semWait (wsem);
                semSignal (x);
           semSignal (rsem);
      semSignal (z);
      READUNIT();
      semWait (x);
           readcount--;
           if (readcount == 0) semSignal (wsem);
      semSignal (x);
    }
}
void writer ()
{
    while (true) {
      semWait (y);
           writecount++;
           if (writecount == 1) semWait (rsem);
      semSignal (y);
      semWait (wsem);
      WRITEUNIT();
      semSignal (wsem);
      semWait (y);
           writecount--;
           if (writecount == 0) semSignal (rsem);
      semSignal (y);
    }
}
void main()
{
    readcount = writecount = 0;
    parbegin (reader, writer);
}
```

Priority goes to writers…