

Red Hat Enterprise Linux 10-beta Security hardening

Enhancing security of Red Hat Enterprise Linux 10 systems

Last Updated: 2025-04-02

Red Hat Enterprise Linux 10-beta Security hardening

Enhancing security of Red Hat Enterprise Linux 10 systems

Legal Notice

Copyright © 2025 Red Hat, Inc.

The text of and illustrations in this document are licensed by Red Hat under a Creative Commons Attribution–Share Alike 3.0 Unported license ("CC-BY-SA"). An explanation of CC-BY-SA is available at

http://creativecommons.org/licenses/by-sa/3.0/

. In accordance with CC-BY-SA, if you distribute this document or an adaptation of it, you must provide the URL for the original version.

Red Hat, as the licensor of this document, waives the right to enforce, and agrees not to assert, Section 4d of CC-BY-SA to the fullest extent permitted by applicable law.

Red Hat, Red Hat Enterprise Linux, the Shadowman logo, the Red Hat logo, JBoss, OpenShift, Fedora, the Infinity logo, and RHCE are trademarks of Red Hat, Inc., registered in the United States and other countries.

Linux ® is the registered trademark of Linus Torvalds in the United States and other countries.

Java [®] is a registered trademark of Oracle and/or its affiliates.

XFS [®] is a trademark of Silicon Graphics International Corp. or its subsidiaries in the United States and/or other countries.

MySQL ® is a registered trademark of MySQL AB in the United States, the European Union and other countries.

Node.js ® is an official trademark of Joyent. Red Hat is not formally related to or endorsed by the official Joyent Node.js open source or commercial project.

The OpenStack [®] Word Mark and OpenStack logo are either registered trademarks/service marks or trademarks/service marks of the OpenStack Foundation, in the United States and other countries and are used with the OpenStack Foundation's permission. We are not affiliated with, endorsed or sponsored by the OpenStack Foundation, or the OpenStack community.

All other trademarks are the property of their respective owners.

Abstract

Learn the processes and practices for securing Red Hat Enterprise Linux servers and workstations against local and remote intrusion, exploitation, and malicious activity. By using these approaches and tools, you can create a more secure computing environment for the data center, workplace, and home.

Table of Contents

RHEL BETA RELEASE	. 5
CHAPTER 1. SWITCHING RHEL TO FIPS MODE	. 6
1.1. FEDERAL INFORMATION PROCESSING STANDARDS 140 AND FIPS MODE	6
RHEL in FIPS mode	6
FIPS mode status	6
FIPS in crypto-policies	6
1.2. INSTALLING THE SYSTEM WITH FIPS MODE ENABLED	7
1.3. ENABLING FIPS MODE WITH RHEL IMAGE BUILDER	8
1.4. ENABLING FIPS MODE BY USING BOOTC-IMAGE-BUILDER	9
1.5. LIST OF RHEL APPLICATIONS USING CRYPTOGRAPHY THAT IS NOT COMPLIANT WITH FIPS 140-3	10
CHAPTER 2. USING SYSTEM-WIDE CRYPTOGRAPHIC POLICIES	13
2.1. SYSTEM-WIDE CRYPTOGRAPHIC POLICIES	13
2.2. CHANGING THE SYSTEM-WIDE CRYPTOGRAPHIC POLICY	15
2.3. SWITCHING THE SYSTEM-WIDE CRYPTOGRAPHIC POLICY TO MODE COMPATIBLE WITH EARLIER RELEASES	16
2.4. SETTING UP SYSTEM-WIDE CRYPTOGRAPHIC POLICIES IN THE WEB CONSOLE	17
2.5. EXCLUDING AN APPLICATION FROM FOLLOWING SYSTEM-WIDE CRYPTO POLICIES	18
2.5.1. Examples of opting out of system-wide crypto policies	18
2.6. CUSTOMIZING SYSTEM-WIDE CRYPTOGRAPHIC POLICIES WITH SUBPOLICIES	19
2.7. CREATING AND SETTING A CUSTOM SYSTEM-WIDE CRYPTOGRAPHIC POLICY	21
2.8. ENHANCING SECURITY WITH THE FUTURE CRYPTOGRAPHIC POLICY USING THE CRYPTO POLICIE	S
RHEL SYSTEM ROLE	22
CHAPTER 3. CONFIGURING APPLICATIONS TO USE CRYPTOGRAPHIC HARDWARE THROUGH PKCS #11	١
	26
3.1. CRYPTOGRAPHIC HARDWARE SUPPORT THROUGH PKCS #11	26
3.2. AUTHENTICATING BY SSH KEYS STORED ON A SMART CARD	26
3.3. CONFIGURING APPLICATIONS FOR AUTHENTICATION WITH CERTIFICATES ON SMART CARDS	28
3.4. USING HSMS PROTECTING PRIVATE KEYS IN APACHE	28
3.5. ADDITIONAL RESOURCES	29
CHAPTER 4. CONTROLLING ACCESS TO SMART CARDS BY USING POLKIT	30
4.1. SMART-CARD ACCESS CONTROL THROUGH POLKIT	30
4.2. TROUBLESHOOTING PROBLEMS RELATED TO PC/SC AND POLKIT	30
4.3. DISPLAYING MORE DETAILED INFORMATION ABOUT POLKIT AUTHORIZATION TO PC/SC	32
4.4. ADDITIONAL RESOURCES	33
CHAPTER 5. SCANNING THE SYSTEM FOR CONFIGURATION COMPLIANCE	34
5.1. CONFIGURATION COMPLIANCE TOOLS IN RHEL	34
5.2. CONFIGURATION COMPLIANCE SCANNING	35
5.2.1. Configuration compliance in RHEL	35
5.2.2. Possible results of an OpenSCAP scan	35
5.2.3. Viewing profiles for configuration compliance	36
5.2.4. Assessing configuration compliance with a specific baseline	37
5.2.5. Assessing security compliance of a container or a container image with a specific baseline	38
5.3. CONFIGURATION COMPLIANCE REMEDIATION	39
5.3.1. Remediating the system to align with a specific baseline	39
5.3.2. Remediating the system to align with a specific baseline by using an SSG Ansible playbook	40
5.3.3. Creating a remediation Ansible playbook to align the system with a specific baseline	41
5.4. PERFORMING A HARDENED INSTALLATION OF RHEL WITH KICKSTART	42
5.5. CUSTOMIZING A SECURITY PROFILE WITH AUTOTAILOR	43

5.6. SCAP SECURITY GUIDE PROFILES SUPPORTED IN RHEL 10	45
5.7. ADDITIONAL RESOURCES	47
CHAPTER 6. ENSURING SYSTEM INTEGRITY WITH KEYLIME	48
6.1. HOW KEYLIME WORKS	48
6.2. CONFIGURING KEYLIME VERIFIER	50
6.3. DEPLOYING KEYLIME VERIFIER AS A CONTAINER	53
6.4. DEPLOYING KEYLIME REGISTRAR FROM A PACKAGE	55
6.5. DEPLOYING KEYLIME REGISTRAR AS A CONTAINER	58
6.6. DEPLOYING A KEYLIME SERVER BY USING RHEL SYSTEM ROLES	60
6.7. VARIABLES FOR THE KEYLIME_SERVER RHEL SYSTEM ROLE	62
6.8. DEPLOYING KEYLIME TENANT FROM A PACKAGE	63
6.9. DEPLOYING KEYLIME AGENT FROM A PACKAGE	65
6.10. CONFIGURING KEYLIME FOR RUNTIME MONITORING	69
6.11. CONFIGURING KEYLIME FOR MEASURED BOOT ATTESTATION	71
6.12. KEYLIME ENVIRONMENT VARIABLES	73
Verifier configuration	74 77
Registrar configuration	77 78
Tenant configuration CA configuration	70 80
Agent configuration	81
Logging configuration	83
Logging configuration	00
CHAPTER 7. CHECKING INTEGRITY WITH AIDE	86
7.1. INSTALLING AIDE	86
7.2. PERFORMING INTEGRITY CHECKS WITH AIDE	86
7.3. UPDATING AN AIDE DATABASE	87
7.4. FILE-INTEGRITY TOOLS: AIDE AND IMA	88
7.5. ADDITIONAL RESOURCES	88
CHAPTER 8. MANAGING SUDO ACCESS	89
8.1. USER AUTHORIZATIONS IN SUDOERS	89
8.2. GRANTING SUDO ACCESS TO A USER	90
8.3. ENABLING UNPRIVILEGED USERS TO RUN CERTAIN COMMANDS	91
CHAPTER 9. CONFIGURING AUTOMATED UNLOCKING OF ENCRYPTED VOLUMES BY USING POLICY-	
BASED DECRYPTION	94
9.1. NETWORK-BOUND DISK ENCRYPTION	94
9.2. DEPLOYING A TANG SERVER WITH SELINUX IN ENFORCING MODE	96
9.3. ROTATING TANG SERVER KEYS AND UPDATING BINDINGS ON CLIENTS	97
9.4. CONFIGURING AUTOMATED UNLOCKING BY USING A TANG KEY IN THE WEB CONSOLE	99
9.5. BASIC NBDE AND TPM2 ENCRYPTION-CLIENT OPERATIONS	102
9.6. CONFIGURING NBDE CLIENTS FOR AUTOMATED UNLOCKING OF LUKS-ENCRYPTED VOLUMES	103
9.7. CONFIGURING NBDE CLIENTS WITH STATIC IP CONFIGURATION	105
9.8. CONFIGURING MANUAL ENROLLMENT OF LUKS-ENCRYPTED VOLUMES BY USING A TPM 2.0 POI	LICY 106
9.9. REMOVING A CLEVIS PIN FROM A LUKS-ENCRYPTED VOLUME MANUALLY	108
9.10. CONFIGURING AUTOMATED ENROLLMENT OF LUKS-ENCRYPTED VOLUMES BY USING KICKSTA	RT 109
9.11. CONFIGURING AUTOMATED UNLOCKING OF A LUKS-ENCRYPTED REMOVABLE STORAGE DEVICE	E
0.12 DEDLOVING LUCIT AVAILABLETVARDE CVCTEMC	110
9.12. DEPLOYING HIGH-AVAILABILITY NBDE SYSTEMS	111
High-available NBDE using Shamir's Secret Sharing	111
Example 1: Redundancy with two Tang servers	111

Example 2: Shared secret on a Tang server and a TPM device	112
9.13. DEPLOYMENT OF VIRTUAL MACHINES IN A NBDE NETWORK	112
9.14. BUILDING AUTOMATICALLY-ENROLLABLE VM IMAGES FOR CLOUD ENVIRONMENTS BY USING	
NBDE	113
9.15. DEPLOYING TANG AS A CONTAINER	113
9.16. CONFIGURING NBDE BY USING RHEL SYSTEM ROLES	114
9.16.1. Using the nbde_server RHEL system role for setting up multiple Tang servers	115
9.16.2. Setting up Clevis clients with DHCP by using the nbde_client RHEL system role	116
9.16.3. Setting up static-IP Clevis clients by using the nbde_client RHEL system role	118
CHAPTER 10. BLOCKING AND ALLOWING APPLICATIONS BY USING FAPOLICYD	121
10.1. INTRODUCTION TO FAPOLICYD	121
10.2. DEPLOYING FAPOLICYD	122
10.3. MARKING FILES AS TRUSTED USING AN ADDITIONAL SOURCE OF TRUST	124
10.4. ADDING CUSTOM ALLOW AND DENY RULES FOR FAPOLICYD	125
10.5. ENABLING FAPOLICYD INTEGRITY CHECKS	128
10.6. TROUBLESHOOTING PROBLEMS RELATED TO FAPOLICYD	128
10.7. PREVENTING USERS FROM EXECUTING UNTRUSTWORTHY CODE BY USING THE FAPOLICYD RHE	ïL
SYSTEM ROLE	131
10.8. ADDITIONAL RESOURCES	132
CHAPTER 11. PROTECTING SYSTEMS AGAINST INTRUSIVE USB DEVICES	133
11.1. USBGUARD	133
11.2. INSTALLING USBGUARD	133
11.3. BLOCKING AND AUTHORIZING A USB DEVICE BY USING THE CLI	134
11.4. PERMANENTLY BLOCKING AND AUTHORIZING A USB DEVICE	135
11.5. CREATING A CUSTOM POLICY FOR USB DEVICES	136
11.6. CREATING A STRUCTURED CUSTOM POLICY FOR USB DEVICES	137
11.7. AUTHORIZING USERS AND GROUPS TO USE THE USBGUARD IPC INTERFACE	139
11.8. LOGGING USBGUARD AUTHORIZATION EVENTS TO THE LINUX AUDIT LOG	140
11.9 ADDITIONAL RESOURCES	140

RHEL BETA RELEASE

Red Hat provides Red Hat Enterprise Linux Beta access to all subscribed Red Hat accounts. The purpose of Beta access is to:

- Provide an opportunity to customers to test major features and capabilities prior to the general availability release and provide feedback or report issues.
- Provide Beta product documentation as a preview. Beta product documentation is under development and is subject to substantial change.

Note that Red Hat does not support the usage of RHEL Beta releases in production use cases. For more information, see the Red Hat Knowledgebase solution What does Beta mean in Red Hat Enterprise Linux and can I upgrade a RHEL Beta installation to a General Availability (GA) release?.

CHAPTER 1. SWITCHING RHEL TO FIPS MODE

To enable the cryptographic module self-checks mandated by the Federal Information Processing Standard (FIPS) 140-3, you must operate Red Hat Enterprise Linux 10 in FIPS mode.

To disable FIPS mode, reinstall the system without enabling FIPS mode.

1.1. FEDERAL INFORMATION PROCESSING STANDARDS 140 AND FIPS MODE

The Federal Information Processing Standards (FIPS) Publication 140 is a series of computer security standards developed by the National Institute of Standards and Technology (NIST) to ensure the quality of cryptographic modules. The FIPS 140 standard ensures that cryptographic tools implement their algorithms correctly. Runtime cryptographic algorithms and integrity self-tests are some of the mechanisms to ensure a system uses cryptography that meets the requirements of the standard.

RHEL in FIPS mode

To ensure that your RHEL system generates and uses all cryptographic keys only with FIPS-approved algorithms, you must switch RHEL to FIPS mode.

To enable FIPS mode, start the installation in FIPS mode. This avoids cryptographic key material regeneration and reevaluation of the compliance of the resulting system associated with converting already deployed systems. Additionally, components that change their algorithm choices based on whether FIPS mode is enabled choose the correct algorithms. For example, LUKS disk encryption uses the PBKDF2 key derivation function (KDF) during installation in FIPS mode, but it chooses the non-FIPS-compliant Argon2 KDF otherwise. Therefore, a non-FIPS installation with disk encryption is either not compliant or potentially unbootable when switched to FIPS mode after the installation.

To operate a FIPS-compliant system, create all cryptographic key material in FIPS mode. Furthermore, the cryptographic key material must never leave the FIPS environment unless it is securely wrapped and never unwrapped in non-FIPS environments.

FIPS mode status

Whether FIPS mode is enabled is determined by the **fips=1** boot option on the kernel command line. The system-wide cryptographic policy automatically follows this setting if it is not explicitly set by using the **update-crypto-policies --set FIPS** command. Systems with a separate partition for **/boot** additionally require a **boot=UUID=<uuid-of-boot-disk>** kernel command line argument. The installer performs the required changes when started in FIPS mode.

Enforcement of restrictions required in FIPS mode depends on the contents of the /proc/sys/crypto/fips_enabled file. If the file contains 1, RHEL core cryptographic components switch to mode, in which they use only FIPS-approved implementations of cryptographic algorithms. If /proc/sys/crypto/fips_enabled contains 0, the cryptographic components do not enable their FIPS mode.

FIPS in crypto-policies

The **FIPS** system-wide cryptographic policy helps to configure higher-level restrictions. Therefore, communication protocols supporting cryptographic agility do not announce ciphers that the system refuses when selected. For example, the ChaCha20 algorithm is not FIPS-approved, and the **FIPS** cryptographic policy ensures that TLS servers and clients do not announce the TLS_ECDHE_ECDSA_WITH_CHACHA20_POLY1305_SHA256 TLS cipher suite, because any attempt to use such a cipher fails.

If you operate RHEL in FIPS mode and use an application providing its own FIPS-mode-related configuration options, ignore these options and the corresponding application guidance. The system

runs in FIPS mode and the system-wide cryptographic policies enforce only FIPS-compliant cryptography. For example, the Node.js configuration option **--enable-fips** is ignored if the system runs in FIPS mode. If you use the **--enable-fips** option on a system not running in FIPS mode, you do not meet the FIPS-140 compliance requirements.



NOTE

The cryptographic modules of RHEL 10 are not yet certified for the FIPS 140-3 requirements by the National Institute of Standards and Technology (NIST) Cryptographic Module Validation Program (CMVP). You can see the validation status of cryptographic modules in the FIPS – Federal Information Processing Standards section on the Product compliance Red Hat Customer Portal page.

Additional resources

- FIPS Federal Information Processing Standards section on the Product compliance Red Hat Customer Portal page
- RHEL system-wide cryptographic policies
- FIPS publications at NIST Computer Security Resource Center .
- Federal Information Processing Standards Publication: FIPS 140-3

1.2. INSTALLING THE SYSTEM WITH FIPS MODE ENABLED

To enable the cryptographic module self-checks mandated by the Federal Information Processing Standard (FIPS) 140, enable FIPS mode during the system installation.



WARNING

After you complete the setup of FIPS mode, you cannot switch off FIPS mode without putting the system into an inconsistent state. If your scenario requires this change, the only correct way is a complete re-installation of the system.

Procedure

- 1. Add the **fips=1** option to the kernel command line at the start of the system installation when the Red Hat Enterprise Linux boot window opens and displays available boot options.
 - a. On UEFI systems, press the **e** key, move the cursor to the end of the **linuxefi** kernel command line, and add **fips=1** to the end of this line, for example:

linuxefi /images/pxeboot/vmlinuz inst.stage2=hd:LABEL=RHEL-1-0-0-BaseOS-x86_64 rd.live.\ check quiet fips=1

b. On BIOS systems, press the **Tab** key, move the cursor to the end of the kernel command line, and add **fips=1** to the end of this line, for example:

> vmlinuz initrd=initrd.img inst.stage2=hd:LABEL=RHEL-1-0-0-BaseOS-x86_64 rd.live.check quiet fips=1

- 2. During the software selection stage, do not install any third-party software.
- 3. After the installation, the system starts in FIPS mode automatically.

Verification

• After the system starts, check that FIPS mode is enabled:

```
$ cat /proc/sys/crypto/fips_enabled 1
```

Additional resources

Customizing boot options

1.3. ENABLING FIPS MODE WITH RHEL IMAGE BUILDER

You can create a customized image and boot a FIPS-enabled RHEL image. Before you compose the image, you must change the value of the **fips** directive in your blueprint.

Prerequisites

• You are logged in as the root user or a user who is a member of the **weldr** group.

Procedure

1. Create a plain text file in the Tom's Obvious, Minimal Language (TOML) format with the following content:

```
name = "system-fips-mode-enabled"
description = "blueprint with FIPS enabled "
version = "0.0.1"

[customizations]
fips = true

[[customizations.user]]
name = "admin"
password = "admin"
groups = ["users", "wheel"]
```

2. Import the blueprint to the RHEL image builder server:

composer-cli blueprints push

blueprint-name>.toml

3. List the existing blueprints to check whether the created blueprint is successfully imported and exists:

composer-cli blueprints show <blueprint-name>

- 4. Check whether the components and versions listed in the blueprint and their dependencies are valid:
 - # composer-cli blueprints depsolve <blueprint-name>
- 5. Build the customized RHEL image:
 - # composer-cli compose start \

 -name> \ <image-type> \
- 6. Review the image status:

```
# composer-cli compose status
...
$ <UUID> FINISHED <date> <blueprint-name> <blueprint-version> <image-type> ...
```

7. Download the image:

composer-cli compose image <UUID>

RHEL image builder downloads the image to the current directory path. The UUID number and the image size are displayed alongside:

\$ <UUID-image-name.type>: <size> MB

Verification

- 1. Log in to the system image with the username and password that you configured in your blueprint.
- 2. Check if FIPS mode is enabled:

```
$ cat /proc/sys/crypto/fips_enabled 1
```

1.4. ENABLING FIPS MODE BY USING BOOTC-IMAGE-BUILDER

To create a disk image and enable FIPS mode with the **bootc-image-builder** or the **bootc install to-disk** tool, pass the custom Containerfile as an argument when building the image.

Prerequisites

- You have Podman installed on your host machine.
- You have **virt-install** installed on your host machine.
- You have root access to run the bootc-image-builder tool, and run the containers in -privileged mode, to build the images.

Procedure

1. Create a Containerfile with the following instructions to enable the **fips=1** kernel argument:

FROM registry.redhat.io/rhel9/rhel-bootc:latest

Enable fips=1 kernel argument: https://containers.github.io/bootc/building/kernel-arguments.html

COPY 01-fips.toml /usr/lib/bootc/kargs.d/

Enable the FIPS crypto policy

crypto-policies-scripts is not installed by default in RHEL-10

RUN dnf install -y crypto-policies-scripts && update-crypto-policies --no-reload --set FIPS

2. Create your bootc-compatible base disk images with **bootc-image-builder**.

1.5. LIST OF RHEL APPLICATIONS USING CRYPTOGRAPHY THAT IS NOT COMPLIANT WITH FIPS 140-3

To pass all relevant cryptographic certifications, such as FIPS 140-3, use libraries from the core cryptographic components set. These libraries, except from **libgcrypt**, also follow the RHEL systemwide cryptographic policies.

See the RHEL core cryptographic components Red Hat Knowledgebase article for an overview of the core cryptographic components, the information on how are they selected, how are they integrated into the operating system, how do they support hardware security modules and smart cards, and how do cryptographic certifications apply to them.

List of RHEL 10 applications using cryptography that is not compliant with FIPS 140-3

Bacula

Implements the CRAM-MD5 authentication protocol.

Cyrus SASL

Uses the SCRAM-SHA-1 authentication method.

Dovecot

Uses SCRAM-SHA-1.

Emacs

Uses SCRAM-SHA-1.

FreeRADIUS

Uses MD5 and SHA-1 for authentication protocols.

Ghostscript

Custom cryptography implementation (MD5, RC4, SHA-2, AES) to encrypt and decrypt documents.

GRUB2

Supports legacy firmware protocols requiring SHA-1 and includes the **libgcrypt** library.

iPXE

Implements TLS stack.

Kerberos

Preserves support for SHA-1 (interoperability with Windows).

Lasso

The lasso_wsse_username_token_derive_key() key derivation function (KDF) uses SHA-1.

MariaDB, MariaDB Connector

The mysql_native_password authentication plugin uses SHA-1.

MySQL

mysql_native_password uses SHA-1.

OpenIPMI

The RAKP-HMAC-MD5 authentication method is not approved for FIPS usage and does not work in FIPS mode.

Ovmf (UEFI firmware), Edk2, shim

Full cryptographic stack (an embedded copy of the OpenSSL library).

Perl

Uses HMAC, HMAC-SHA1, HMAC-MD5, SHA-1, SHA-224,....

Pidgin

Implements DES and RC4 ciphers.

PKCS #12 file processing (OpenSSL, GnuTLS, NSS, Firefox, Java)

All uses of PKCS #12 are not FIPS-compliant, because the Key Derivation Function (KDF) used for calculating the whole-file HMAC is not FIPS-approved. As such, PKCS #12 files are considered to be plain text for the purposes of FIPS compliance. For key-transport purposes, wrap PKCS #12 (.p12) files using a FIPS-approved encryption scheme.

Poppler

Can save PDFs with signatures, passwords, and encryption based on non-allowed algorithms if they are present in the original PDF (for example MD5, RC4, and SHA-1).

PostgreSQL

Implements Blowfish, DES, and MD5. A KDF uses SHA-1.

QAT Engine

Mixed hardware and software implementation of cryptographic primitives (RSA, EC, DH, AES,...)

Ruby

Provides insecure MD5 and SHA-1 library functions.

Samba

Preserves support for RC4 and DES (interoperability with Windows).

Syslinux

BIOS passwords use SHA-1.

SWTPM

Explicitly disables FIPS mode in its OpenSSL usage.

Unbound

DNS specification requires that DNSSEC resolvers use a SHA-1-based algorithm in DNSKEY records for validation.

Valgrind

AES, SHA hashes.^[1]

zip

Custom cryptography implementation (insecure PKWARE encryption algorithm) to encrypt and decrypt archives using a password.

Additional resources

- FIPS Federal Information Processing Standards section on the Product compliance Red Hat Customer Portal page
- RHEL core cryptographic components (Red Hat Knowledgebase)

 $\hbox{$\tt [1]$ Re-implements in software hardware-offload operations, such as AES-NI or SHA-1 and SHA-2 on ARM.}$

CHAPTER 2. USING SYSTEM-WIDE CRYPTOGRAPHIC POLICIES

The system-wide cryptographic policies is a system component that configures the core cryptographic subsystems, covering the TLS, IPsec, SSH, DNSSec, and Kerberos protocols. It provides a small set of policies, which the administrator can select.

2.1. SYSTEM-WIDE CRYPTOGRAPHIC POLICIES

When a system-wide policy is set up, applications in RHEL follow it and refuse to use algorithms and protocols that do not meet the policy, unless you explicitly request the application to do so. That is, the policy applies to the default behavior of applications when running with the system-provided configuration but you can override it if required.

RHEL 10 contains the following predefined policies:

DEFAULT

The default system-wide cryptographic policy level offers secure settings for current threat models. It allows the TLS 1.2 and 1.3 protocols, as well as the IKEv2 and SSH2 protocols. The RSA keys and Diffie-Hellman parameters are accepted if they are at least 2048 bits long. TLS ciphers that use the RSA key exchange are rejected.

LEGACY

Ensures maximum compatibility with Red Hat Enterprise Linux 6 and earlier; it is less secure due to an increased attack surface. CBC-mode ciphers are allowed to be used with SSH. It allows the TLS 1.2 and 1.3 protocols, as well as the IKEv2 and SSH2 protocols. The RSA keys and Diffie-Hellman parameters are accepted if they are at least 2048 bits long. SHA-1 signatures are allowed outside TLS. Ciphers that use the RSA key exchange are accepted.

FUTURE

A stricter forward-looking security level intended for testing a possible future policy. This policy does not allow the use of SHA-1 in DNSSec or as an HMAC. SHA2-224 and SHA3-224 hashes are rejected. 128-bit ciphers are disabled. CBC-mode ciphers are disabled except in Kerberos. It allows the TLS 1.2 and 1.3 protocols, as well as the IKEv2 and SSH2 protocols. The RSA keys and Diffie-Hellman parameters are accepted if they are at least 3072 bits long. If your system communicates on the public internet, you might face interoperability problems.



IMPORTANT

Because a cryptographic key used by a certificate on the Customer Portal API does not meet the requirements by the **FUTURE** system-wide cryptographic policy, the **redhat-support-tool** utility does not work with this policy level at the moment.

To work around this problem, use the **DEFAULT** cryptographic policy while connecting to the Customer Portal API.

FIPS

Conforms with the FIPS 140 requirements. Red Hat Enterprise Linux systems in FIPS mode use this policy.



NOTE

Your system is not FIPS-compliant after you set the **FIPS** cryptographic policy. The only correct way to make your RHEL system compliant with the FIPS 140 standards is by installing it in FIPS mode.

RHEL also provides the **FIPS:OSPP** system-wide subpolicy, which contains further restrictions for cryptographic algorithms required by the Common Criteria (CC) certification. The system becomes less interoperable after you set this subpolicy. For example, you cannot use RSA and DH keys shorter than 3072 bits, additional SSH algorithms, and several TLS groups. Setting **FIPS:OSPP** also prevents connecting to Red Hat Content Delivery Network (CDN) structure. Furthermore, you cannot integrate Active Directory (AD) into the IdM deployments that use **FIPS:OSPP**, communication between RHEL hosts using **FIPS:OSPP** and AD domains might not work, or some AD accounts might not be able to authenticate.



NOTE

Your system is not CC-compliant after you set the **FIPS:OSPP** cryptographic subpolicy. The only correct way to make your RHEL system compliant with the CC standard is by following the guidance provided in the **cc-config** package. See the Common Criteria section on the Product compliance Red Hat Customer Portal page for a list of certified RHEL versions, validation reports, and links to CC guides.

Red Hat continuously adjusts all policy levels so that all libraries provide secure defaults, except when using the **LEGACY** policy. Even though the **LEGACY** profile does not provide secure defaults, it does not include any algorithms that are easily exploitable. As such, the set of enabled algorithms or acceptable key sizes in any provided policy may change during the lifetime of Red Hat Enterprise Linux.

Such changes reflect new security standards and new security research. If you must ensure interoperability with a specific system for the whole lifetime of Red Hat Enterprise Linux, you should opt-out from the system-wide cryptographic policies for components that interact with that system or re-enable specific algorithms using custom cryptographic policies.

The specific algorithms and ciphers described as allowed in the policy levels are available only if an application supports them:

Table 2.1. Cipher suites and protocols enabled in the cryptographic policies

	LEGACY	DEFAULT	FIPS	FUTURE
IKEv1	no	no	no	no
3DES	no	no	no	no
RC4	no	no	no	no
DH	min. 2048-bit	min. 2048-bit	min. 2048-bit	min. 3072-bit
RSA	min. 2048-bit	min. 2048-bit	min. 2048-bit	min. 3072-bit
DSA	no	no	no	no

	LEGACY	DEFAULT	FIPS	FUTURE
TLS v1.1 and older	no	no	no	no
TLS v1.2 and newer	yes	yes	yes	yes
SHA-1 in digital signatures and certificates	yes ^[a]	no	no	no
CBC mode ciphers	yes	no ^[b]	no ^[c]	no ^[d]
Symmetric ciphers with keys < 256 bits	yes	yes	yes	no

 $\lceil a \rceil$ SHA-1 signatures are disabled in TLS contexts

[b] CBC ciphers are disabled for SSH

 $\lceil c \rceil$ CBC ciphers are disabled for all protocols except Kerberos

 $\lceil d \rceil$ CBC ciphers are disabled for all protocols except Kerberos

Additional resources

- crypto-policies(7) and update-crypto-policies(8) man pages on your system
- Product compliance (Red Hat Customer Portal)
- Enable SHA-1 signatures in OpenSSL on Red Hat Enterprise Linux 10 (Red Hat Knowledgebase)

2.2. CHANGING THE SYSTEM-WIDE CRYPTOGRAPHIC POLICY

You can change the system-wide cryptographic policy on your system by using the **update-crypto-policies** tool and restarting your system.

Prerequisites

• You have root privileges on the system.

Procedure

1. Optional: Display the current cryptographic policy:

\$ update-crypto-policies --show DEFAULT

2. Set the new cryptographic policy:

update-crypto-policies --set < POLICY> < POLICY>

Replace *POLICY* with the policy or subpolicy you want to set, for example, **FUTURE**, **LEGACY**, or **FIPS:OSPP**.

3. Restart the system:

reboot

Verification

• Display the current cryptographic policy:

\$ update-crypto-policies --show
<POLICY>

Additional resources

For more information on system-wide cryptographic policies, see System-wide cryptographic policies

2.3. SWITCHING THE SYSTEM-WIDE CRYPTOGRAPHIC POLICY TO MODE COMPATIBLE WITH EARLIER RELEASES

The default system-wide cryptographic policy in Red Hat Enterprise Linux 10 does not allow communication using older, insecure protocols. For environments that require to be compatible with Red Hat Enterprise Linux 6 and in some cases also with earlier releases, the less secure **LEGACY** policy level is available.



WARNING

Switching to the **LEGACY** policy level results in a less secure system and applications.

Procedure

 To switch the system-wide cryptographic policy to the **LEGACY** level, enter the following command as **root**:

update-crypto-policies --set LEGACY Setting system policy to LEGACY

Additional resources

• For the list of available cryptographic policy levels, see the **update-crypto-policies(8)** man page.

• For defining custom cryptographic policies, see the **Custom Policies** section in the **update-crypto-policies(8)** man page and the **Crypto Policy Definition Format** section in the **crypto-policies(7)** man page.

2.4. SETTING UP SYSTEM-WIDE CRYPTOGRAPHIC POLICIES IN THE WEB CONSOLE

You can set one of system-wide cryptographic policies and subpolicies directly in the RHEL web console interface. Besides the three predefined system-wide cryptographic policies, you can also apply the following combination of the **LEGACY** policy and the **AD-SUPPORT** subpolicy through the graphical interface:

LEGACY:AD-SUPPORT


The **LEGACY** policy with less secure settings that improve interoperability for Active Directory services.

Prerequisites


- You have installed the RHEL 10 web console.
 For instructions, see Installing and enabling the web console.
- You have **root** privileges or permissions to enter administrative commands with **sudo**.

Procedure

- Log in to the RHEL 10 web console.
 For details, see Logging in to the web console.
- 2. In the **Configuration** card of the **Overview** page, click your current policy value next to **Crypto policy**.



3. In the **Change crypto policy** dialog window, click on the policy you want to start using on your system.



4. Click the **Apply and reboot** button.

Verification

 After the restart, log back in to web console, and check that the Crypto policy value corresponds to the one you selected.

Alternatively, you can enter the **update-crypto-policies --show** command to display the current system-wide cryptographic policy in your terminal.

2.5. EXCLUDING AN APPLICATION FROM FOLLOWING SYSTEM-WIDE CRYPTO POLICIES

You can customize cryptographic settings used by your application preferably by configuring supported cipher suites and protocols directly in the application.

You can also remove a symlink related to your application from the /etc/crypto-policies/back-ends directory and replace it with your customized cryptographic settings. This configuration prevents the use of system-wide cryptographic policies for applications that use the excluded back end. Furthermore, this modification is not supported by Red Hat.

2.5.1. Examples of opting out of system-wide crypto policies

wget

To customize cryptographic settings used by the **wget** network downloader, use **--secure-protocol** and **--ciphers** options. For example:

\$ wget --secure-protocol=TLSv1_1 --ciphers="SECURE128" https://example.com

See the HTTPS (SSL/TLS) Options section of the wget(1) man page for more information.

curl

To specify ciphers used by the **curl** tool, use the **--ciphers** option and provide a colon-separated list of ciphers as a value. For example:

\$ curl https://example.com --ciphers '@SECLEVEL=0:DES-CBC3-SHA:RSA-DES-CBC3-SHA'

See the **curl(1)** man page for more information.

Firefox

Even though you cannot opt out of system-wide cryptographic policies in the **Firefox** web browser, you can further restrict supported ciphers and TLS versions in Firefox's Configuration Editor. Type **about:config** in the address bar and change the value of the **security.tls.version.min** option as required. Setting **security.tls.version.min** to **1** allows TLS 1.0 as the minimum required, **security.tls.version.min 2** enables TLS 1.1, and so on.

OpenSSH

To opt out of the system-wide cryptographic policies for your OpenSSH server, specify the cryptographic policy in a drop-in configuration file located in the /etc/ssh/sshd_config.d/ directory, with a two-digit number prefix smaller than 50, so that it lexicographically precedes the **50-redhat.conf** file, and with a .conf suffix, for example, **49-crypto-policy-override.conf**.

See the **sshd config(5)** man page for more information.

To opt out of system-wide cryptographic policies for your OpenSSH client, perform one of the following tasks:

- For a given user, override the global **ssh_config** with a user-specific configuration in the ~/.**ssh/config** file.
- For the entire system, specify the cryptographic policy in a drop-in configuration file located in the /etc/ssh/ssh_config.d/ directory, with a two-digit number prefix smaller than 50, so that it lexicographically precedes the 50-redhat.conf file, and with a .conf suffix, for example, 49-crypto-policy-override.conf.

See the **ssh** config(5) man page for more information.

Libreswan

See the Configuring IPsec connections that opt out of the system-wide crypto policies in the Securing networks document for detailed information.

Additional resources

• update-crypto-policies(8) man page on your system

2.6. CUSTOMIZING SYSTEM-WIDE CRYPTOGRAPHIC POLICIES WITH SUBPOLICIES

Use this procedure to adjust the set of enabled cryptographic algorithms or protocols.

You can either apply custom subpolicies on top of an existing system-wide cryptographic policy or define such a policy from scratch.

The concept of scoped policies allows enabling different sets of algorithms for different back ends. You can limit each configuration directive to specific protocols, libraries, or services.

Furthermore, directives can use asterisks for specifying multiple values using wildcards.

The /etc/crypto-policies/state/CURRENT.pol file lists all settings in the currently applied system-wide cryptographic policy after wildcard expansion. To make your cryptographic policy more strict, consider using values listed in the /usr/share/crypto-policies/policies/FUTURE.pol file.

You can find example subpolicies in the /usr/share/crypto-policies/policies/modules/ directory. The subpolicy files in this directory contain also descriptions in lines that are commented out.

Procedure

- 1. Checkout to the /etc/crypto-policies/policies/modules/ directory:
 - # cd /etc/crypto-policies/policies/modules/
- 2. Create subpolicies for your adjustments, for example:

touch MYCRYPTO-1.pmod # touch SCOPES-AND-WILDCARDS.pmod



IMPORTANT

Use upper-case letters in file names of policy modules.

3. Open the policy modules in a text editor of your choice and insert options that modify the system-wide cryptographic policy, for example:

vi MYCRYPTO-1.pmod

min_rsa_size = 3072 hash = SHA2-384 SHA2-512 SHA3-384 SHA3-512

vi SCOPES-AND-WILDCARDS.pmod

Disable the AES-128 cipher, all modes cipher = -AES-128-*

Disable CHACHA20-POLY1305 for the TLS protocol (OpenSSL, GnuTLS, NSS, and OpenJDK)

cipher@TLS = -CHACHA20-POLY1305

- # Allow using the FFDHE-1024 group with the SSH protocol (libssh and OpenSSH) group@SSH = FFDHE-1024+
- # Disable all CBC mode ciphers for the SSH protocol (libssh and OpenSSH) cipher@SSH = -*-CBC
- # Allow the AES-256-CBC cipher in applications using libssh cipher@libssh = AES-256-CBC+

- 4. Save the changes in the module files.
- 5. Apply your policy adjustments to the **DEFAULT** system-wide cryptographic policy level:
 - # update-crypto-policies --set DEFAULT: MYCRYPTO-1: SCOPES-AND-WILDCARDS
- 6. To make your cryptographic settings effective for already running services and applications, restart the system:
 - # reboot

Verification

 Check that the /etc/crypto-policies/state/CURRENT.pol file contains your changes, for example:

\$ cat /etc/crypto-policies/state/CURRENT.pol | grep rsa_size min rsa size = 3072

Additional resources

- Custom Policies section in the update-crypto-policies(8) man page
- Crypto Policy Definition Format section in the crypto-policies(7) man page
- How to customize crypto policies in RHEL 8.2 Red Hat blog article

2.7. CREATING AND SETTING A CUSTOM SYSTEM-WIDE CRYPTOGRAPHIC POLICY

For specific scenarios, you can customize the system-wide cryptographic policy by creating and using a complete policy file.

Procedure

1. Create a policy file for your customizations:

cd /etc/crypto-policies/policies/ # touch *MYPOLICY*.pol

Alternatively, start by copying one of the four predefined policy levels:

cp /usr/share/crypto-policies/policies/DEFAULT.pol /etc/crypto-policies/policies/MYPOLICY.pol

- 2. Edit the file with your custom cryptographic policy in a text editor of your choice to fit your requirements, for example:
 - # vi /etc/crypto-policies/policies/MYPOLICY.pol
- 3. Switch the system-wide cryptographic policy to your custom level:

update-crypto-policies --set MYPOLICY

4. To make your cryptographic settings effective for already running services and applications, restart the system:

reboot

Additional resources

- Custom Policies section in the update-crypto-policies(8) man page and the Crypto Policy Definition Format section in the crypto-policies(7) man page on your system
- How to customize crypto policies in RHEL Red Hat blog article

2.8. ENHANCING SECURITY WITH THE FUTURE CRYPTOGRAPHIC POLICY USING THE CRYPTO POLICIES RHEL SYSTEM ROLE

You can use the **crypto_policies** RHEL system role to configure the **FUTURE** policy on your managed nodes. This policy helps to achieve for example:

- Future-proofing against emerging threats: anticipates advancements in computational power.
- Enhanced security: stronger encryption standards require longer key lengths and more secure algorithms.
- Compliance with high-security standards: for example in healthcare, telco, and finance the data sensitivity is high, and availability of strong cryptography is critical.

Typically, **FUTURE** is suitable for environments handling highly sensitive data, preparing for future regulations, or adopting long-term security strategies.



WARNING

Legacy systems or software does not have to support the more modern and stricter algorithms and protocols enforced by the **FUTURE** policy. For example, older systems might not support TLS 1.3 or larger key sizes. This could lead to compatibility problems.

Also, using strong algorithms usually increases the computational workload, which could negatively affect your system performance.

Prerequisites

- You have prepared the control node and the managed nodes
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

 name: Configure cryptographic policies hosts: managed-node-01.example.com tasks:

- name: Configure the FUTURE cryptographic security policy on the managed node ansible.builtin.include_role:

name: rhel-system-roles.crypto_policies

vars:

- crypto_policies_policy: FUTURE- crypto_policies_reboot_ok: true

The settings specified in the example playbook include the following:

crypto_policies_policy: FUTURE

Configures the required cryptographic policy (**FUTURE**) on the managed node. It can be either the base policy or a base policy with some subpolicies. The specified base policy and subpolicies have to be available on the managed node. The default value is **null**. It means that the configuration is not changed and the **crypto_policies** RHEL system role will only collect the Ansible facts.

crypto_policies_reboot_ok: true

Causes the system to reboot after the cryptographic policy change to make sure all of the services and applications will read the new configuration files. The default value is **false**.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.crypto_policies/README.md file on the control node.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml



WARNING

Because the **FIPS:OSPP** system-wide subpolicy contains further restrictions for cryptographic algorithms required by the Common Criteria (CC) certification, the system is less interoperable after you set it. For example, you cannot use RSA and DH keys shorter than 3072 bits, additional SSH algorithms, and several TLS groups. Setting **FIPS:OSPP** also prevents connecting to Red Hat Content Delivery Network (CDN) structure. Furthermore, you cannot integrate Active Directory (AD) into the IdM deployments that use **FIPS:OSPP**, communication between RHEL hosts using **FIPS:OSPP** and AD domains might not work, or some AD accounts might not be able to authenticate.

Note that your **system is not CC-compliant** after you set the **FIPS:OSPP** cryptographic subpolicy. The only correct way to make your RHEL system compliant with the CC standard is by following the guidance provided in the **cc-config** package. See the Common Criteria section on the Product compliance Red Hat Customer Portal page for a list of certified RHEL versions, validation reports, and links to CC guides hosted at the National Information Assurance Partnership (NIAP) website.

Verification

1. On the control node, create another playbook named, for example, **verify_playbook.yml**:

- name: Verification

hosts: managed-node-01.example.com

tasks:

- name: Verify active cryptographic policy

ansible.builtin.include_role:

name: rhel-system-roles.crypto_policies

- name: Display the currently active cryptographic policy ansible.builtin.debug:

var: crypto_policies_active

The settings specified in the example playbook include the following:

crypto_policies_active

An exported Ansible fact that contains the currently active policy name in the format as accepted by the **crypto_policies_policy** variable.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/verify_playbook.yml

3. Run the playbook:

```
$ ansible-playbook ~/verify_playbook.yml
TASK [debug] *******************
ok: [host] => {
```

```
"crypto_policies_active": "FUTURE"
}
```

The **crypto_policies_active** variable shows the active policy on the managed node.

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.crypto_policies/README.md file
- /usr/share/doc/rhel-system-roles/crypto_policies/ directory
- update-crypto-policies(8) and crypto-policies(7) manual pages

CHAPTER 3. CONFIGURING APPLICATIONS TO USE CRYPTOGRAPHIC HARDWARE THROUGH PKCS #11

Separating parts of your secret information about dedicated cryptographic devices, such as smart cards and cryptographic tokens for end-user authentication and hardware security modules (HSM) for server applications, provides an additional layer of security. In Red Hat Enterprise Linux, support for cryptographic hardware through the PKCS #11 API is consistent across different applications, and the isolation of secrets on cryptographic hardware is not a complicated task.

3.1. CRYPTOGRAPHIC HARDWARE SUPPORT THROUGH PKCS #11

Public-Key Cryptography Standard (PKCS) #11 defines an application programming interface (API) to cryptographic devices that hold cryptographic information and perform cryptographic functions.

PKCS #11 introduces the *cryptographic token*, an object that presents each hardware or software device to applications in a unified manner. Therefore, applications view devices such as smart cards, which are typically used by persons, and hardware security modules, which are typically used by computers, as PKCS #11 cryptographic tokens.

A PKCS #11 token can store various object types including a certificate; a data object; and a public, private, or secret key. These objects are uniquely identifiable through the PKCS #11 Uniform Resource Identifier (URI) scheme.

A PKCS #11 URI is a standard way to identify a specific object in a PKCS #11 module according to the object attributes. This enables you to configure all libraries and applications with the same configuration string in the form of a URI.

RHEL provides the OpenSC PKCS #11 driver for smart cards by default. However, hardware tokens and HSMs can have their own PKCS #11 modules that do not have their counterpart in the system. You can register such PKCS #11 modules with the **p11-kit** tool, which acts as a wrapper over the registered smart-card drivers in the system.

To make your own PKCS #11 module work on the system, add a new text file to the /etc/pkcs11/modules/ directory

You can add your own PKCS #11 module into the system by creating a new text file in the /etc/pkcs11/modules/ directory. For example, the OpenSC configuration file in p11-kit looks as follows:

\$ cat /usr/share/p11-kit/modules/opensc.module module: opensc-pkcs11.so

Additional resources

- The PKCS #11 URI Scheme (IETF.org)
- Controlling access to smart cards (Red Hat Blog)

3.2. AUTHENTICATING BY SSH KEYS STORED ON A SMART CARD

You can create and store ECDSA and RSA keys on a smart card and authenticate by the smart card on an OpenSSH client. Smart-card authentication replaces the default password authentication.

Prerequisites

• On the client side, the **opensc** package is installed and the **pcscd** service is running.

Procedure

1. List all keys provided by the OpenSC PKCS #11 module including their PKCS #11 URIs and save the output to the **keys.pub** file:

```
$ ssh-keygen -D pkcs11: > keys.pub
```

2. Transfer the public key to the remote server. Use the **ssh-copy-id** command with the **keys.pub** file created in the previous step:

```
$ ssh-copy-id -f -i keys.pub <username@ssh-server-example.com>
```

3. Connect to *<ssh-server-example.com>* by using the ECDSA key. You can use just a subset of the URI, which uniquely references your key, for example:

```
$ ssh -i "pkcs11:id=%01?module-path=/usr/lib64/pkcs11/opensc-pkcs11.so" <ssh-server-example.com>
Enter PIN for 'SSH key':
[ssh-server-example.com] $
```

Because OpenSSH uses the **p11-kit-proxy** wrapper and the OpenSC PKCS #11 module is registered to the **p11-kit** tool, you can simplify the previous command:

```
$ ssh -i "pkcs11:id=%01" <ssh-server-example.com>
Enter PIN for 'SSH key':
[ssh-server-example.com] $
```

If you skip the **id=** part of a PKCS #11 URI, OpenSSH loads all keys that are available in the proxy module. This can reduce the amount of typing required:

```
$ ssh -i pkcs11: <ssh-server-example.com>
Enter PIN for 'SSH key':
[ssh-server-example.com] $
```

4. Optional: You can use the same URI string in the ~/.ssh/config file to make the configuration permanent:

```
$ cat ~/.ssh/config
IdentityFile "pkcs11:id=%01?module-path=/usr/lib64/pkcs11/opensc-pkcs11.so"
$ ssh <ssh-server-example.com>
Enter PIN for 'SSH key':
[ssh-server-example.com] $
```

The **ssh** client utility now automatically uses this URI and the key from the smart card.

Additional resources

• p11-kit(8), opensc.conf(5), pcscd(8), ssh(1), and ssh-keygen(1) man pages on your system

3.3. CONFIGURING APPLICATIONS FOR AUTHENTICATION WITH CERTIFICATES ON SMART CARDS

Authentication by using smart cards in applications may increase security and simplify automation. You can integrate the Public Key Cryptography Standard (PKCS) #11 URIs into your application by using the following methods:

- The **Firefox** web browser automatically loads the **p11-kit-proxy** PKCS #11 module. This means that every supported smart card in the system is automatically detected. For using TLS client authentication, no additional setup is required and keys and certificates from a smart card are automatically used when a server requests them.
- If your application uses the GnuTLS or NSS library, it already supports PKCS #11 URIs. Also, applications that rely on the OpenSSL library can access cryptographic hardware modules, including smart cards, through the PKCS #11 provider installed by the pkcs11-provider package.
- Applications that require working with private keys on smart cards and that do not use NSS, GnuTLS, nor OpenSSL can use the p11-kit API directly to work with cryptographic hardware modules, including smart cards, rather than using the PKCS #11 API of specific PKCS #11 modules.
- With the the wget network downloader, you can specify PKCS #11 URIs instead of paths to locally stored private keys and certificates. This might simplify creation of scripts for tasks that require safely stored private keys and certificates. For example:

\$ wget --private-key 'pkcs11:token=softhsm;id=%01;type=private?pin-value=111111' -- certificate 'pkcs11:token=softhsm;id=%01;type=cert' https://example.com/

• You can also specify PKCS #11 URI when using the **curl** tool:

\$ curl --key 'pkcs11:token=softhsm;id=%01;type=private?pin-value=111111' --cert 'pkcs11:token=softhsm;id=%01;type=cert' https://example.com/



NOTE

Because a PIN is a security measure that controls access to keys stored on a smart card and the configuration file contains the PIN in the plain-text form, consider additional protection to prevent an attacker from reading the PIN. For example, you can use the **pin-source** attribute and provide a **file:** URI for reading the PIN from a file. See RFC 7512: PKCS #11 URI Scheme Query Attribute Semantics for more information. Note that using a command path as a value of the **pin-source** attribute is not supported.

Additional resources

• curl(1), wget(1), p11-kit(8), and provider-pkcs11(7) man pages on your system

3.4. USING HSMS PROTECTING PRIVATE KEYS IN APACHE

The **Apache** HTTP server can work with private keys stored on hardware security modules (HSMs), which helps to prevent the keys' disclosure and man-in-the-middle attacks. Note that this usually requires high-performance HSMs for busy servers.

For secure communication in the form of the HTTPS protocol, the **Apache** HTTP server (**httpd**) uses the OpenSSL library. OpenSSL does not support PKCS #11 natively. To use HSMs, you must install the **pkcs11-provider** package, which provides access to PKCS #11 modules. You can use a PKCS #11 URI instead of a regular file name to specify a server key and a certificate in the /etc/httpd/conf.d/ssl.conf configuration file, for example:

SSLCertificateFile "pkcs11:id=%01;token=softhsm;type=cert" SSLCertificateKeyFile "pkcs11:id=%01;token=softhsm;type=private?pin-value=111111"

Install the **httpd-manual** package to obtain complete documentation for the **Apache** HTTP Server, including TLS configuration. The directives available in the /etc/httpd/conf.d/ssl.conf configuration file are described in detail in the /usr/share/httpd/manual/mod/mod_ssl.html file.

3.5. ADDITIONAL RESOURCES

• pkcs11.conf(5) man page on your system

CHAPTER 4. CONTROLLING ACCESS TO SMART CARDS BY USING POLKIT

To cover possible threats that cannot be prevented by mechanisms built into smart cards, such as PINs, PIN pads, and biometrics, and for more fine-grained control, Red Hat Enterprise Linux uses the **polkit** framework for controlling access control to smart cards.

System administrators can configure **polkit** to fit specific scenarios, such as smart-card access for non-privileged or non-local users or services.

4.1. SMART-CARD ACCESS CONTROL THROUGH POLKIT

The Personal Computer/Smart Card (PC/SC) protocol specifies a standard for integrating smart cards and their readers into computing systems. In RHEL, the **pcsc-lite** package provides middleware to access smart cards that use the PC/SC API. A part of this package, the **pcscd** (PC/SC Smart Card) daemon, ensures that the system can access a smart card by using the PC/SC protocol.

Because access-control mechanisms built into smart cards, such as PINs, PIN pads, and biometrics, do not cover all possible threats, RHEL uses the **polkit** framework for more robust access control. The **polkit** authorization manager can grant access to privileged operations. In addition to granting access to disks, you can use **polkit** also to specify policies for securing smart cards. For example, you can define which users can perform which operations with a smart card.

After installing the **pcsc-lite** package and starting the **pcscd** daemon, the system enforces policies defined in the /**usr/share/polkit-1/actions/** directory. The default system-wide policy is in the /**usr/share/polkit-1/actions/org.debian.pcsc-lite.policy** file. Polkit policy files use the XML format and the syntax is described in the **polkit(8)** man page.

The **polkitd** service monitors the /etc/polkit-1/rules.d/ and /usr/share/polkit-1/rules.d/ directories for any changes in rule files stored in these directories. The files contain authorization rules in JavaScript format. System administrators can add custom rule files in both directories, and **polkitd** reads them in lexical order based on their file name. If two files have the same names, then the file in /etc/polkit-1/rules.d/ is read first.

Additional resources

• polkit(8), polkitd(8), and pcscd(8) man pages on your system

4.2. TROUBLESHOOTING PROBLEMS RELATED TO PC/SC AND POLKIT

Polkit policies that are automatically enforced after you install the **pcsc-lite** package and start the **pcscd** daemon may ask for authentication in the user's session even if the user does not directly interact with a smart card. In GNOME, you can see the following error message:

Authentication is required to access the PC/SC daemon

Note that the system can install the **pcsc-lite** package as a dependency when you install other packages related to smart cards such as **opensc**.

If your scenario does not require any interaction with smart cards and you want to prevent displaying authorization requests for the PC/SC daemon, you can remove the **pcsc-lite** package. Keeping the minimum of necessary packages is a good security practice anyway.

If you use smart cards, start troubleshooting by checking the rules in the system-provided policy file at /usr/share/polkit-1/actions/org.debian.pcsc-lite.policy. You can add your custom rule files to the policy in the /etc/polkit-1/rules.d/ directory, for example, 03-allow-pcscd.rules. Note that the rule files use the JavaScript syntax, the policy file is in the XML format.

To understand what authorization requests the system displays, check the Journal log, for example:

```
$ journalctl -b | grep pcsc ...
Process 3087 (user: 1001) is NOT authorized for action: access_pcsc ...
```

The previous log entry means that the user is not authorized to perform an action by the policy. You can solve this denial by adding a corresponding rule to /etc/polkit-1/rules.d/.

You can search also for log entries related to the **polkitd** unit, for example:

```
$ journalctl -u polkit ...
polkitd[NNN]: Error compiling script /etc/polkit-1/rules.d/00-debug-pcscd.rules ...
polkitd[NNN]: Operator of unix-session:c2 FAILED to authenticate to gain authorization for action org.debian.pcsc-lite.access_pcsc for unix-process:4800:14441 [/usr/libexec/gsd-smartcard] (owned by unix-user:group) ...
```

In the previous output, the first entry means that the rule file contains some syntax error. The second entry means that the user failed to gain the access to **pcscd**.

You can also list all applications that use the PC/SC protocol by a short script. Create an executable file, for example, **pcsc-apps.sh**, and insert the following code:

```
#!/bin/bash

cd /proc

for p in [0-9]*
do
    if grep libpcsclite.so.1.0.0 $p/maps &> /dev/null
    then
    echo -n "process: "
    cat $p/cmdline
    echo " ($p)"
    fi
    done
```

Run the script as root:

```
# ./pcsc-apps.sh
process: /usr/libexec/gsd-smartcard (3048)
enable-sync --auto-ssl-client-auth --enable-crashpad (4828)
...
```

Additional resources

• journalctl, polkit(8), polkitd(8), and pcscd(8) man pages on your system

4.3. DISPLAYING MORE DETAILED INFORMATION ABOUT POLKIT AUTHORIZATION TO PC/SC

In the default configuration, the **polkit** authorization framework sends only limited information to the Journal log. You can extend **polkit** log entries related to the PC/SC protocol by adding new rules.

Prerequisites

- You have installed the **pcsc-lite** package on your system.
- The **pcscd** daemon is running.

Procedure

- 1. Create a new file in the /etc/polkit-1/rules.d/ directory:
 - # touch /etc/polkit-1/rules.d/00-test.rules
- 2. Edit the file in an editor of your choice, for example:
 - # vi /etc/polkit-1/rules.d/00-test.rules
- 3. Insert the following lines:

```
polkit.addRule(function(action, subject) {
  if (action.id == "org.debian.pcsc-lite.access_pcsc" ||
    action.id == "org.debian.pcsc-lite.access_card") {
  polkit.log("action=" + action);
  polkit.log("subject=" + subject);
  }
});
```

Save the file, and exit the editor.

4. Restart the **pcscd** and **polkit** services:

systemctl restart pcscd.service pcscd.socket polkit.service

Verification

- 1. Make an authorization request for **pcscd**. For example, open the Firefox web browser or use the **pkcs11-tool -L** command provided by the **opensc** package.
- 2. Display the extended log entries, for example:

```
# journalctl -u polkit --since "1 hour ago" polkitd[1224]: <no filename>:4: action=[Action id='org.debian.pcsc-lite.access_pcsc'] polkitd[1224]: <no filename>:5: subject=[Subject pid=2020481 user=user' groups=user,wheel,mock,wireshark seat=null session=null local=true active=true]
```

Additional resources

• polkit(8) and polkitd(8) man pages on your system

4.4. ADDITIONAL RESOURCES

• Controlling access to smart cards (Red Hat Blog)

CHAPTER 5. SCANNING THE SYSTEM FOR CONFIGURATION COMPLIANCE

A compliance audit is a process of determining whether a given object follows all the rules specified in a compliance policy. The compliance policy is defined by security professionals who specify the required settings, often in the form of a checklist, that a computing environment should use.

Compliance policies can vary substantially across organizations and even across different systems within the same organization. Differences among these policies are based on the purpose of each system and its importance for the organization. Custom software settings and deployment characteristics also raise a need for custom policy checklists.

5.1. CONFIGURATION COMPLIANCE TOOLS IN RHEL

You can perform a fully automated compliance audit in Red Hat Enterprise Linux by using the following configuration compliance tools. These tools are based on the Security Content Automation Protocol (SCAP) standard and are designed for automated tailoring of compliance policies.

OpenSCAP

The **OpenSCAP** library, with the accompanying **oscap** command-line utility, is designed to perform configuration and vulnerability scans on a local system, to validate configuration compliance content, and to generate reports and guides based on these scans and evaluations.



IMPORTANT

You can experience memory-consumption problems while using **OpenSCAP**, which can cause stopping the program prematurely and prevent generating any result files. See the OpenSCAP memory-consumption problems Knowledgebase article for details.

SCAP Security Guide (SSG)

The **scap-security-guide** package provides collections of security policies for Linux systems. The guidance consists of a catalog of practical hardening advice, linked to government requirements where applicable. The project bridges the gap between generalized policy requirements and specific implementation guidelines.

Script Check Engine (SCE)

With SCE, which is an extension to the SCAP protocol, administrators can write their security content by using a scripting language, such as Bash, Python, and Ruby. The SCE extension is provided in the **openscap-engine-sce** package. The SCE itself is not part of the SCAP standard.

To perform automated compliance audits on multiple systems remotely, you can use the OpenSCAP solution for Red Hat Satellite.

Additional resources

- oscap(8) and scap-security-guide(8) man pages on your system
- Red Hat Security Demos: Creating Customized Security Policy Content to Automate Security Compliance
- Red Hat Security Demos: Defend Yourself with RHEL Security Technologies

Managing security compliance in Red Hat Satellite

5.2. CONFIGURATION COMPLIANCE SCANNING

5.2.1. Configuration compliance in RHEL

You can use configuration compliance scanning to conform to a baseline defined by a specific organization. For example, if you are a payment processor, you might have to align your systems with the Payment Card Industry Data Security Standard (PCI-DSS). You can also perform configuration compliance scanning to harden your system security.

Red Hat recommends you follow the Security Content Automation Protocol (SCAP) content provided in the SCAP Security Guide package because it is in line with Red Hat best practices for affected components.

The SCAP Security Guide package provides content which conforms to the SCAP 1.2 and SCAP 1.3 standards. The **openscap scanner** utility is compatible with both SCAP 1.2 and SCAP 1.3 content provided in the SCAP Security Guide package.



IMPORTANT

Performing a configuration compliance scanning does not guarantee the system is compliant.

The SCAP Security Guide suite provides profiles for several platforms in a form of data stream documents. A data stream is a file that contains definitions, benchmarks, profiles, and individual rules. Each rule specifies the applicability and requirements for compliance. RHEL provides several profiles for compliance with security policies. In addition to the industry standard, Red Hat data streams also contain information for remediation of failed rules.

Structure of compliance scanning resources

A profile is a set of rules based on a security policy, such as PCI-DSS and Health Insurance Portability and Accountability Act (HIPAA). This enables you to audit the system in an automated way for compliance with security standards.

You can modify (tailor) a profile to customize certain rules, for example, password length.

For more information about profile tailoring, see Customizing a security profile with autotailor.

5.2.2. Possible results of an OpenSCAP scan

Depending on the data stream and profile applied to an OpenSCAP scan, as well as various properties of your system, each rule may produce a specific result. These are the possible results with brief explanations of their meanings:

Pass

The scan did not find any conflicts with this rule.

Fail

The scan found a conflict with this rule.

Not checked

OpenSCAP does not perform an automatic evaluation of this rule. Check whether your system conforms to this rule manually.

Not applicable

This rule does not apply to the current configuration.

Not selected

This rule is not part of the profile. OpenSCAP does not evaluate this rule and does not display these rules in the results.

Error

The scan encountered an error. For additional information, you can enter the **oscap** command with the **--verbose DEVEL** option. File a support case on the Red Hat customer portal or open a ticket in the RHEL project in Red Hat Jira .

Unknown

The scan encountered an unexpected situation. For additional information, you can enter the **oscap** command with the `--verbose DEVEL option. File a support case on the Red Hat customer portal or open a ticket in the RHEL project in Red Hat Jira .

5.2.3. Viewing profiles for configuration compliance

Before you decide to use profiles for scanning or remediation, you can list them and check their detailed descriptions by using the **oscap info** subcommand.

Prerequisites

The openscap-scanner and scap-security-guide packages are installed.

Procedure

1. List all available files with security compliance profiles provided by the SCAP Security Guide project:

\$ Is /usr/share/xml/scap/ssg/content/ssg-rhel9-ds.xml

2. Display detailed information about a selected data stream by using the **oscap info** subcommand. XML files containing data streams are indicated by the **-ds** string in their names. In the **Profiles** section, you can find a list of available profiles and their IDs:

\$ oscap info /usr/share/xml/scap/ssg/content/ssg-rhel10-ds.xml Profiles:

• • •

Title: Australian Cyber Security Centre (ACSC) Essential Eight

Id: xccdf_org.ssgproject.content_profile_e8

Title: Health Insurance Portability and Accountability Act (HIPAA)

Id: xccdf_org.ssgproject.content_profile_hipaa

Title: PCI-DSS v3.2.1 Control Baseline for Red Hat Enterprise Linux 9

Id: xccdf_org.ssgproject.content_profile_pci-dss

. . .

3. Select a profile from the data stream file and display additional details about the selected profile. To do so, use **oscap info** with the **--profile** option followed by the last section of the ID displayed in the output of the previous command. For example, the ID of the HIPPA profile is **xccdf org.ssgproject.content profile hipaa**, and the value for the **--profile** option is **hipaa**:

\$ oscap info --profile hipaa /usr/share/xml/scap/ssg/content/ssg-rhel10-ds.xml

..

Profile

Title: Health Insurance Portability and Accountability Act (HIPAA)

Description: The HIPAA Security Rule establishes U.S. national standards to protect individuals' electronic personal health information that is created, received, used, or maintained by a covered entity.

• • •

Additional resources

- scap-security-guide(8) man page
- OpenSCAP memory consumption problems

5.2.4. Assessing configuration compliance with a specific baseline

You can determine whether your system or a remote system conforms to a specific baseline, and save the results in a report by using the **oscap** command-line tool.

Prerequisites

- The openscap-scanner and scap-security-guide packages are installed.
- You know the ID of the profile within the baseline with which the system should comply. To find the ID, see the Viewing profiles for configuration compliance section.

Procedure

1. Scan the local system for compliance with the selected profile and save the scan results to a file:

\$ oscap xccdf eval --report <scan-report.html> --profile cprofileID>
/usr/share/xml/scap/ssg/content/ssg-rhel10-ds.xml

Replace:

- <scan-report.html> with the file name where oscap saves the scan results.

2. Optional: Scan a remote system for compliance with the selected profile and save the scan results to a file:

\$ oscap-ssh <username>@<hostname> <port> xccdf eval --report <scan-report.html> -- profile profile ID> /usr/share/xml/scap/ssg/content/ssg-rhel10-ds.xml

Replace:

- <username>@<hostname> with the user name and host name of the remote system.
- <port> with the port number through which you can access the remote system.
- <scan-report.html> with the file name where oscap saves the scan results.
- profileID> with the profile ID with which the system should comply, for example, hipaa.

Additional resources

- scap-security-guide(8) man page on your system
- SCAP Security Guide documentation in the /usr/share/doc/scap-security-guide/ directory
- /usr/share/doc/scap-security-guide/guides/ssg-rhel10-guide-index.html [Guide to the Secure Configuration of RHEL 10] installed with the scap-security-guide-doc package
- OpenSCAP memory consumption problems

5.2.5. Assessing security compliance of a container or a container image with a specific baseline

You can assess the compliance of your container or a container image with a specific security baseline, such as Payment Card Industry Data Security Standard (PCI-DSS) and Health Insurance Portability and Accountability Act (HIPAA).

Prerequisites

- The **openscap-utils** and **scap-security-guide** packages are installed.
- You have root access to the system.

Procedure

- 1. Find the ID of a container or a container image:
 - a. To find the ID of a container, enter the **podman ps -a** command.
 - b. To find the ID of a container image, enter the **podman images** command.
- 2. Evaluate the compliance of the container or container image with a profile and save the scan results into a file:

 $\label{eq:content} \mbox{\# oscap-podman $<$ID>$ $xccdf eval --report $<$scan-report.$html> --profile $<$profileID>$ \mbox{/usr/share/xml/scap/ssg/content/ssg-rhel10-ds.xml} \mbox{xml } \mbox{xm

Replace:

- <ID> with the ID of your container or container image
- <scan-report.html> with the file name where oscap saves the scan results
- <profileID> with the profile ID with which the system should comply, for example, hipaa or pci-dss

Verification

- Check the results in a browser of your choice, for example:
 - \$ firefox <scan-report.html> &



NOTE

The rules marked as **notapplicable** apply only to bare-metal and virtualized systems and not to containers or container images.

Additional resources

- oscap-podman(8) and scap-security-guide(8) man pages on your system
- /usr/share/doc/scap-security-guide/ directory

5.3. CONFIGURATION COMPLIANCE REMEDIATION

To automatically align you system with a specific profile, you can perform a remediation. You can remediate the system to align with any profile provided by the SCAP Security Guide.

5.3.1. Remediating the system to align with a specific baseline

You can remediate the RHEL system to align with a specific baseline. You can remediate the system to align with any profile provided by the SCAP Security Guide.



WARNING

If not used carefully, running the system evaluation with the **Remediate** option enabled might render the system non-functional. Red Hat does not provide any automated method to revert changes made by security-hardening remediations. Remediations are supported on RHEL systems in the default configuration. If your system has been altered after the installation, running remediation might not make it compliant with the required security profile.

Prerequisites

• The **scap-security-guide** package is installed.

Procedure

1. Remediate the system by using the **oscap** command with the **--remediate** option:

oscap xccdf eval --profile rhel10-ds.xml

Replace *rofileID* with the profile ID with which the system should comply, for example, **hipaa**.

2. Restart your system.

Verification

1. Evaluate compliance of the system with the profile, and save the scan results to a file:

\$ oscap xccdf eval --report <scan-report.html> --profile cprofileID>
/usr/share/xml/scap/ssg/content/ssg-rhel10-ds.xml

Replace:

- <scan-report.html> with the file name where oscap saves the scan results.
- profileID> with the profile ID with which the system should comply, for example, hipaa.

Additional resources

• scap-security-guide(8) and oscap(8) man pages on your system

5.3.2. Remediating the system to align with a specific baseline by using an SSG Ansible playbook

You can remediate your system to align with a specific baseline by using an Ansible playbook file from the SCAP Security Guide (SSG) project. This example uses the Health Insurance Portability and Accountability Act (HIPAA) profile, but you can remediate to align with any other profile provided by the SCAP Security Guide.



WARNING

If not used carefully, running the system evaluation with the **Remediate** option enabled might render the system non-functional. Red Hat does not provide any automated method to revert changes made by security-hardening remediations. Remediations are supported on RHEL systems in the default configuration. If your system has been altered after the installation, running remediation might not make it compliant with the required security profile.

Prerequisites

- The **scap-security-guide** package is installed.
- The **ansible-core** package is installed. See the Ansible Installation Guide for more information.

Procedure

1. Remediate your system to align with HIPAA by using Ansible:

ansible-playbook -i localhost, -c local /usr/share/scap-security-guide/ansible/rhel10-playbook-hipaa.yml

2. Restart the system.

Verification

1. Evaluate the compliance of the system with the HIPAA profile, and save the scan results to a file:

oscap xccdf eval --profile hipaa --report <scan-report.html> /usr/share/xml/scap/ssg/content/ssg-rhel10-ds.xml

Replace **<scan-report.html>** with the file name where **oscap** saves the scan results.

Additional resources

- scap-security-guide(8) and oscap(8) man pages on your system
- Ansible Documentation

5.3.3. Creating a remediation Ansible playbook to align the system with a specific baseline

You can create an Ansible playbook containing only the remediations that are required to align your system with a specific baseline. This playbook is smaller because it does not cover already satisfied requirements. Creating the playbook does not modify your system in any way, you only prepare a file for later application. This example uses the Health Insurance Portability and Accountability Act (HIPAA) profile.

Prerequisites

• The **scap-security-guide** package is installed.

Procedure

1. Scan the system and save the results:

oscap xccdf eval --profile hipaa --results <hipaa-results.xml>/usr/share/xml/scap/ssg/content/ssg-rhel10-ds.xml

- 2. Find the value of the result ID in the file with the results:
 - # oscap info <hipaa-results.xml>
- 3. Generate an Ansible playbook based on the file generated in step 1:

oscap xccdf generate fix --fix-type ansible --result-id <xcdf_org.openscap_testresult_xccdf_org.ssgproject.content_profile_hipaa> --output <hipaaremediations.yml> <hipaa-results.xml>

4. Review the generated file, which contains the Ansible remediations for rules that failed during the scan performed in step 1. After reviewing this generated file, you can apply it by using the **ansible-playbook** *<hipaa-remediations.yml>* command.

Verification

• In a text editor of your choice, review that the generated **<hipaa-remediations.yml>** file contains rules that failed in the scan performed in step 1.

Additional resources

- scap-security-guide(8) and oscap(8) man pages on your system
- Ansible Documentation

5.4. PERFORMING A HARDENED INSTALLATION OF RHEL WITH KICKSTART

If you need your system to be compliant with a specific security profile, such as DISA STIG, CIS, or ANSSI, you can prepare a Kickstart file that defines the hardened configuration, customize the configuration with a tailoring file, and start an automated installation of the hardened system.

Prerequisites

- The **openscap-scanner** is installed on your system.
- The scap-security-guide package is installed on your system and the package version corresponds to the version of RHEL that you want to install. For more information, see Supported versions of the SCAP Security Guide in RHEL. Using a different version can cause conflicts.



NOTE

If your system has the same version of RHEL as the version you want to install, you can install the **scap-security-guide** package directly.

Procedure

1. Find the ID of the security profile from the data stream file:

\$ oscap info /usr/share/xml/scap/ssg/content/ssg-rhel10-ds.xml Profiles:

. . .

Title: Australian Cyber Security Centre (ACSC) Essential Eight

ld: xccdf org.ssgproject.content profile e8

Title: Health Insurance Portability and Accountability Act (HIPAA)

Id: xccdf_org.ssgproject.content_profile_hipaa

Title: PCI-DSS v3.2.1 Control Baseline for Red Hat Enterprise Linux 10 ld: xccdf_org.ssgproject.content_profile_pci-dss ...

- 2. Optional: If you want to customize your hardening with XCCDF Tailoring file you can use the **autotailor** command provided in the **openscap-utils** package. For more information, see Customizing a security profile with autotailor.
- 3. Generate the kickstart file from the SCAP source data stream:

\$ oscap xccdf generate fix --profile rofile_ID> --output <kickstart_file>.cfg --fix-type
kickstart /usr/share/xml/scap/ssg/content/ssg-rhel10-ds.xml

If you are using a tailoring file, embed the tailoring file into the generated kickstart file by using the **--tailoring-file tailoring.xml** option and your custom profile ID, for example:

\$ oscap xccdf generate fix --tailoring-file tailoring.xml --profile <custom_profile_ID> --output <kickstart_file>.cfg --fix-type kickstart ./ssg-rhel10-ds.xml

4. Review and, if necessary, manually modify the generated **<***kickstart_file>.cfg* to fit the needs of your deployment. Follow the instructions in the comments in the file.



NOTE

Some changes might affect the compliance of the systems installed by the kickstart file. For example, some security policies require defined partitions or specific packages and services.

- 5. Use the kickstart file for your installation. For the installer to use the kickstart, the kickstart can be served through a web server, provided in PXE, or embedded into the ISO image. For detailed steps, see the Installing RHEL fully and semi-automated chapter in the Automatically installing RHEL document.
- 6. After the installation finishes, the system reboots automatically. After the reboot, log in and review the installation SCAP report saved in the /root directory.

Verification

- Scan the system for compliance and save the report in a HTML file for review:
 - With the original profile:

oscap xccdf eval --report report.html --profile cprofile_ID>
/usr/share/xml/scap/ssg/content/ssg-rhel10-ds.xml

• With the tailored profile:

oscap xccdf eval --report report.html --tailoring-file tailoring.xml --profile <custom_profile_ID>/usr/share/xml/scap/ssg/content/ssg-rhel10-ds.xml

5.5. CUSTOMIZING A SECURITY PROFILE WITH AUTOTAILOR

You can customize a security profile to better adjust it to your specific needs, for example, to implement

an internal policy that differs from the official profile. When customizing a profile, you can select additional rules, remove rules that you cover differently, and change parameters of certain rules such as minimum password length. You cannot define new rules when customizing a profile.

By using the **autotailor** utility, you create an XCCDF tailoring file that contains all of the modifications of the original profile. Then, when you are scanning, remediating, or installing a system in accordance to a SCAP profile, you pass this tailoring file to the **oscap** command-line utility.

Prerequisites

- The **openscap-utils** package is installed on your system.
- You know the ID of the profile within the baseline which you want to customize. To find the ID, see the Viewing profiles for configuration compliance section.

Procedure

1. Create a tailoring file for your profile by using the **autotailor** command, for example:

Where:

<customization_options> are the modifications of the profile. Use one or more of the following options:

--select=<ruleID>

Add an existing rule to the profile.

--unselect=<ruleID>

Remove a rule from the profile.

--var-value=<valueID>=<value>

Override a pre-set value. For example, to set var_sshd_max_sessions to 10, use --var-value=var_sshd_max_sessions=10.

- <tailoring.xml> is the file name where autotailor saves the tailoring.
- <custom_profileID> is the profile ID within which the autotailor saves customizations, for example, custom_cis.
- <profileID> is the profile ID with which the system should comply, for example, cis.



NOTE

For all profile, rule, and variable XCCDF IDs you can use either a full namespaced identifier or a shortened ID which **autotailor** automatically augments with the namespace prefix. For example, **cis** is equivalent to

xccdf_org.ssgproject.content_profile_cis.

You can override the default namespace **org.ssgproject.content** by using the **-- id-namespace** option.

2. Optional: Create a tailoring file based on the customizations defined in the JSON Tailoring format:

\$ autotailor --output=<tailoring.xml> --json-tailoring=<json_tailoring.json>

Replace:

• <json_tailoring.json> with the file name with JSON Tailoring definitions.



NOTE

You can mix **--json-tailoring** with **--select**, **--unselect**, and **--var-value** command-line customizations. In that case, command-line customizations have priority over JSON Tailoring.

Additional resources

• autotailor(8) man page on your system

5.6. SCAP SECURITY GUIDE PROFILES SUPPORTED IN RHEL 10

Use only the SCAP content provided in the particular minor release of RHEL. This is because components that participate in hardening are sometimes updated with new capabilities. SCAP content changes to reflect these updates, but it is not always backward compatible.

Table 5.1. SCAP Security Guide profiles supported in RHEL 10.0

Profile name	Profile ID	Policy version
[DRAFT] French National Agency for the Security of Information Systems (ANSSI) BP-028 Enhanced Level	xccdf_org.ssgproject.conten t_profile_anssi_bp28_enhan ced	2.0
[DRAFT] French National Agency for the Security of Information Systems (ANSSI) BP-028 High Level	xccdf_org.ssgproject.conten t_profile_anssi_bp28_high	2.0
[DRAFT] French National Agency for the Security of Information Systems (ANSSI) BP-028 Intermediary Level	xccdf_org.ssgproject.conten t_profile_anssi_bp28_interm ediary	2.0
[DRAFT] French National Agency for the Security of Information Systems (ANSSI) BP-028 Minimal Level	xccdf_org.ssgproject.conten t_profile_anssi_bp28_minim al	2.0
[DRAFT] CIS Red Hat Enterprise Linux 9 Benchmark for Level 2 - Server	xccdf_org.ssgproject.conten t_profile_cis	DRAFT

Profile name	Profile ID	Policy version
[DRAFT] CIS Red Hat Enterprise Linux 9 Benchmark for Level 1 - Server	xccdf_org.ssgproject.conten t_profile_cis_server_l1	DRAFT
[DRAFT] CIS Red Hat Enterprise Linux 9 Benchmark for Level 1 - Workstation	xccdf_org.ssgproject.conten t_profile_cis_workstation_l1	DRAFT
[DRAFT] CIS Red Hat Enterprise Linux 9 Benchmark for Level 2 - Workstation	xccdf_org.ssgproject.conten t_profile_cis_workstation_l2	DRAFT
[DRAFT] Australian Cyber Security Centre (ACSC) Essential Eight	xccdf_org.ssgproject.conten t_profile_e8	not versioned
[DRAFT] Health Insurance Portability and Accountability Act (HIPAA)	xccdf_org.ssgproject.conten t_profile_hipaa	not versioned
[DRAFT] Australian Cyber Security Centre (ACSC) ISM Official - Base	xccdf_org.ssgproject.conten t_profile_ism_o	not versioned
[DRAFT] Australian Cyber Security Centre (ACSC) ISM Official - Secret	xccdf_org.ssgproject.conten t_profile_ism_o_secret	not versioned
[DRAFT] Australian Cyber Security Centre (ACSC) ISM Official - Top Secret	xccdf_org.ssgproject.conten t_profile_ism_o_top_secret	not versioned
[DRAFT] PCI-DSS v3.2.1 Control Baseline for Red Hat Enterprise Linux 9	xccdf_org.ssgproject.conten t_profile_pci-dss	4.0
[DRAFT] The Defense Information Systems Agency Security Technical Implementation Guide (DISA STIG) for Red Hat Enterprise Linux 10	xccdf_org.ssgproject.conten t_profile_stig	DRAFT

Profile name	Profile ID	Policy version
[DRAFT] The Defense Information Systems Agency Security Technical Implementation Guide (DISA STIG) with GUI for Red Hat Enterprise Linux 10	xccdf_org.ssgproject.conten t_profile_stig_gui	DRAFT

5.7. ADDITIONAL RESOURCES

- Supported versions of the SCAP Security Guide in RHEL
- The OpenSCAP project page provides detailed information about the **oscap** utility and other components and projects related to SCAP.
- The SCAP Security Guide (SSG) project page provides the latest security content for Red Hat Enterprise Linux.
- Using OpenSCAP for security compliance and vulnerability scanning A hands-on lab on running tools based on the Security Content Automation Protocol (SCAP) standard for compliance scanning in RHEL.
- Red Hat Security Demos: Creating Customized Security Policy Content to Automate Security
 Compliance A hands-on lab to get initial experience in automating security compliance using
 the tools that are included in RHEL to comply with both industry standard security policies and
 custom security policies. If you want training or access to these lab exercises for your team,
 contact your Red Hat account team for additional details.
- Red Hat Security Demos: Defend Yourself with RHEL Security Technologies A hands-on lab to learn how to implement security at all levels of your RHEL system, using the key security technologies available to you in RHEL, including OpenSCAP. If you want training or access to these lab exercises for your team, contact your Red Hat account team for additional details.
- National Institute of Standards and Technology (NIST) SCAP page has a vast collection of SCAP-related materials, including SCAP publications, specifications, and the SCAP Validation Program.
- Managing security compliance in Red Hat Satellite This set of guides describes, among other topics, how to maintain system security on multiple systems by using OpenSCAP.

CHAPTER 6. ENSURING SYSTEM INTEGRITY WITH KEYLIME

With Keylime, you can continuously monitor the integrity of remote systems and verify the state of systems at boot. You can also send encrypted files to the monitored systems, and specify automated actions triggered whenever a monitored system fails the integrity test.

6.1. HOW KEYLIME WORKS

You can configure Keylime agents to perform one or more of the following actions:

Runtime integrity monitoring

Keylime runtime integrity monitoring continuously monitors the system on which the agent is deployed and measures the integrity of the files included in the allowlist and not included in the excludelist.

Measured boot

Keylime measured boot verifies the system state at boot.

Keylime's concept of trust is based on the Trusted Platform Module (TPM) technology. A TPM is a hardware, firmware, or virtual component with integrated cryptographic keys. By polling TPM quotes and comparing the hashes of objects, Keylime provides initial and runtime monitoring of remote systems.



IMPORTANT

Keylime running in a virtual machine or using a virtual TPM depends upon the integrity of the underlying host. Ensure you trust the host environment before relying upon Keylime measurements in a virtual environment.

Keylime consists of three main components:

Verifier

Initially and continuously verifies the integrity of the systems that run the agent. You can deploy the verifier from a package, as a container, or by usign the **keylime_server** RHEL system role.

Registrar

Contains a database of all agents and it hosts the public keys of the TPM vendors. You can deploy the registrar from a package, as a container, or by usign the **keylime_server** RHEL system role.

Agent

Deployed to remote systems measured by the verifier.

In addition, Keylime uses the **keylime_tenant** utility for many functions, including provisioning the agents on the target systems.

Agent

Provision

Tenant

ip, port

Verifier

Registrar

database_url

Verifier database

Registrar database

Figure 6.1. Connections between Keylime components through configurations

379_RHEL_0923

Keylime ensures the integrity of the monitored systems in a chain of trust by using keys and certificates exchanged between the components and the tenant. For a secure foundation of this chain, use a certificate authority (CA) that you can trust.



NOTE

If the agent receives no key and certificate, it generates a key and a self-signed certificate with no involvement from the CA.

→ TLS connection Agent ---- Plain text connection (not encrypted) server_key (optional) ---- TLS connection using agent certificate obtained from the registrar server_cert (optional) trusted_client_ca Path to the verifier client CA certificate Verifier Registrar Path to the tenant client server_key server_key server_cert server_cert client_key trusted_client_ca client_cert Path to the verifier client CA certificate trusted_client_ca Path to the tenant client Path to the tenant client CA certificate trusted_server_ca Tenant Path to the registrar server client_key CA certificate client_cert trusted_server_ca Path to the verifier server CA certificate Path to the registrar server CA certificate

Figure 6.2. Connections between Keylime components certificates and keys

6.2. CONFIGURING KEYLIME VERIFIER

The verifier is the most important component in Keylime. It performs initial and periodic checks of system integrity and supports bootstrapping a cryptographic key securely with the agent. The verifier uses mutual TLS encryption for its control interface.



IMPORTANT

To maintain the chain of trust, keep the system that runs the verifier secure and under your control.

You can install the verifier on a separate system or on the same system as the Keylime registrar, depending on your requirements. Running the verifier and registrar on separate systems provides better performance.



NOTE

To keep the configuration files organized within the drop-in directories, use file names with a two-digit number prefix, for example /etc/keylime/verifier.conf.d/00-verifier-ip.conf. The configuration processing reads the files inside the drop-in directory in lexicographic order and sets each option to the last value it reads.

Prerequisites

- You have **root** permissions and network connection to the system or systems on which you want to install Keylime components.
- You have valid keys and certificates from your certificate authority.
- Optional: You have access to the databases where Keylime saves data from the verifier. You can use any of the following database management systems:
 - SQLite (default)
 - PostgreSQL
 - MySQL
 - MariaDB

Procedure

- 1. Install the Keylime verifier:
 - # dnf install keylime-verifier
- Define the IP address and port of verifier by creating a new .conf file in the /etc/keylime/verifier.conf.d/ directory, for example, /etc/keylime/verifier.conf.d/00-verifier-ip.conf, with the following content:

```
[verifier]
ip = <verifier_IP_address>
```

- Replace <*verifier_IP_address*> with the verifier's IP address. Alternatively, use ip = * or ip = 0.0.0.0 to bind the verifier to all available IP addresses.
- Optionally, you can also change the verifier's port from the default value 8881 by using the port option.
- 3. Optional: Configure the verifier's database for the list of agents. The default configuration uses an SQLite database in the verifier's /var/lib/keylime/cv_data.sqlite/ directory. You can define a different database by creating a new .conf file in the /etc/keylime/verifier.conf.d/ directory, for example, /etc/keylime/verifier.conf.d/00-db-url.conf, with the following content:

```
[verifier] database_url = cprotocol>://<name>:<password>@<ip_address_or_hostname>/cproperties>
```

Replace replace cor_hostname>/c

Ensure that the credentials you use provide the permissions for Keylime to create the database structure.

- 4. Add certificates and keys to the verifier. You can either let Keylime generate them, or use existing keys and certificates:
 - With the default **tls_dir = generate** option, Keylime generates new certificates for the verifier, registrar, and tenant in the /var/lib/keylime/cv_ca/ directory.
 - To load existing keys and certificates in the configuration, define their location in the verifier configuration. The certificates must be accessible by the **keylime** user, under which the Keylime services are running.

Create a new .conf file in the /etc/keylime/verifier.conf.d/ directory, for example, /etc/keylime/verifier.conf.d/00-keys-and-certs.conf, with the following content:

```
[verifier]

tls_dir = /var/lib/keylime/cv_ca

server_key = </path/to/server_key>
server_key_password = <passphrase1>
server_cert = </path/to/server_cert>
trusted_client_ca = ['</path/to/ca/cert1>', '</path/to/ca/cert2>']
client_key = </path/to/client_key>
client_key_password = <passphrase2>
client_cert = </path/to/client_cert>
trusted_server_ca = ['</path/to/ca/cert3>', '</path/to/ca/cert4>']
```



NOTE

Use absolute paths to define key and certificate locations. Alternatively, relative paths are resolved from the directory defined in the **tls_dir** option.

5. Open the port in firewall:

```
# firewall-cmd --add-port 8881/tcp
# firewall-cmd --runtime-to-permanent
```

If you use a different port, replace **8881** with the port number defined in the .conf file.

6. Start the verifier service:

systemctl enable --now keylime_verifier



NOTE

In the default configuration, start the **keylime_verifier** before starting the **keylime_registrar** service because the verifier creates the CA and certificates for the other Keylime components. This order is not necessary when you use custom certificates.

Verification

Check that the keylime_verifier service is active and running:

systemctl status keylime_verifier

keylime_verifier.service - The Keylime verifier
 Loaded: loaded (/usr/lib/systemd/system/keylime_verifier.service; disabled; vendor preset: disabled)

Active: active (running) since Wed 2022-11-09 10:10:08 EST; 1min 45s ago

Next steps

• Section 6.4, "Deploying Keylime registrar from a package" .

6.3. DEPLOYING KEYLIME VERIFIER AS A CONTAINER

The Keylime verifier performs initial and periodic checks of system integrity and supports bootstrapping a cryptographic key securely with the agent. You can configure the Keylime verifier as a container instead of the RPM method, without any binaries or packages on the host. The container deployment provides better isolation, modularity, and reproducibility of Keylime components.

After you start the container, the Keylime verifier is deployed with default configuration files. You can customize the configuration by using one or more of following methods:

- Mounting the host's directories that contain the configuration files to the container.
- Modifying the environment variables directly on the container. Modifying the environment variables overrides the values from the configuration files.

Prerequisites

- The **podman** package and its dependencies are installed on the system.
- Optional: You have access to a database where Keylime saves data from the verifier. You can use any of the following database management systems:
 - SQLite (default)
 - PostgreSQL
 - MySQL
 - MariaDB
- You have valid keys and certificates from your certificate authority.

Procedure

- 1. Optional: Install the **keylime-verifier** package to access the configuration files. You can configure the container without this package, but it might be easier to modify the configuration files provided with the package.
 - # dnf install keylime-verifier
- Bind the verifier to all available IP addresses by creating a new .conf file in the /etc/keylime/verifier.conf.d/ directory, for example, /etc/keylime/verifier.conf.d/00-verifier-ip.conf, with the following content:

```
[verifier]
ip = *
```

- Optionally, you can also change the verifier's port from the default value 8881 by using the port option.
- 3. Optional: Configure the verifier's database for the list of agents. The default configuration uses an SQLite database in the verifier's /var/lib/keylime/cv_data.sqlite/ directory. You can define a different database by creating a new .conf file in the /etc/keylime/verifier.conf.d/ directory, for example, /etc/keylime/verifier.conf.d/00-db-url.conf, with the following content:

```
[verifier] database_url = cprotocol>://<name>:<password>@<ip_address_or_hostname>/cproperties>
```

Replace cprotocol>://<name>:<password>@<ip_address_or_hostname>//cproperties> with
the URL of the database, for example, postgresql://verifier:UQ?
nRNY9g7GZzN7@198.51.100.1/verifierdb.

Ensure that the credentials you use have the permissions for Keylime to create the database structure.

- 4. Add certificates and keys to the verifier. You can either let Keylime generate them, or use existing keys and certificates:
 - With the default **tls_dir = generate** option, Keylime generates new certificates for the verifier, registrar, and tenant in the /var/lib/keylime/cv_ca/ directory.
 - To load existing keys and certificates in the configuration, define their location in the
 verifier configuration. The certificates must be accessible by the **keylime** user, under which
 the Keylime processes are running.

Create a new .conf file in the /etc/keylime/verifier.conf.d/ directory, for example, /etc/keylime/verifier.conf.d/00-keys-and-certs.conf, with the following content:

```
[verifier]

tls_dir = /var/lib/keylime/cv_ca

server_key = </path/to/server_key>
server_cert = </path/to/server_cert>

trusted_client_ca = ['</path/to/ca/cert1>', '</path/to/ca/cert2>']
client_key = </path/to/client_key>
client_cert = </path/to/client_cert>
trusted_server_ca = ['</path/to/ca/cert3>', '</path/to/ca/cert4>']
```



NOTE

Use absolute paths to define key and certificate locations. Alternatively, relative paths are resolved from the directory defined in the **tls_dir** option.

5. Open the port in firewall:

```
# firewall-cmd --add-port 8881/tcp
# firewall-cmd --runtime-to-permanent
```

If you use a different port, replace 8881 with the port number defined in the .conf file.

6. Run the container:

\$ podman run --name keylime-verifier \

- -p 8881:8881 \
- -v /etc/keylime/verifier.conf.d:/etc/keylime/verifier.conf.d:Z \
- -v /var/lib/keylime/cv_ca:/var/lib/keylime/cv_ca:Z \
- -d \
- -e KEYLIME VERIFIER SERVER KEY PASSWORD=<passphrase1>\
- -e KEYLIME_VERIFIER_CLIENT_KEY_PASSWORD=<passphrase2> \
 registry.access.redhat.com/rhel9/keylime-verifier
- The **-p** option opens the default port **8881** on the host and on the container.
- The **-v** option creates a bind mount for the directory to the container.
 - With the **Z** option, Podman marks the content with a private unshared label. This means only the current container can use the private volume.
- The **-d** option runs the container detached and in the background.
- The option -e KEYLIME_VERIFIER_SERVER_KEY_PASSWORD=rasephrase1>
 defines the server key passphrase.
- The option -e KEYLIME_VERIFIER_CLIENT_KEY_PASSWORD=cpassphrase2> defines the client key passphrase.
- You can override configuration options with environment variables by using the option -e
 KEYLIME_VERIFIER_<ENVIRONMENT_VARIABLE>=<value>. To modify additional
 options, insert the -e option separately for each environment variable. For a complete list of
 environment variables and their default values, see Keylime environment variables.

Verification

• Check that the container is running:

\$ podman ps -a

CONTAINER ID IMAGE

STATUS PORTS NAMES

80b6b9dbf57c registry.access.redhat.com/rhel9/keylime-verifier:latest keylime_verifier 14
seconds ago Up 14 seconds 0.0.0.0:8881->8881/tcp keylime-verifier

Next steps

• podman-run(1) man page on your system

6.4. DEPLOYING KEYLIME REGISTRAR FROM A PACKAGE

The registrar is the Keylime component that contains a database of all agents, and it hosts the public keys of the TPM vendors. After the registrar's HTTPS service accepts trusted platform module (TPM) public keys, it presents an interface to obtain these public keys for checking quotes.



IMPORTANT

To maintain the chain of trust, keep the system that runs the registrar secure and under your control.

You can install the registrar on a separate system or on the same system as the Keylime verifier, depending on your requirements. Running the verifier and registrar on separate systems provides better performance.



NOTE

To keep the configuration files organized within the drop-in directories, use file names with a two-digit number prefix, for example /etc/keylime/registrar.conf.d/00-registrar-ip.conf. The configuration processing reads the files inside the drop-in directory in lexicographic order and sets each option to the last value it reads.

Prerequisites

- You have network access to the systems where the Keylime verifier is installed and running. For more information, see
- You have **root** permissions and network connection to the system or systems on which you want to install Keylime components.
- You have access to the database where Keylime saves data from the registrar. You can use any of the following database management systems:
 - SQLite (default)
 - PostgreSQL
 - MySQL
 - MariaDB
- You have valid keys and certificates from your certificate authority.

Procedure

1. Install the Keylime registrar:

dnf install keylime-registrar

2. Define the IP address and port of the registrar by creating a new .conf file in the /etc/keylime/registrar.conf.d/ directory, for example, /etc/keylime/registrar.conf.d/00-registrar-ip.conf, with the following content:

```
[registrar]
ip = <registrar_IP_address>
```

- Replace <registrar_IP_address> with the registrar's IP address. Alternatively, use ip = * or ip = 0.0.0.0 to bind the registrar to all available IP addresses.
- Optionally, change the port to which the Keylime agents connect by using the **port** option. The default value is **8890**.
- Optionally, change the TLS port to which the Keylime verifier and tenant connect by using the **tls_port** option. The default value is **8891**.
- 3. Optional: Configure the registrar's database for the list of agents. The default configuration uses an SQLite database in the registrar's /var/lib/keylime/reg_data.sqlite directory. You can

create a new .conf file in the /etc/keylime/registrar.conf.d/ directory, for example, /etc/keylime/registrar.conf.d/00-db-url.conf, with the following content:

```
[registrar] database_url = cprotocol>://<name>:<password>@<ip_address_or_hostname>/cproperties>
```

Replace content c

Ensure that the credentials you use have the permissions for Keylime to create the database structure.

- 4. Add certificates and keys to the registrar:
 - You can use the default configuration and load the keys and certificates to the /var/lib/keylime/reg_ca/ directory.
 - Alternatively, you can define the location of the keys and certificates in the configuration.
 Create a new .conf file in the /etc/keylime/registrar.conf.d/ directory, for example, /etc/keylime/registrar.conf.d/00-keys-and-certs.conf, with the following content:

```
[registrar]
tls_dir = /var/lib/keylime/reg_ca
server_key = </path/to/server_key>
server_key_password = <passphrase1>
server_cert = </path/to/server_cert>
trusted_client_ca = ['</path/to/ca/cert1>', '</path/to/ca/cert2>']
```



NOTE

Use absolute paths to define key and certificate locations. Alternatively, you can define a directory in the **tls_dir** option and use paths relative to that directory.

5. Open the ports in firewall:

```
# firewall-cmd --add-port 8890/tcp --add-port 8891/tcp # firewall-cmd --runtime-to-permanent
```

If you use a different port, replace 8890 or 8891 with the port number defined in the .conf file.

6. Start the **keylime_registrar** service:

systemctl enable --now keylime_registrar



NOTE

In the default configuration, start the **keylime_verifier** before starting the **keylime_registrar** service because the verifier creates the CA and certificates for the other Keylime components. This order is not necessary when you use custom certificates.

Verification

Check that the keylime_registrar service is active and running:

systemctl status keylime_registrar
 keylime_registrar.service - The Keylime registrar service
 Loaded: loaded (/usr/lib/systemd/system/keylime_registrar.service; disabled; vendor preset: disabled)
 Active: active (running) since Wed 2022-11-09 10:10:17 EST; 1min 42s ago

Next steps

• Deploying Keylime tenant from a package

6.5. DEPLOYING KEYLIME REGISTRAR AS A CONTAINER

The registrar is the Keylime component that contains a database of all agents, and it hosts the public keys of the trusted platform module (TPM) vendors. After the registrar's HTTPS service accepts TPM public keys, it presents an interface to obtain these public keys for checking quotes. You can configure the Keylime registrar as a container instead of the RPM method, without any binaries or packages on the host. The container deployment provides better isolation, modularity, and reproducibility of Keylime components.

After you start the container, the Keylime registrar is deployed with default configuration files. You can customize the configuration by using one or more of following methods:

- Mounting the host's directories that contain the configuration files to the container. This is available in all versions of RHEL 9.
- Modifying the environment variables directly on the container. This is available in RHEL 9.3 and later versions. Modifying the environment variables overrides the values from the configuration files.

Prerequisites

- The **podman** package and its dependencies are installed on the system.
- Optional: You have access to a database where Keylime saves data from the registrar. You can use any of the following database management systems:
 - SQLite (default)
 - PostgreSQL
 - MySQL
 - MariaDB
- You have valid keys and certificates from your certificate authority.

Procedure

1. Optional: Install the **keylime-registrar** package to access the configuration files. You can configure the container without this package, but it might be easier to modify the configuration files provided with the package.

dnf install keylime-registrar

 Bind the registrar to all available IP addresses by creating a new .conf file in the /etc/keylime/registrar.conf.d/ directory, for example, /etc/keylime/registrar.conf.d/00-registrar-ip.conf, with the following content:

```
[registrar]
ip = *
```

- Optionally, change the port to which the Keylime agents connect by using the **port** option. The default value is **8890**.
- Optionally, change the TLS port to which the Keylime tenant connects by using the **tls_port** option. The default value is **8891**.
- 3. Optional: Configure the registrar's database for the list of agents. The default configuration uses an SQLite database in the registrar's /var/lib/keylime/reg_data.sqlite directory. You can create a new .conf file in the /etc/keylime/registrar.conf.d/ directory, for example, /etc/keylime/registrar.conf.d/00-db-url.conf, with the following content:

```
[registrar] database_url = cprotocol>://<name>:<password>@<ip_address_or_hostname>/cproperties>
```

Replace replace con_hostnamerepressible with
the URL of the database, for example, postgresql://registrar:EKYYX-bqY2?
#raXm@198.51.100.1/registrardb.

Ensure that the credentials you use have the permissions for Keylime to create the database structure.

- 4. Add certificates and keys to the registrar:
 - You can use the default configuration and load the keys and certificates to the /var/lib/keylime/reg_ca/ directory.
 - Alternatively, you can define the location of the keys and certificates in the configuration.
 Create a new .conf file in the /etc/keylime/registrar.conf.d/ directory, for example, /etc/keylime/registrar.conf.d/00-keys-and-certs.conf, with the following content:

```
[registrar]
tls_dir = /var/lib/keylime/reg_ca
server_key = </path/to/server_key>
server_cert = </path/to/server_cert>
trusted_client_ca = ['</path/to/ca/cert1>', '</path/to/ca/cert2>']
```



NOTE

Use absolute paths to define key and certificate locations. Alternatively, you can define a directory in the **tls_dir** option and use paths relative to that directory.

5. Open the ports in firewall:

```
# firewall-cmd --add-port 8890/tcp --add-port 8891/tcp # firewall-cmd --runtime-to-permanent
```

If you use a different port, replace 8890 or 8891 with the port number defined in the .conf file.

6. Run the container:

```
$ podman run --name keylime-registrar \
    -p 8890:8890 \
    -p 8891:8891 \
    -v /etc/keylime/registrar.conf.d:/etc/keylime/registrar.conf.d:Z \
    -v /var/lib/keylime/reg_ca:/var/lib/keylime/reg_ca:Z \
    -d \
    -e KEYLIME_REGISTRAR_SERVER_KEY_PASSWORD=passphrase1> \
    registry.access.redhat.com/rhel9/keylime-registrar
```

- The **-p** option opens the default ports **8890** and **8881** on the host and on the container.
- The **-v** option creates a bind mount for the directory to the container.
 - With the **Z** option, Podman marks the content with a private unshared label. This means only the current container can use the private volume.
- The **-d** option runs the container detached and in the background.
- The option -e KEYLIME_VERIFIER_SERVER_KEY_PASSWORD=rasephrase1>
 defines the server key passphrase.
- You can override configuration options with environment variables by using the option -e
 KEYLIME_REGISTRAR__<
 ENVIRONMENT_VARIABLE>=<
 value>
 . To modify additional
 options, insert the -e option separately for each environment variable. For a complete list of
 environment variables and their default values, see

Verification

• Check that the container is running:

```
$ podman ps -a

CONTAINER ID IMAGE COMMAND CREATED STATUS

PORTS NAMES

07d4b4bff1b6 localhost/keylime-registrar:latest keylime_registrar 12 seconds ago Up 12 seconds 0.0.0.0:8881->8881/tcp, 0.0.0.0:8891->8891/tcp keylime-registrar
```

Next steps

• For more information about the **podman run** command, see the **podman-run(1)** man page.

6.6. DEPLOYING A KEYLIME SERVER BY USING RHEL SYSTEM ROLES

You can set up the verifier and registrar, which are the Keylime server components, by using the **keylime_server** RHEL system role. The **keylime_server** role installs and configures both the verifier and registrar components together on each node.

Perform this procedure on the Ansible control node.

For more information about Keylime, see 8.1. How Keylime works.

Prerequisites

- You have prepared the control node and the managed nodes
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- The managed nodes or groups of managed nodes on which you want to run this playbook are listed in the Ansible inventory file.

Procedure

- 1. Create a playbook that defines the required role:
 - a. Create a new YAML file and open it in a text editor, for example:
 - # vi keylime-playbook.yml
 - b. Insert the following content:

```
- name: Manage keylime servers
hosts: all
vars:
  keylime_server_verifier_ip: "{{ ansible_host }}"
  keylime_server_registrar_ip: "{{ ansible_host }}"
  keylime_server_verifier_tls_dir: <ver_tls_directory>
  keylime_server_verifier_server_cert: <ver_server_certfile>
  keylime server verifier server key: <ver server key>
  keylime_server_verifier_server_key_passphrase: <ver_server_key_passphrase>
  keylime_server_verifier_trusted_client_ca: <ver_trusted_client_ca_list>
  keylime server verifier client cert: <ver client certfile>
  keylime_server_verifier_client_key: <ver_client_key>
  keylime server verifier client key passphrase: <ver client key passphrase>
  keylime_server_verifier_trusted_server_ca: <ver_trusted_server_ca_list>
  keylime_server_registrar_tls_dir: <reg_tls_directory>
  keylime_server_registrar_server_cert: <reg_server_certfile>
  keylime_server_registrar_server_key: <reg_server_key>
  keylime_server_registrar_server_key_passphrase: <reg_server_key_passphrase>
  keylime_server_registrar_trusted_client_ca: <reg_trusted_client_ca_list>
 roles:
  - rhel-system-roles.keylime_server
```

You can find out more about the variables in Variables for the keylime_server RHEL system role.

2. Run the playbook:

\$ ansible-playbook < keylime-playbook.yml>

Verification

1. Check that the **keylime_verifier** service is active and running on the managed host:

systemctl status keylime verifier

• keylime_verifier.service - The Keylime verifier

Loaded: loaded (/usr/lib/systemd/system/keylime_verifier.service; disabled; vendor preset: disabled)

Active: active (running) since Wed 2022-11-09 10:10:08 EST; 1min 45s ago

2. Check that the **keylime_registrar** service is active and running:

systemctl status keylime_registrar

• keylime_registrar.service - The Keylime registrar service

Loaded: loaded (/usr/lib/systemd/system/keylime_registrar.service; disabled; vendor preset: disabled)

Active: active (running) since Wed 2022-11-09 10:10:17 EST; 1min 42s ago

Next steps

Deploying Keylime tenant from a package

6.7. VARIABLES FOR THE KEYLIME_SERVER RHEL SYSTEM ROLE

When setting up a Keylime server by using the **keylime_server** RHEL system role, you can customize the following variables for registrar and verifier.

List of keylime_server RHEL system role variables for configuring the Keylime verifier

keylime_server_verifier_ip

Defines the IP address of the verifier.

keylime_server_verifier_tls_dir

Specifies the directory where the keys and certificates are stored. If set to default, the verifier uses the /var/lib/keylime/cv_ca directory.

keylime_server_verifier_server_key_passphrase

Specifies a passphrase to decrypt the server private key. If the value is empty, the private key is not encrypted.

keylime server verifier server cert: Specifies the Keylime verifier server certificate file.

keylime_server_verifier_trusted_client_ca

Defines the list of trusted client CA certificates. You must store the files in the directory set in the **keylime_server_verifier_tls_dir** option.

keylime server verifier client key

Defines the file containing the Keylime verifier private client key.

keylime_server_verifier_client_key_passphrase

Defines the passphrase to decrypt the client private key file. If the value is empty, the private key is not encrypted.

keylime_server_verifier_client_cert

Defines the Keylime verifier client certificate file.

keylime_server_verifier_trusted_server_ca

Defines the list of trusted server CA certificates. You must store the files in the directory set in the **keylime_server_verifier_tls_dir** option.

List of registrar variables for setting up keylime_server RHEL system role

keylime_server_registrar_ip

Defines the IP address of the registrar.

keylime server registrar tls dir

Specifies the directory where you store the keys and certificates for the registrar. If you set it to default, the registrar uses the /var/lib/keylime/reg_ca directory.

keylime_server_registrar_server_key

Defines the Keylime registrar private server key file.

keylime_server_registrar_server_key_passphrase

Specifies the passphrase to decrypt the server private key of the registrar. If the value is empty, the private key is not encrypted.

keylime_server_registrar_server_cert

Specifies the Keylime registrar server certificate file.

keylime_server_registrar_trusted_client_ca

Defines the list of trusted client CA certificates. You must store the files in the directory set in the **keylime_server_registrar_tls_dir** option.

6.8. DEPLOYING KEYLIME TENANT FROM A PACKAGE

Keylime uses the **keylime_tenant** utility for many functions, including provisioning the agents on the target systems. You can install **keylime_tenant** on any system, including the systems that run other Keylime components, or on a separate system, depending on your requirements.

Prerequisites

- You have **root** permissions and network connection to the system or systems on which you want to install Keylime components.
- You have network access to the systems where the other Keylime components are configured:

Verifier

For more information, see

Procedure

1. Install the Keylime tenant:

dnf install keylime-tenant

2. Define the tenant's connection to the Keylime verifier by editing the /etc/keylime/tenant.conf.d/00-verifier-ip.conf file:

```
[tenant]
verifier_ip = <verifier_ip>
```

- Replace **<verifier_ip>** with the IP address to the verifier's system.
- If the verifier uses a different port than the default value **8881**, add the **verifier_port =** <**verifier_port>** setting.
- 3. Define the tenant's connection to the Keylime registrar by editing the /etc/keylime/tenant.conf.d/00-registrar-ip.conf file:

```
[tenant]
registrar_ip = <registrar_ip>
```

- Replace < registrar_ip> with the IP address to the registrar's system.
- If the registrar uses a different port than the default value **8891**, add the **registrar_port =** <**registrar_port>** setting.
- 4. Add certificates and keys to the tenant:
 - a. You can use the default configuration and load the keys and certificates to the /var/lib/keylime/cv_ca directory.
 - Alternatively, you can define the location of the keys and certificates in the configuration.
 Create a new .conf file in the /etc/keylime/tenant.conf.d/ directory, for example, /etc/keylime/tenant.conf.d/00-keys-and-certs.conf, with the following content:

```
[tenant]

tls_dir = /var/lib/keylime/cv_ca

client_key = tenant-key.pem

client_key_password = <passphrase1>

client_cert = tenant-cert.pem

trusted_server_ca = ['</path/to/ca/cert>']
```

The **trusted_server_ca** parameter accepts paths to the verifier and registrar server CA certificate. You can provide multiple comma-separated paths, for example if the verifier and registrar use different CAs.



NOTE

Use absolute paths to define key and certificate locations. Alternatively, you can define a directory in the **tls_dir** option and use paths relative to that directory.

5. Optional: If the trusted platform module (TPM) endorsement key (EK) cannot be verified by using certificates in the /var/lib/keylime/tpm_cert_store directory, add the certificate to that directory. This can occur particularly when using virtual machines with emulated TPMs.

Verification

1. Check the status of the verifier:

```
# keylime_tenant -c cvstatus
Reading configuration from ['/etc/keylime/logging.conf']
2022-10-14 12:56:08.155 - keylime.tpm - INFO - TPM2-TOOLS Version: 5.2
Reading configuration from ['/etc/keylime/tenant.conf']
2022-10-14 12:56:08.157 - keylime.tenant - INFO - Setting up client TLS...
```

```
2022-10-14 12:56:08.158 - keylime.tenant - INFO - Using default client_cert option for tenant 2022-10-14 12:56:08.158 - keylime.tenant - INFO - Using default client_key option for tenant 2022-10-14 12:56:08.178 - keylime.tenant - INFO - TLS is enabled. 2022-10-14 12:56:08.178 - keylime.tenant - WARNING - Using default UUID d432fbb3-d2f1-4a97-9ef7-75bd81c00000 2022-10-14 12:56:08.221 - keylime.tenant - INFO - Verifier at 127.0.0.1 with Port 8881 does not have agent d432fbb3-d2f1-4a97-9ef7-75bd81c00000.
```

If correctly set up, and if no agent is configured, the verifier responds that it does not recognize the default agent UUID.

2. Check the status of the registrar:

```
# keylime_tenant -c regstatus
Reading configuration from ['/etc/keylime/logging.conf']
2022-10-14 12:56:02.114 - keylime.tpm - INFO - TPM2-TOOLS Version: 5.2
Reading configuration from ['/etc/keylime/tenant.conf']
2022-10-14 12:56:02.116 - keylime.tenant - INFO - Setting up client TLS...
2022-10-14 12:56:02.116 - keylime.tenant - INFO - Using default client cert option for tenant
2022-10-14 12:56:02.116 - keylime.tenant - INFO - Using default client key option for tenant
2022-10-14 12:56:02.137 - keylime.tenant - INFO - TLS is enabled.
2022-10-14 12:56:02.137 - keylime.tenant - WARNING - Using default UUID d432fbb3-d2f1-
4a97-9ef7-75bd81c00000
2022-10-14 12:56:02.171 - keylime.registrar client - CRITICAL - Error: could not get agent
d432fbb3-d2f1-4a97-9ef7-75bd81c00000 data from Registrar Server: 404
2022-10-14 12:56:02.172 - keylime.registrar_client - CRITICAL - Response code 404: agent
d432fbb3-d2f1-4a97-9ef7-75bd81c00000 not found
2022-10-14 12:56:02.172 - keylime.tenant - INFO - Agent d432fbb3-d2f1-4a97-9ef7-
75bd81c00000 does not exist on the registrar. Please register the agent with the registrar.
2022-10-14 12:56:02.172 - keylime.tenant - INFO - {"code": 404, "status": "Agent d432fbb3-
d2f1-4a97-9ef7-75bd81c00000 does not exist on registrar 127.0.0.1 port 8891.", "results": {}}
```

If correctly set up, and if no agent is configured, the registrar responds that it does not recognize the default agent UUID.

Additional resources

• For additional advanced options for the **keylime_tenant** utility, enter the **keylime_tenant -h** command.

6.9. DEPLOYING KEYLIME AGENT FROM A PACKAGE

The Keylime agent is the component deployed to all systems to be monitored by Keylime.

By default, the Keylime agent stores all its data in the $\prec{|var|lib/keylime|}$ directory of the monitored system.



NOTE

To keep the configuration files organized within the drop-in directories, use file names with a two-digit number prefix, for example /etc/keylime/agent.conf.d/00-registrar-ip.conf. The configuration processing reads the files inside the drop-in directory in lexicographic order and sets each option to the last value it reads.

Prerequisites

- You have **root** permissions to the monitored system.
- The monitored system has a Trusted Platform Module (TPM). To verify, enter the **tpm2_pcrread** command. If the output returns several hashes, a TPM is available.
- You have network access to the systems where the other Keylime components are configured:

Verifier

For more information, see

Procedure

- 1. Install the Keylime agent:
 - # dnf install keylime-agent

This command installs the **keylime-agent-rust** package.

Define the agent's IP address and port in the configuration files. Create a new .conf file in the /etc/keylime/agent.conf.d/ directory, for example, /etc/keylime/agent.conf.d/00-agent-ip.conf, with the following content:

```
[agent]
ip = '<agent_ip>'
```



NOTE

The Keylime agent configuration uses the TOML format, which is different from the INI format used for configuration of the other components. Therefore, enter values in valid TOML syntax, for example, paths in single quotation marks and arrays of multiple paths in square brackets.

- Replace <agent_IP_address> with the agent's IP address. Alternatively, use ip = '*' or ip = '0.0.0.0' to bind the agent to all available IP addresses.
- Optionally, you can also change the agent's port from the default value 9002 by using the port = '<agent_port>' option.
- 3. Define the registrar's IP address and port in the configuration files. Create a new .conf file in the /etc/keylime/agent.conf.d/ directory, for example, /etc/keylime/agent.conf.d/00-registrar-ip.conf, with the following content:

```
[agent]
registrar_ip = '<registrar_IP_address>'
```

- Replace < registrar_IP_address> with the registrar's IP address.
- Optionally, you can also change the registrar's port from the default value **8890** by using the registrar_port = '<registrar_port>' option.
- 4. Optional: Define the agent's universally unique identifier (UUID). If it is not defined, the default UUID is used. Create a new .conf file in the /etc/keylime/agent.conf.d/ directory, for example, /etc/keylime/agent.conf.d/00-agent-uuid.conf, with the following content:

```
[agent]
uuid = '<agent_UUID>'
```

- Replace <agent_UUID> with the agent's UUID, for example d432fbb3-d2f1-4a97-9ef7-abcdef012345. You can use the uuidgen utility to generate a UUID.
- 5. Optional: Load existing keys and certificates for the agent. If the agent receives no server_key and server_cert, it generates its own key and a self-signed certificate.
 Define the location of the keys and certificates in the configuration. Create a new .conf file in the /etc/keylime/agent.conf.d/ directory, for example, /etc/keylime/agent.conf.d/00-keys-and-certs.conf, with the following content:

```
[agent]
server_key = '</path/to/server_key>'
server_key_password = '<passphrase1>'
server_cert = '</path/to/server_cert>'
trusted_client_ca = '[</path/to/ca/cert3>, </path/to/ca/cert4>]'
```



NOTE

Use absolute paths to define key and certificate locations. The Keylime agent does not accept relative paths.

6. Open the port in firewall:

```
# firewall-cmd --add-port 9002/tcp
# firewall-cmd --runtime-to-permanent
```

If you use a different port, replace 9002 with the port number defined in the .conf file.

7. Enable and start the **keylime_agent** service:

```
# systemctl enable --now keylime_agent
```

8. Optional: From the system where the Keylime tenant is configured, verify that the agent is correctly configured and can connect to the registrar.

```
# keylime_tenant -c regstatus --uuid <agent_uuid>
Reading configuration from ['/etc/keylime/logging.conf']
...
==\n----END CERTIFICATE----\n", "ip": "127.0.0.1", "port": 9002, "regcount": 1, "operational_state": "Registered"}}}
```

- Replace <agent_uuid> with the agent's UUID.
 If the registrar and agent are correctly configured, the output displays the agent's IP address and port, followed by "operational_state": "Registered".
- 9. Create a new IMA policy by entering the following content into the /etc/ima/ima-policy file:

```
# PROC_SUPER_MAGIC = 0x9fa0
dont_measure fsmagic=0x9fa0
# SYSFS_MAGIC = 0x62656572
dont_measure fsmagic=0x62656572
```

```
# DEBUGFS_MAGIC = 0x64626720
dont_measure fsmagic=0x64626720
# TMPFS MAGIC = 0x01021994
dont_measure fsmagic=0x1021994
# RAMFS MAGIC
dont_measure fsmagic=0x858458f6
# DEVPTS SUPER MAGIC=0x1cd1
dont measure fsmagic=0x1cd1
# BINFMTFS MAGIC=0x42494e4d
dont measure fsmagic=0x42494e4d
# SECURITYFS MAGIC=0x73636673
dont measure fsmagic=0x73636673
# SELINUX_MAGIC=0xf97cff8c
dont measure fsmagic=0xf97cff8c
# SMACK_MAGIC=0x43415d53
dont measure fsmagic=0x43415d53
# NSFS MAGIC=0x6e736673
dont measure fsmagic=0x6e736673
# EFIVARFS MAGIC
dont measure fsmagic=0xde5e81e4
# CGROUP SUPER MAGIC=0x27e0eb
dont measure fsmagic=0x27e0eb
# CGROUP2_SUPER_MAGIC=0x63677270
dont measure fsmagic=0x63677270
# OVERLAYFS MAGIC
# when containers are used we almost always want to ignore them
dont_measure fsmagic=0x794c7630
# MEASUREMENTS
measure func=BPRM CHECK
measure func=FILE MMAP mask=MAY EXEC
measure func=MODULE_CHECK uid=0
```

This policy targets runtime monitoring of executed applications. You can adjust this policy according to your scenario. You can find the MAGIC constants in the **statfs(2)** man page.

10. Update kernel parameters:

```
# grubby --update-kernel DEFAULT --args 'ima_appraise=fix ima_canonical_fmt ima_policy=tcb ima_template=ima-ng'
```

11. Reboot the system to apply the new IMA policy.

Verification

1. Verify that the agent is running:

```
    # systemctl status keylime_agent
    keylime_agent.service - The Keylime compute agent
        Loaded: loaded (/usr/lib/systemd/system/keylime_agent.service; enabled; preset:
        disabled)
        Active: active (running) since ...
```

Next steps

After the agent is configured on all systems you want to monitor, you can deploy Keylime to perform one or both of the following functions:

Additional resources

• Integrity Measurement Architecture (IMA) Wiki

6.10. CONFIGURING KEYLIME FOR RUNTIME MONITORING

To verify that the state of monitored systems is correct, the Keylime agent must be running on the monitored systems.



IMPORTANT

Because Keylime runtime monitoring uses integrity measurement architecture (IMA) to measure large numbers of files, it might have a significant impact on the performance of your system.

When provisioning the agent, you can also define a file that Keylime sends to the monitored system. Keylime encrypts the file sent to the agent, and decrypts it only if the agent's system complies with the TPM policy and with the IMA allowlist.

You can make Keylime ignore changes of specific files or within specific directories by configuring a Keylime excludelist. The excluded files are still measured by IMA.

From Keylime version 7.3.0, provided in RHEL 9.3, the allowlist and excludelist are combined into the Keylime runtime policy.

Prerequisites

• You have network access to the systems where the Keylime components are configured:

Procedure

1. On the monitored system where the Keylime agent is configured and running, generate an allowlist from the current state of the system:



Replace *<allowlist.txt>* with the file name of the allowlist.



IMPORTANT

Use the SHA-256 hash function. SHA-1 is not secure and has been deprecated in RHEL 9. For additional information, see SHA-1 deprecation in Red Hat Enterprise Linux 9.

2. Copy the generated allowlist to the system where the **keylime_tenant** utility is configured, for example:

scp <allowlist.txt> root@<tenant.ip>:/root/<allowlist.txt>

3. Optional: You can define a list of files or directories excluded from Keylime measurements by

creating a file on the tenant system and entering the paths of files and directories to exclude. The excludelist accepts Python regular expressions with one regular expression per line. See Regular expression operations at docs.python.org for the complete list of special characters. Save the excludelist on the tenant system.

4. Combine the allowlist and excludelist into the Keylime runtime policy:

keylime_create_policy -a <allowlist.txt> -e <excludelist.txt> -o <policy.json>

5. On the system where the Keylime tenant is configured, provision the agent by using the **keylime_tenant** utility:

keylime_tenant -c add -t <agent_ip> -u <agent_uuid> --runtime-policy <policy.json> --cert default

- Replace <agent_ip> with the agent's IP address.
- Replace <agent_uuid> with the agent's UUID.
- Replace <policy.json> with the path to the Keylime runtime policy file.
- With the --cert option, the tenant generates and signs a certificate for the agent by using
 the CA certificates and keys located in the specified directory, or the default
 /var/lib/keylime/ca/ directory. If the directory contains no CA certificates and keys, the
 tenant will generate them automatically according to the configuration in the
 /etc/keylime/ca.conf file and save them to the specified directory. The tenant then sends
 these keys and certificates to the agent.

When generating CA certificates or signing agent certificates, you might be prompted for the password to access the CA private key: **Please enter the password to decrypt your keystore:**

If you do not want to use a certificate, use the **-f** option instead for delivering a file to the agent. Provisioning an agent requires sending any file, even an empty file.



NOTE

Keylime encrypts the file sent to the agent, and decrypts it only if the agent's system complies with the TPM policy and the IMA allowlist. By default, Keylime decompresses sent **.zip** files.

As an example, with the following command, **keylime_tenant** provisions a new Keylime agent at **127.0.0.1** with UUID **d432fbb3-d2f1-4a97-9ef7-75bd81c00000** and loads a runtime policy **policy.json**. It also generates a certificate in the default directory and sends the certificate file to the agent. Keylime decrypts the file only if the TPM policy configured in **/etc/keylime/verifier.conf** is satisfied:

keylime_tenant -c add -t 127.0.0.1 -u d432fbb3-d2f1-4a97-9ef7-75bd81c00000 --runtime-policy policy.json --cert default



NOTE

You can stop Keylime from monitoring a node by using the **# keylime_tenant -c delete -u delete -u agent_uuid>** command.

You can modify the configuration of an already registered agent by using the **keylime_tenant -c update** command.

Verification

- 1. Optional: Reboot the monitored system to verify that the settings are persistent.
- 2. Verify a successful attestation of the agent:

```
# keylime_tenant -c cvstatus -u <agent.uuid>
...
{"<agent.uuid>": {"operational_state": "Get Quote"..."attestation_count": 5
...
```

Replace *<agent.uuid>* with the agent's UUID.

If the value of **operational_state** is **Get Quote** and **attestation_count** is nonzero, the attestation of this agent is successful.

If the value of **operational_state** is **Invalid Quote** or **Failed** attestation fails, the command displays output similar to the following:

```
{"<agent.uuid>": {"operational_state": "Invalid Quote", ... "ima.validation.imang.not_in_allowlist", "attestation_count": 5, "last_received_quote": 1684150329, "last_successful_attestation": 1684150327}}
```

3. If the attestation fails, display more details in the verifier log:

```
# journalctl -u keylime_verifier
keylime.tpm - INFO - Checking IMA measurement list...
keylime.ima - WARNING - File not found in allowlist: /root/bad-script.sh
keylime.ima - ERROR - IMA ERRORS: template-hash 0 fnf 1 hash 0 good 781
keylime.cloudverifier - WARNING - agent D432FBB3-D2F1-4A97-9EF7-75BD81C00000
failed, stopping polling
```

Additional resources

• For more information about IMA, see Enhancing security with the kernel integrity subsystem.

6.11. CONFIGURING KEYLIME FOR MEASURED BOOT ATTESTATION

When you configure Keylime for measured boot attestation, Keylime checks that the boot process on the measured system corresponds to the state you defined.

Prerequisites

• You have network access to the systems where the Keylime components are configured:

Verifier

For more information, see

• Unified Extensible Firmware Interface (UEFI) is enabled on the agent system.

Procedure

1. On the monitored system where the Keylime agent is configured and running, install the **python3-keylime** package, which contains the **create_mb_refstate** script:

dnf -y install python3-keylime

2. On the monitored system, generate a policy from the measured boot log of the current state of the system by using the **create_mb_refstate** script:

/usr/share/keylime/scripts/create_mb_refstate
/sys/kernel/security/tpm0/binary_bios_measurements
<./measured_boot_reference_state.json>

- Replace <./measured_boot_reference_state.json> with the path where the script saves the generated policy.
- If your UEFI system does not have Secure Boot enabled, pass the --without-secureboot argument.



IMPORTANT

The policy generated with the **create_mb_refstate** script is based on the current state of the system and is very strict. Any modifications of the system including kernel updates and system updates will change the boot process and the system will fail the attestation.

3. Copy the generated policy to the system where the **keylime_tenant** utility is configured, for example:

```
# scp root@<agent_ip>:<./measured_boot_reference_state.json> <./measured_boot_reference_state.json>
```

4. On the system where the Keylime tenant is configured, provision the agent by using the **keylime_tenant** utility:

```
# keylime_tenant -c add -t <agent_ip> -u <agent_uuid> --mb_refstate <./measured_boot_reference_state.json> --cert default
```

- Replace <agent_ip> with the agent's IP address.
- Replace <agent_uuid> with the agent's UUID.
- Replace <./measured_boot_reference_state.json> with the path to the measured boot policy.

If you configure measured boot in combination with runtime monitoring, provide all the options from both use cases when entering the **keylime tenant -c add** command.



NOTE

You can stop Keylime from monitoring a node by using the **# keylime_tenant -c delete -t <agent_ip> -u <agent_uuid>** command.

You can modify the configuration of an already registered agent by using the **keylime_tenant -c update** command.

Verification

1. Reboot the monitored system and verify a successful attestation of the agent:

```
# keylime_tenant -c cvstatus -u <agent_uuid>
...
{"<agent.uuid>": {"operational_state": "Get Quote"..."attestation_count": 5
...
```

Replace <agent_uuid> with the agent's UUID.

If the value of **operational_state** is **Get Quote** and **attestation_count** is nonzero, the attestation of this agent is successful.

If the value of **operational_state** is **Invalid Quote** or **Failed** attestation fails, the command displays output similar to the following:

```
{"<agent.uuid>": {"operational_state": "Invalid Quote", ... "ima.validation.imang.not_in_allowlist", "attestation_count": 5, "last_received_quote": 1684150329, "last_successful_attestation": 1684150327}}
```

2. If the attestation fails, display more details in the verifier log:

```
# journalctl -u keylime_verifier {"d432fbb3-d2f1-4a97-9ef7-75bd81c00000": {"operational_state": "Tenant Quote Failed", ... "last_event_id": "measured_boot.invalid_pcr_0", "attestation_count": 0, "last_received_quote": 1684487093, "last_successful_attestation": 0}}
```

6.12. KEYLIME ENVIRONMENT VARIABLES

You can set Keylime environment variables to override the values from the configuration files, for example, when starting a container with the **podman run** command by using the **-e** option.

The environment variables have the following syntax:

```
KEYLIME_<SECTION>_<ENVIRONMENT_VARIABLE>=<value>
```

Where:

- **<SECTION>** is the section of the Keylime configuration file.
- *<ENVIRONMENT_VARIABLE>* is the environment variable.
- <value> is the value to which you want to set the environment variable.

For example, **-e KEYLIME_VERIFIER_MAX_RETRIES=6** sets the **max_retries** configuration option in the **[verifier]** section to **6**.

Verifier configuration

Table 6.1. [verifier] section

Configuration option	Environment variable	Default value
auto_migrate_db	KEYLIME_VERIFIER_AUTO_ MIGRATE_DB	True
client_cert	KEYLIME_VERIFIER_CLIENT _CERT	default
client_key_password	KEYLIME_VERIFIER_CLIENT _KEY_PASSWORD	
client_key	KEYLIME_VERIFIER_CLIENT _KEY	default
database_pool_sz_ovfl	KEYLIME_VERIFIER_DATAB ASE_POOL_SZ_OVFL	5,10
database_url	KEYLIME_VERIFIER_DATAB ASE_URL	sqlite
durable_attestation_import	KEYLIME_VERIFIER_DURAB LE_ATTESTATION_IMPORT	
enable_agent_mtls	KEYLIME_VERIFIER_ENABL E_AGENT_MTLS	True
exponential_backoff	KEYLIME_VERIFIER_EXPON ENTIAL_BACKOFF	True
ignore_tomtou_errors	KEYLIME_VERIFIER_IGNOR E_TOMTOU_ERRORS	False
ip	KEYLIME_VERIFIER_IP	127.0.0.1
max_retries	KEYLIME_VERIFIER_MAX_R ETRIES	5
max_upload_size	KEYLIME_VERIFIER_MAX_U PLOAD_SIZE	104857600
measured_boot_evaluate	KEYLIME_VERIFIER_MEASU RED_BOOT_EVALUATE	once

Configuration option	Environment variable	Default value
measured_boot_imports	KEYLIME_VERIFIER_MEASU RED_BOOT_IMPORTS	0
measured_boot_policy_nam e	KEYLIME_VERIFIER_MEASU RED_BOOT_POLICY_NAME	accept-all
num_workers	KEYLIME_VERIFIER_NUM_W ORKERS	0
persistent_store_encoding	KEYLIME_VERIFIER_PERSIS TENT_STORE_ENCODING	
persistent_store_format	KEYLIME_VERIFIER_PERSIS TENT_STORE_FORMAT	json
persistent_store_url	KEYLIME_VERIFIER_PERSIS TENT_STORE_URL	
port	KEYLIME_VERIFIER_PORT	8881
quote_interval	KEYLIME_VERIFIER_QUOTE _INTERVAL	2
registrar_ip	KEYLIME_VERIFIER_REGIST RAR_IP	127.0.0.1
registrar_port	KEYLIME_VERIFIER_REGIST RAR_PORT	8891
request_timeout	KEYLIME_VERIFIER_REQUE ST_TIMEOUT	60.0
require_allow_list_signature s	KEYLIME_VERIFIER_REQUI RE_ALLOW_LIST_SIGNATU RES	True
retry_interval	KEYLIME_VERIFIER_RETRY _INTERVAL	2
server_cert	KEYLIME_VERIFIER_SERVE R_CERT	default
server_key_password	KEYLIME_VERIFIER_SERVE R_KEY_PASSWORD	default

Configuration option	Environment variable	Default value
server_key	KEYLIME_VERIFIER_SERVE R_KEY	default
severity_labels	KEYLIME_VERIFIER_SEVERI TY_LABELS	["info", "notice", "warning", "error", "critical", "alert", "emergency"]
severity_policy	KEYLIME_VERIFIER_SEVERI TY_POLICY	[{"event_id": ".*", "severity_label" : "emergency"}]
signed_attributes	KEYLIME_VERIFIER_SIGNED _ATTRIBUTES	
time_stamp_authority_certs_ path	KEYLIME_VERIFIER_TIME_S TAMP_AUTHORITY_CERTS_ PATH	
time_stamp_authority_url	KEYLIME_VERIFIER_TIME_S TAMP_AUTHORITY_URL	
tls_dir	KEYLIME_VERIFIER_TLS_DI	generate
transparency_log_sign_algo	KEYLIME_VERIFIER_TRANS PARENCY_LOG_SIGN_ALG O	sha256
transparency_log_url	KEYLIME_VERIFIER_TRANS PARENCY_LOG_URL	
trusted_client_ca	KEYLIME_VERIFIER_TRUST ED_CLIENT_CA	default
trusted_server_ca	KEYLIME_VERIFIER_TRUST ED_SERVER_CA	default
uuid	KEYLIME_VERIFIER_UUID	default
version	KEYLIME_VERIFIER_VERSION	2.0

Table 6.2. [revocations] section

Configuration option	Environment variable	Default value
----------------------	----------------------	---------------

enabled_revocation_notificat ions	KEYLIME_VERIFIER_REVOC ATIONS_ENABLED_REVOC ATION_NOTIFICATIONS	[agent]
webhook_url	KEYLIME_VERIFIER_REVOC ATIONS_WEBHOOK_URL	

Registrar configuration

Table 6.3. [registrar] section

Configuration option	Environment variable	Default value
auto_migrate_db	KEYLIME_REGISTRAR_AUT O_MIGRATE_DB	True
database_pool_sz_ovfl	KEYLIME_REGISTRAR_DAT ABASE_POOL_SZ_OVFL	5,10
database_url	KEYLIME_REGISTRAR_DAT ABASE_URL	sqlite
durable_attestation_import	KEYLIME_REGISTRAR_DUR ABLE_ATTESTATION_IMPO RT	
ip	KEYLIME_REGISTRAR_IP	127.0.0.1
persistent_store_encoding	KEYLIME_REGISTRAR_PER SISTENT_STORE_ENCODIN G	
persistent_store_format	KEYLIME_REGISTRAR_PER SISTENT_STORE_FORMAT	json
persistent_store_url	KEYLIME_REGISTRAR_PER SISTENT_STORE_URL	
port	KEYLIME_REGISTRAR_POR T	8890
prov_db_filename	KEYLIME_REGISTRAR_PRO V_DB_FILENAME	provider_reg_data.sqlite
server_cert	KEYLIME_REGISTRAR_SER VER_CERT	default

server_key_password	KEYLIME_REGISTRAR_SER VER_KEY_PASSWORD	default
server_key	KEYLIME_REGISTRAR_SER VER_KEY	default
signed_attributes	KEYLIME_REGISTRAR_SIGN ED_ATTRIBUTES	ek_tpm,aik_tpm,ekcert
time_stamp_authority_certs_ path	KEYLIME_REGISTRAR_TIME _STAMP_AUTHORITY_CERT S_PATH	
time_stamp_authority_url	KEYLIME_REGISTRAR_TIME _STAMP_AUTHORITY_URL	
tls_dir	KEYLIME_REGISTRAR_TLS_ DIR	default
tls_port	KEYLIME_REGISTRAR_TLS_ PORT	8891
transparency_log_sign_algo	KEYLIME_REGISTRAR_TRA NSPARENCY_LOG_SIGN_A LGO	sha256
transparency_log_url	KEYLIME_REGISTRAR_TRA NSPARENCY_LOG_URL	
trusted_client_ca	KEYLIME_REGISTRAR_TRU STED_CLIENT_CA	default
version	KEYLIME_REGISTRAR_VER SION	2.0

Tenant configuration

Table 6.4. [tenant] section

Configuration option	Environment variable	Default value
accept_tpm_encryption_algs	KEYLIME_TENANT_ACCEPT _TPM_ENCRYPTION_ALGS	ecc, rsa
accept_tpm_hash_algs	KEYLIME_TENANT_ACCEPT _TPM_HASH_ALGS	sha512, sha384, sha256

accept_tpm_signing_algs	KEYLIME_TENANT_ACCEPT _TPM_SIGNING_ALGS	ecschnorr, rsassa
client_cert	KEYLIME_TENANT_CLIENT_ CERT	default
client_key_password	KEYLIME_TENANT_CLIENT_ KEY_PASSWORD	
client_key	KEYLIME_TENANT_CLIENT_ KEY	default
ek_check_script	KEYLIME_TENANT_EK_CHE CK_SCRIPT	
enable_agent_mtls	KEYLIME_TENANT_ENABLE _AGENT_MTLS	True
exponential_backoff	KEYLIME_TENANT_EXPONE NTIAL_BACKOFF	True
max_payload_size	KEYLIME_TENANT_MAX_PA YLOAD_SIZE	1048576
max_retries	KEYLIME_TENANT_MAX_RE TRIES	5
mb_refstate	KEYLIME_TENANT_MB_REF STATE	
registrar_ip	KEYLIME_TENANT_REGIST RAR_IP	127.0.0.1
registrar_port	KEYLIME_TENANT_REGIST RAR_PORT	8891
request_timeout	KEYLIME_TENANT_REQUES T_TIMEOUT	60
require_ek_cert	KEYLIME_TENANT_REQUIR E_EK_CERT	True
retry_interval	KEYLIME_TENANT_RETRY_I NTERVAL	2
tls_dir	KEYLIME_TENANT_TLS_DIR	default
tpm_cert_store	KEYLIME_TENANT_TPM_CE RT_STORE	/var/lib/keylime/tpm_cert_sto re

trusted_server_ca	KEYLIME_TENANT_TRUSTE D_SERVER_CA	default
verifier_ip	KEYLIME_TENANT_VERIFIE R_IP	127.0.0.1
verifier_port	KEYLIME_TENANT_VERIFIE R_PORT	8881
version	KEYLIME_TENANT_VERSIO N	2.0

CA configuration

Table 6.5. [ca] section

Configuration option	Environment variable	Default value
cert_bits	KEYLIME_CA_CERT_BITS	2048
cert_ca_lifetime	KEYLIME_CA_CERT_CA_LIF ETIME	3650
cert_ca_name	KEYLIME_CA_CERT_CA_NA ME	Keylime Certificate Authority
cert_country	KEYLIME_CA_CERT_COUNT RY	US
cert_crl_dist	KEYLIME_CA_CERT_CRL_DI ST	http://localhost:38080/crl
cert_lifetime	KEYLIME_CA_CERT_LIFETI ME	365
cert_locality	KEYLIME_CA_CERT_LOCAL ITY	Lexington
cert_org_unit	KEYLIME_CA_CERT_ORG_U NIT	53
cert_organization	KEYLIME_CA_CERT_ORGA NIZATION	MITLL
cert_state	KEYLIME_CA_CERT_STATE	MA
password	KEYLIME_CA_PASSWORD	default

version	KEYLIME_CA_VERSION	2.0
---------	--------------------	-----

Agent configuration

Table 6.6. [agent] section

Configuration option	Environment variable	Default value
contact_ip	KEYLIME_AGENT_CONTAC T_IP	127.0.0.1
contact_port	KEYLIME_AGENT_CONTAC T_PORT	9002
dec_payload_file	KEYLIME_AGENT_DEC_PAY LOAD_FILE	decrypted_payload
ek_handle	KEYLIME_AGENT_EK_HAND LE	generate
enable_agent_mtls	KEYLIME_AGENT_ENABLE_ AGENT_MTLS	true
enable_insecure_payload	KEYLIME_AGENT_ENABLE_ INSECURE_PAYLOAD	false
enable_revocation_notificati ons	KEYLIME_AGENT_ENABLE_ REVOCATION_NOTIFICATIO NS	true
enc_keyname	KEYLIME_AGENT_ENC_KEY NAME	derived_tci_key
exponential_backoff	KEYLIME_AGENT_EXPONEN TIAL_BACKOFF	true
extract_payload_zip	KEYLIME_AGENT_EXTRACT _PAYLOAD_ZIP	true
ip	KEYLIME_AGENT_IP	127.0.0.1
max_retries	KEYLIME_AGENT_MAX_RET RIES	4
measure_payload_pcr	KEYLIME_AGENT_MEASUR E_PAYLOAD_PCR	-1
payload_script	KEYLIME_AGENT_PAYLOA D_SCRIPT	autorun.sh

Configuration option	Environment variable	Default value
port	KEYLIME_AGENT_PORT	9002
registrar_ip	KEYLIME_AGENT_REGISTR AR_IP	127.0.0.1
registrar_port	KEYLIME_AGENT_REGISTR AR_PORT	8890
retry_interval	KEYLIME_AGENT_RETRY_I NTERVAL	2
revocation_actions	KEYLIME_AGENT_REVOCA TION_ACTIONS	
revocation_cert	KEYLIME_AGENT_REVOCA TION_CERT	default
revocation_notification_ip	KEYLIME_AGENT_REVOCA TION_NOTIFICATION_IP	127.0.0.1
revocation_notification_port	KEYLIME_AGENT_REVOCA TION_NOTIFICATION_PORT	8992
run_as	KEYLIME_AGENT_RUN_AS	keylime:tss
secure_size	KEYLIME_AGENT_SECURE_ SIZE	1m
server_cert	KEYLIME_AGENT_SERVER_ CERT	default
server_key_password	KEYLIME_AGENT_SERVER_ KEY_PASSWORD	
server_key	KEYLIME_AGENT_SERVER_ KEY	default
tls_dir	KEYLIME_AGENT_TLS_DIR	default
tpm_encryption_alg	KEYLIME_AGENT_TPM_ENC RYPTION_ALG	rsa
tpm_hash_alg	KEYLIME_AGENT_TPM_HAS H_ALG	sha256
tpm_ownerpassword	KEYLIME_AGENT_TPM_OW NERPASSWORD	

Configuration option	Environment variable	Default value
tpm_signing_alg	KEYLIME_AGENT_TPM_SIG NING_ALG	rsassa
trusted_client_ca	KEYLIME_AGENT_TRUSTED _CLIENT_CA	default
uuid	KEYLIME_AGENT_UUID	d432fbb3-d2f1-4a97-9ef7- 75bd81c00000
version	KEYLIME_AGENT_VERSION	2.0

Logging configuration

Table 6.7. [logging] section

Configuration option	Environment variable	Default value
version	KEYLIME_LOGGING_VERSION	2.0

Table 6.8. [loggers] section

Configuration option	Environment variable	Default value
keys	KEYLIME_LOGGING_LOGG ERS_KEYS	root,keylime

Table 6.9. [handlers] section

Configuration option	Environment variable	Default value
keys	KEYLIME_LOGGING_HANDL ERS_KEYS	consoleHandler

Table 6.10. [formatters] section

Configuration option	Environment variable	Default value
keys	KEYLIME_LOGGING_FORM ATTERS_KEYS	formatter

Table 6.11. [formatter_formatter] section

Configuration option Environment variable Default value	
---	--

datefmt	KEYLIME_LOGGING_FORM ATTER_FORMATTER_DATE FMT	%Y-%m-%d %H:%M:%S
format	KEYLIME_LOGGING_FORM ATTER_FORMATTER_FORM AT	%(asctime)s.%(msecs)03d - %(name)s - %(levelname)s - %(message)s

Table 6.12. [logger_root] section

Configuration option	Environment variable	Default value
handlers	KEYLIME_LOGGING_LOGG ER_ROOT_HANDLERS	consoleHandler
level	KEYLIME_LOGGING_LOGG ER_ROOT_LEVEL	INFO

Table 6.13. [handler_consoleHandler] section

Configuration option	Environment variable	Default value
args	KEYLIME_LOGGING_HANDL ER_CONSOLEHANDLER_AR GS	(sys.stdout,)
class	KEYLIME_LOGGING_HANDL ER_CONSOLEHANDLER_CL ASS	StreamHandler
formatter	KEYLIME_LOGGING_HANDL ER_CONSOLEHANDLER_FO RMATTER	formatter
level	KEYLIME_LOGGING_HANDL ER_CONSOLEHANDLER_LE VEL	INFO

Table 6.14. [logger_keylime] section

Configuration option	Environment variable	Default value
handlers	KEYLIME_LOGGING_LOGG ER_KEYLIME_HANDLERS	
level	KEYLIME_LOGGING_LOGG ER_KEYLIME_LEVEL	INFO

qualname	KEYLIME_LOGGING_LOGG ER_KEYLIME_QUALNAME	keylime
----------	---	---------

CHAPTER 7. CHECKING INTEGRITY WITH AIDE

Advanced Intrusion Detection Environment (AIDE) is a utility that creates a database of files on the system, and then uses that database to ensure file integrity and detect system intrusions.

7.1. INSTALLING AIDE

To start file-integrity checking with AIDE, you must install the corresponding package and initiate the AIDE database.

Prerequisites

• The **AppStream** repository is enabled.

Procedure

1. Install the aide package:

dnf install aide

2. Generate an initial database:

- 3. Optional: In the default configuration, the **aide --init** command checks just a set of directories and files defined in the /**etc/aide.conf** file. To include additional directories or files in the AIDE database, and to change their watched parameters, edit /**etc/aide.conf** accordingly.
- 4. To start using the database, remove the .new substring from the initial database file name:

mv /var/lib/aide/aide.db.new.gz /var/lib/aide/aide.db.gz

5. Optional: To change the location of the AIDE database, edit the /etc/aide.conf file and modify the DBDIR value. For additional security, store the database, configuration, and the /usr/sbin/aide binary file in a secure location such as a read-only media.

7.2. PERFORMING INTEGRITY CHECKS WITH AIDE

You can use the **crond** service to schedule regular file-integrity checks with AIDE.

Prerequisites

• AIDE is properly installed and its database is initialized. See Installing AIDE

Procedure

1. To initiate a manual check:

```
# aide --check
Start timestamp: 2024-07-08 10:43:46 -0400 (AIDE 0.16)
AIDE found differences between database and file system!!
Summary:
 Total number of entries: 55856
 Added entries: 0
 Removed entries: 0
 Changed entries: 1
Changed entries:
f ... ..S:/root/.viminfo
Detailed information about changes:
-----
File: /root/.viminfo
SELinux: system_u:object_r:admin_home_t:s | unconfined_u:object_r:admin_home
       0
                          | t:s0
```

2. At a minimum, configure the system to run AIDE weekly. Optimally, run AIDE daily. For example, to schedule a daily execution of AIDE at *04:05* a.m. by using the **cron** command, add the following line to the /etc/crontab file:

```
05 4 * * * root /usr/sbin/aide --check
```

Additional resources

• cron(8) man page on your system

7.3. UPDATING AN AIDE DATABASE

After verifying the changes of your system, such as package updates or configuration files adjustments, update also your baseline AIDE database.

Prerequisites

AIDE is properly installed and its database is initialized. See Installing AIDE

Procedure

1. Update your baseline AIDE database:

aide --update

The aide --update command creates the /var/lib/aide/aide.db.new.gz database file.

2. To start using the updated database for integrity checks, remove the **.new** substring from the file name.

7.4. FILE-INTEGRITY TOOLS: AIDE AND IMA

Red Hat Enterprise Linux provides several tools for checking and preserving the integrity of files and directories on your system. The following table helps you decide which tool better fits your scenario.

Table 7.1. Comparison between AIDE and IMA

Question	Advanced Intrusion Detection Environment (AIDE)	Integrity Measurement Architecture (IMA)
What	AIDE is a utility that creates a database of files and directories on the system. This database serves for checking file integrity and detect intrusion detection.	IMA detects if a file is altered by checking file measurement (hash values) compared to previously stored extended attributes.
How	AIDE uses rules to compare the integrity state of the files and directories.	IMA uses file hash values to detect the intrusion.
Why	Detection - AIDE detects if a file is modified by verifying the rules.	Detection and Prevention - IMA detects and prevents an attack by replacing the extended attribute of a file.
Usage	AIDE detects a threat when the file or directory is modified.	IMA detects a threat when someone tries to alter the entire file.
Extension	AIDE checks the integrity of files and directories on the local system.	IMA ensures security on the local and remote systems.

7.5. ADDITIONAL RESOURCES

- aide(1) man page on your system
- Kernel integrity subsystem

CHAPTER 8. MANAGING SUDO ACCESS

System administrators can grant **sudo** access to allow non-root users to execute administrative commands that are normally reserved for the root user. As a result, non-root users can execute such commands without logging in to the root user account.

8.1. USER AUTHORIZATIONS IN SUDOERS

The /etc/sudoers file specifies which users can use the **sudo** command to execute other commands. The rules can apply to individual users and user groups. You can also define rules for groups of hosts, commands, and even users more easily by using aliases. Default aliases are defined in the first part of the /etc/sudoers file.

When a user enters a command with **sudo** for which the user does not have authorization, the system records a message that contains the string **<username>**: user NOT in sudoers to the journal log.

The default /etc/sudoers file provides information and examples of authorizations. You can activate a specific example rule by uncommenting the corresponding line. The section with user authorizations is marked with the following introduction:

Next comes the main part: which users can run what software on ## which machines (the sudoers file can be shared between multiple ## systems).

You can create new **sudoers** authorizations and modify existing authorizations by using the following format:

<username> <hostname.example.com>=(<run_as_user>:<run_as_group>) <path/to/command>

Where:

- **<username>** is the user that enters the command, for example, **user1**. If the value starts with **%**, it defines a group, for example, **%group1**.
- **<hostname.example.com>** is the name of the host on which the rule applies.
- The section (<<u>run_as_user>:<run_as_group></u>) defines the user or group as which the command is executed. If you omit this section, <<u>username></u> can execute the command as root.
- <path/to/command> is the complete absolute path to the command. You can also limit the user to only performing a command with specific options and arguments by adding those options after the command path. If you do not specify any options, the user can use the command with all options.

You can apply the rule to all users, hosts, or commands by replacing any of these variables with **ALL**.



WARNING

With overly permissive rules, such as **ALL ALL=(ALL) ALL**, all users can run all commands as all users on all hosts. This presents serious security risks.

You can specify the arguments negatively by using the ! operator. For example, !root specifies all users except root. Note that allowing specific users, groups, and commands is more secure than disallowing specific users, groups, and commands. This is because allow rules also block new unauthorized users or groups.



WARNING

Avoid using negative rules for commands because users can overcome such rules by renaming commands with the **alias** command.

The system reads the /etc/sudoers file from beginning to end. Therefore, if the file contains multiple entries for a user, the entries are applied in order. In case of conflicting values, the system uses the last match, even if it is not the most specific match.

To preserve the rules during system updates and for easier fixing of errors, enter new rules by creating new files in the /etc/sudoers.d/ directory instead of entering rules directly to the /etc/sudoers file. The system reads the files in the /etc/sudoers.d directory when it reaches the following line in the /etc/sudoers file:

#includedir /etc/sudoers.d

Note that the number sign (#) at the beginning of this line is part of the syntax and does not mean the line is a comment. The names of files in that directory must not contain a period and must not end with a tilde (~).

Additional resources

• sudo(8) and sudoers(5) man pages on your system

8.2. GRANTING SUDO ACCESS TO A USER

System administrators can allow non-root users to execute administrative commands by granting them **sudo** access. The **sudo** command provides users with administrative access without using the password of the root user.

When users need to perform an administrative command, they can precede that command with **sudo**. If the user has authorization for the command, the command is executed as if they were root.

Be aware of the following limitations:

- Only users listed in the /etc/sudoers configuration file can use the sudo command.
- The command is executed in the shell of the user, not in the root shell. However, there are some exceptions such as when full **sudo** privileges are granted to any user. In such cases, users can switch to and run the commands in root shell. For example:
- sudo -i
- sudo su -

_ . .

Prerequisites

• You have root access to the system.

Procedure

1. As root, open the /etc/sudoers file.

visudo

The /etc/sudoers file defines the policies applied by the sudo command.

2. In the /etc/sudoers file, find the lines that grant sudo access to users in the administrative wheel group.

```
## Allows people in group wheel to run all commands %wheel ALL=(ALL) ALL
```

- 3. Make sure the line that starts with **%wheel** is not commented out with the number sign (#).
- 4. Save any changes, and exit the editor.
- 5. Add users you want to grant **sudo** access to into the administrative **wheel** group.

usermod --append -G wheel <username>

Replace **<username>** with the name of the user.

Verification

• Verify that the user is in the administrative **wheel** group:

```
# id <username> uid=5000(<username>) gid=5000(<username>),10(wheel)
```

Additional resources

• sudo(8), visudo(8), and sudoers(5) man pages on your system

8.3. ENABLING UNPRIVILEGED USERS TO RUN CERTAIN COMMANDS

As an administrator, you can allow unprivileged users to enter certain commands on specific workstations by configuring a policy in the /etc/sudoers.d/ directory. This is more secure than granting full sudo access to a user or giving someone the root password for the following reasons:

- More granular control over privileged actions. You can allow a user to perform certain actions on specific hosts instead of giving them full administrative access.
- Better logging. When a user performs an action through **sudo**, the action is logged with their user name and not just root.
- Transparent control. You can set email notifications for every time the user attempts to use sudo privileges.

Prerequisites

• You have root access to the system.

Procedure

1. As root, create a new **sudoers.d**/ directory under /etc/:

mkdir -p /etc/sudoers.d/

2. Create a new file in the /etc/sudoers.d/ directory:

visudo -f /etc/sudoers.d/<filename>

The file opens automatically.

3. Add the following line to the /etc/sudoers.d/<filename> file:

<username> <hostname.example.com> = (<run_as_user>:<run_as_group>)
<path/to/command>

- Replace <username> with the name of the user.
- Replace <hostname.example.com> with the URL of the host.
- Replace (<<u>run_as_user</u>>:<<u>run_as_group</u>>) with the user or group as which the command can be executed. If you omit this section, <<u>username</u>> can execute the command as root.
- Replace path/to/command> with the complete absolute path to the command. You can
 also limit the user to only performing a command with specific options and arguments by
 adding those options after the command path. If you do not specify any options, the user
 can use the command with all options.
- To allow two and more commands on the same host on one line, you can list them separated by a comma followed by a space.

For example, to allow **user1** to execute the **dnf** and **reboot** commands on **host1.example.com**, enter **user1 host1.example.com** = /bin/dnf, /sbin/reboot.

4. Optional: To receive email notifications every time the user attempts to use **sudo** privileges, add the following lines to the file:

```
Defaults mail_always
Defaults mailto="<email@example.com>"
```

5. Save the changes, and exit the editor.

Verification

1. To verify if a user can run a command with **sudo** privileges, switch the account:

```
# su <username> -
```

2. As the user, enter the command with the **sudo** command:

\$ sudo <command>
[sudo] password for <username>:

Enter the user's **sudo** password.

3. If the privileges are configured correctly, the system displays the list of commands and options. For example, with the **dnf** command, it shows the following output:

```
...
usage: dnf [options] COMMAND
...
```

If the system returns the error message *<username* is not in the sudoers file. This incident will be reported, the file for *<username* in **/etc/sudoers.d**/ does not exist.

If the system returns the error message **<username>** is not allowed to run sudo on **<host.example.com>**, the configuration was not completed correctly. Ensure that you are logged in as root and that the configuration was performed correctly.

If the system returns the error message **Sorry, user** *<username>* is not allowed to execute '*<path/to/command>*' as root on *<host.example.com>*., the command is not correctly defined in the rule for the user.

Additional resources

• sudo(8), visudo(8), and sudoers(5) man pages on your system

CHAPTER 9. CONFIGURING AUTOMATED UNLOCKING OF ENCRYPTED VOLUMES BY USING POLICY-BASED DECRYPTION

Policy-Based Decryption (PBD) is a collection of technologies that enable unlocking encrypted root and secondary volumes of hard drives on physical and virtual machines. PBD uses a variety of unlocking methods, such as user passwords, a Trusted Platform Module (TPM) device, a PKCS #11 device connected to a system, for example, a smart card, or a special network server.

PBD allows combining different unlocking methods into a policy, which makes it possible to unlock the same volume in different ways. The current implementation of the PBD in Red Hat Enterprise Linux consists of the Clevis framework and plug-ins called *pins*. Each pin provides a separate unlocking capability. Currently, the following pins are available:

tang

Allows unlocking volumes using a network server.

tpm2

allows unlocking volumes using a TPM2 policy.

SSS


allows deploying high-availability systems using the Shamir's Secret Sharing (SSS) cryptographic scheme.

9.1. NETWORK-BOUND DISK ENCRYPTION

The Network Bound Disc Encryption (NBDE) is a subcategory of Policy-Based Decryption (PBD) that allows binding encrypted volumes to a special network server. The current implementation of the NBDE includes a Clevis pin for the Tang server and the Tang server itself.

In RHEL, NBDE is implemented through the following components and technologies:

Figure 9.1. NBDE scheme when using a LUKS1-encrypted volume. The luksmeta package is not used for LUKS2 volumes.



RHEL_453350_0717

Tang is a server for binding data to network presence. It makes a system containing your data available when the system is bound to a certain secure network. Tang is stateless and does not require TLS or

authentication. Unlike escrow-based solutions, where the server stores all encryption keys and has knowledge of every key ever used, Tang never interacts with any client keys, so it never gains any identifying information from the client.

Clevis is a pluggable framework for automated decryption. In NBDE, Clevis provides automated unlocking of LUKS volumes. The **clevis** package provides the client side of the feature.

A *Clevis pin* is a plug-in into the Clevis framework. One of such pins is a plug-in that implements interactions with the NBDE server – Tang.

Clevis and Tang are generic client and server components that provide network-bound encryption. In RHEL, they are used in conjunction with LUKS to encrypt and decrypt root and non-root storage volumes to accomplish Network-Bound Disk Encryption.

Both client- and server-side components use the José library to perform encryption and decryption operations.

When you begin provisioning NBDE, the Clevis pin for Tang server gets a list of the Tang server's advertised asymmetric keys. Alternatively, since the keys are asymmetric, a list of Tang's public keys can be distributed out of band so that clients can operate without access to the Tang server. This mode is called *offline provisioning*.

The Clevis pin for Tang uses one of the public keys to generate a unique, cryptographically-strong encryption key. Once the data is encrypted by using this key, the key is discarded. The Clevis client should store the state produced by this provisioning operation in a convenient location. This process of encrypting data is the *provisioning step*.

The LUKS version 2 (LUKS2) is the default disk-encryption format in RHEL, hence, the provisioning state for NBDE is stored as a token in a LUKS2 header. The leveraging of provisioning state for NBDE by the **luksmeta** package is used only for volumes encrypted with LUKS1.

The Clevis pin for Tang supports both LUKS1 and LUKS2 without specification need. Clevis can encrypt plain-text files but you have to use the **cryptsetup** tool for encrypting block devices.

When the client is ready to access its data, it loads the metadata produced in the provisioning step and it responds to recover the encryption key. This process is the *recovery step*.

In NBDE, Clevis binds a LUKS volume by using a pin so that it can be automatically unlocked. After successful completion of the binding process, the disk can be unlocked using the provided Dracut unlocker.



NOTE

If the **kdump** kernel crash dumping mechanism is set to save the content of the system memory to a LUKS-encrypted device, you are prompted for entering a password during the second kernel boot.

Additional resources

- NBDE (Network-Bound Disk Encryption) Technology (Red Hat Knowledgebase)
- tang(8), clevis(1), jose(1), and clevis-luks-unlockers(7) man pages on your system
- How to set up Network-Bound Disk Encryption with multiple LUKS devices (Clevis + Tang unlocking) (Red Hat Knowledgebase)

9.2. DEPLOYING A TANG SERVER WITH SELINUX IN ENFORCING MODE

You can use a Tang server to automatically unlock LUKS-encrypted volumes on Clevis-enabled clients. In the minimalistic scenario, you deploy a Tang server on port 80 by installing the **tang** package and entering the **systemctl enable tangd.socket --now** command. The following example procedure demonstrates the deployment of a Tang server running on a custom port as a confined service in SELinux enforcing mode.

Prerequisites

- The **policycoreutils-python-utils** package and its dependencies are installed.
- The **firewalld** service is running.

Procedure

1. To install the **tang** package and its dependencies, enter the following command as **root**:

dnf install tang

2. Pick an unoccupied port, for example, 7500/tcp, and allow the **tangd** service to bind to that port:

semanage port -a -t tangd_port_t -p tcp 7500

Note that a port can be used only by one service at a time, and thus an attempt to use an already occupied port implies the **ValueError: Port already defined** error message.

3. Open the port in the firewall:

```
# firewall-cmd --add-port=7500/tcp
# firewall-cmd --runtime-to-permanent
```

- 4. Enable the tangd service:
 - # systemctl enable tangd.socket
- 5. Create an override file:
 - # systemctl edit tangd.socket
- 6. In the following editor screen, which opens an empty **override.conf** file located in the /etc/systemd/system/tangd.socket.d/ directory, change the default port for the Tang server from 80 to the previously picked number by adding the following lines:

[Socket] ListenStream= ListenStream=7500



IMPORTANT

Insert the previous code snippet between the lines starting with **# Anything** between here and **# Lines below this**, otherwise the system discards your changes.

- 7. Save the changes by pressing Ctrl+O and Enter. Exit the editor by pressing Ctrl+X.
- 8. Reload the changed configuration:
 - # systemctl daemon-reload
- 9. Check that your configuration is working:

systemctl show tangd.socket -p Listen Listen=[::]:7500 (Stream)

10. Start the **tangd** service:

systemctl restart tangd.socket

Because **tangd** uses the **systemd** socket activation mechanism, the server starts as soon as the first connection comes in. A new set of cryptographic keys is automatically generated at the first start. To perform cryptographic operations such as manual key generation, use the **jose** utility.

Verification

 On your NBDE client, verify that your Tang server works correctly by using the following command. The command must return the identical message you pass for encryption and decryption:

echo test | clevis encrypt tang '{"url":"<tang.server.example.com:7500>"}' -y | clevis decrypt test

Additional resources

• tang(8), semanage(8), firewall-cmd(1), jose(1), systemd.unit(5), and systemd.socket(5) man pages on your system

9.3. ROTATING TANG SERVER KEYS AND UPDATING BINDINGS ON CLIENTS

For security reasons, rotate your Tang server keys and update existing bindings on clients periodically. The precise interval at which you should rotate them depends on your application, key sizes, and institutional policy.

Alternatively, you can rotate Tang keys by using the **nbde_server** RHEL system role. See Using the nbde_server system role for setting up multiple Tang servers for more information.

Prerequisites

A Tang server is running.

• The **clevis** and **clevis-luks** packages are installed on your clients.

Procedure

1. Rename all keys in the /var/db/tang key database directory to have a leading . to hide them from advertisement. Note that the file names in the following example differs from unique file names in the key database directory of your Tang server:

```
# cd /var/db/tang
# ls -l
-rw-r--r--. 1 root root 349 Feb 7 14:55 UV6dqXSwe1bRKG3KbJmdiR020hY.jwk
-rw-r--r--. 1 root root 354 Feb 7 14:55 y9hxLTQSiSB5jSEGWnjhY8fDTJU.jwk
# mv UV6dqXSwe1bRKG3KbJmdiR020hY.jwk .UV6dqXSwe1bRKG3KbJmdiR020hY.jwk
# mv y9hxLTQSiSB5jSEGWnjhY8fDTJU.jwk .y9hxLTQSiSB5jSEGWnjhY8fDTJU.jwk
```

2. Check that you renamed and therefore hid all keys from the Tang server advertisement:

```
# Is -I
total 0
```

3. Generate new keys using the /usr/libexec/tangd-keygen command in /var/db/tang on the Tang server:

```
# /usr/libexec/tangd-keygen /var/db/tang
# ls /var/db/tang
3ZWS6-cDrCG61UPJS2BMmPU4I54.jwk zyLuX6hijUy_PSeUEFDi7hi38.jwk
```

4. Check that your Tang server advertises the signing key from the new key pair, for example:

```
# tang-show-keys 7500
3ZWS6-cDrCG61UPJS2BMmPU4I54
```

5. On your NBDE clients, use the **clevis luks report** command to check if the keys advertised by the Tang server remains the same. You can identify slots with the relevant binding using the **clevis luks list** command, for example:

```
# clevis luks list -d /dev/sda2
1: tang '{"url":"http://tang.srv"}'
# clevis luks report -d /dev/sda2 -s 1
...
Report detected that some keys were rotated.
Do you want to regenerate luks metadata with "clevis luks regen -d /dev/sda2 -s 1"? [ynYN]
```

6. To regenerate LUKS metadata for the new keys either press **y** to the prompt of the previous command, or use the **clevis luks regen** command:

```
# clevis luks regen -d /dev/sda2 -s 1
```

7. When you are sure that all old clients use the new keys, you can remove the old keys from the Tang server, for example:

```
# cd /var/db/tang
# rm .*.jwk
```



WARNING

Removing the old keys while clients are still using them can result in data loss. If you accidentally remove such keys, use the **clevis luks regen** command on the clients, and provide your LUKS password manually.

Additional resources

• tang-show-keys(1), clevis-luks-list(1), clevis-luks-report(1), and clevis-luks-regen(1) man pages on your system

9.4. CONFIGURING AUTOMATED UNLOCKING BY USING A TANG KEY IN THE WEB CONSOLE


You can configure automated unlocking of a LUKS-encrypted storage device using a key provided by a Tang server.

Prerequisites


- You have installed the RHEL 10 web console.
 For instructions, see Installing and enabling the web console.
- The **cockpit-storaged** and **clevis-luks** packages are installed on your system.
- The **cockpit.socket** service is running at port 9090.
- A Tang server is available. See Deploying a Tang server with SELinux in enforcing mode for details.
- You have **root** privileges or permissions to enter administrative commands with **sudo**.

Procedure

- Log in to the RHEL 10 web console.
 For details, see Logging in to the web console.
- 2. Switch to administrative access, provide your credentials, and click **Storage**. In the **Storage** table, click the disk that contains an encrypted volume you plan to add to unlock automatically.
- 3. In the following page with details of the selected disk, click + in the **Keys** section to add a Tang key:



4. Select **Tang keyserver** as **Key source**, provide the address of your Tang server, and a password that unlocks the LUKS-encrypted device. Click **Add** to confirm:



The following dialog window provides a command to verify that the key hash matches.

5. In a terminal on the Tang server, use the **tang-show-keys** command to display the key hash for comparison. In this example, the Tang server is running on the port *7500*:

tang-show-keys *7500* x100_1k6GPiDOaMIL3WbpCjHOy9ul1bSfdhl3M08wO0


6. Click **Trust key** when the key hashes in the web console and in the output of previously listed commands are the same:



After you select an encrypted root file system and a Tang server, you can skip adding the **rd.neednet=1** parameter to the kernel command line, installing the **clevis-dracut** package, and regenerating an initial RAM disk (**initrd**). For non-root file systems, the web console now enables the **remote-cryptsetup.target** and **clevis-luks-akspass.path systemd** units, installs the **clevis-systemd** package, and adds the **_netdev** parameter to the **fstab** and **crypttab** configuration files.

Verification

1. Check that the newly added Tang key is now listed in the **Keys** section with the **Keyserver** type:



2. Verify that the bindings are available for the early boot, for example:

Isinitrd | grep clevis-luks Irwxrwxrwx 1 root root 48 Jan 4 02:56 etc/system/cryptsetup.target.wants/clevis-luks-askpass.path -> /usr/lib/systemd/system/clevis-luks-askpass.path ...

Additional resources

Getting started using the RHEL web console

9.5. BASIC NBDE AND TPM2 ENCRYPTION-CLIENT OPERATIONS

The Clevis framework can encrypt plain-text files and decrypt both ciphertexts in the JSON Web Encryption (JWE) format and LUKS-encrypted block devices. Clevis clients can use either Tang network servers or Trusted Platform Module 2.0 (TPM 2.0) chips for cryptographic operations.

The following commands demonstrate the basic functionality provided by Clevis on examples containing plain-text files. You can also use them for troubleshooting your NBDE or Clevis+TPM deployments.

Encryption client bound to a Tang server

 To check that a Clevis encryption client binds to a Tang server, use the clevis encrypt tang sub-command:

\$ clevis encrypt tang '{"url":"http://tang.srv:port"}' < input-plain.txt > secret.jwe
The advertisement contains the following signing keys:

_Oslk0T-E2l6qjfdDiwVmidoZjA

Do you wish to trust these keys? [ynYN] y

Change the *http://tang.srv:port* URL in the previous example to match the URL of the server where **tang** is installed. The *secret.jwe* output file contains your encrypted cipher text in the JWE format. This cipher text is read from the *input-plain.txt* input file.

Alternatively, if your configuration requires a non-interactive communication with a Tang server without SSH access, you can download an advertisement and save it to a file:

\$ curl -sfg http://tang.srv:port/adv -o adv.jws

Use the advertisement in the **adv.jws** file for any following tasks, such as encryption of files or messages:

- \$ echo 'hello' | clevis encrypt tang '{"url":"http://tang.srv:port","adv":"adv.jws"}'
- To decrypt data, use the clevis decrypt command and provide the cipher text (JWE):
 - \$ clevis decrypt < secret.jwe > output-plain.txt

Encryption client using TPM 2.0

• To encrypt using a TPM 2.0 chip, use the **clevis encrypt tpm2** sub-command with the only argument in form of the JSON configuration object:

\$ clevis encrypt tpm2 '{}' < input-plain.txt > secret.jwe

To choose a different hierarchy, hash, and key algorithms, specify configuration properties, for example:

 $\label{thm:continuous} $\ clevis\ encrypt\ tpm2\ '{\ "hash":"sha256","key":"rsa"}' < input-plain.txt > secret.jwe $$$

• To decrypt the data, provide the ciphertext in the JSON Web Encryption (JWE) format:

\$ clevis decrypt < secret.jwe > output-plain.txt

The pin also supports sealing data to a Platform Configuration Registers (PCR) state. That way, the data can only be unsealed if the PCR hashes values match the policy used when sealing.

For example, to seal the data to the PCR with index 0 and 7 for the SHA-256 bank:

\$ clevis encrypt tpm2 '{"pcr_bank":"sha256","pcr_ids":"0,7"}' < input-plain.txt > secret.jwe



WARNING

Hashes in PCRs can be rewritten, and you no longer can unlock your encrypted volume. For this reason, add a strong passphrase that enable you to unlock the encrypted volume manually even when a value in a PCR changes.

If the system cannot automatically unlock your encrypted volume after an upgrade of the **shim-x64** package, follow the steps in the Clevis TPM2 no longer decrypts LUKS devices after a restart KCS article.

Additional resources

- clevis-encrypt-tang(1), clevis-luks-unlockers(7), clevis(1), and clevis-encrypt-tpm2(1) man pages on your system
- **clevis**, **clevis decrypt**, and **clevis encrypt tang** commands without any arguments show the built-in CLI help, for example:

\$ clevis encrypt tang
Usage: clevis encrypt tang CONFIG < PLAINTEXT > JWE
...

9.6. CONFIGURING NBDE CLIENTS FOR AUTOMATED UNLOCKING OF LUKS-ENCRYPTED VOLUMES

With the Clevis framework, you can configure clients for automated unlocking of LUKS-encrypted volumes when a selected Tang server is available. This creates an NBDE (Network-Bound Disk Encryption) deployment.

Prerequisites

A Tang server is running and available.

Procedure

1. To automatically unlock an existing LUKS-encrypted volume, install the clevis-luks subpackage:

dnf install clevis-luks

2. Identify the LUKS-encrypted volume for PBD. In the following example, the block device is referred as /dev/sda2:

3. Bind the volume to a Tang server using the **clevis luks bind** command:

```
# clevis luks bind -d /dev/sda2 tang '{"url":"http://tang.srv"}'
The advertisement contains the following signing keys:
```

Oslk0T-E2l6qjfdDiwVmidoZjA

Do you wish to trust these keys? [ynYN] y You are about to initialize a LUKS device for metadata storage. Attempting to initialize it may result in data loss if data was already written into the LUKS header gap in a different format. A backup is advised before initialization is performed.

Do you wish to initialize /dev/sda2? [yn] y Enter existing LUKS password:

This command performs four steps:

- a. Creates a new key with the same entropy as the LUKS master key.
- b. Encrypts the new key with Clevis.
- c. Stores the Clevis JWE object in the LUKS2 header token or uses LUKSMeta if the non-default LUKS1 header is used.
- d. Enables the new key for use with LUKS.



NOTE

The binding procedure assumes that the header contains at least one free LUKS password slot. The **clevis luks bind** command takes one of the slots.

Now, you can unlock the volume with your existing password as well as with the Clevis policy.

4. To enable the early boot system to process the disk binding, use the **dracut** tool on an already installed system. In RHEL, Clevis produces a generic **initrd** (initial RAM disk) without host-specific configuration options and does not automatically add parameters such as **rd.neednet=1**

to the kernel command line. If your configuration relies on a Tang pin that requires network during early boot, use the **--hostonly-cmdline** argument and **dracut** adds **rd.neednet=1** when it detects a Tang binding:

- a. Install the clevis-dracut package:
 - # dnf install clevis-dracut
- b. Regenerate the initial RAM disk:
 - # dracut -fv --regenerate-all --hostonly-cmdline
- c. Alternatively, create a .conf file in the /etc/dracut.conf.d/ directory, and add the hostonly_cmdline=yes option to the file. Then, you can use dracut without --hostonlycmdline, for example:

```
\# echo "hostonly_cmdline=yes" > /etc/dracut.conf.d/clevis.conf \# dracut -fv --regenerate-all
```

- d. You can also ensure that networking for a Tang pin is available during early boot by using the **grubby** tool on the system where Clevis is installed:
 - # grubby --update-kernel=ALL --args="rd.neednet=1"

Verification

 Verify that the Clevis JWE object is successfully placed in a LUKS header, use the clevis luks list command:

```
# clevis luks list -d /dev/sda2
1: tang '{"url":"http://tang.srv:port"}'
```

2. Check that the bindings are available for the early boot, for example:

```
# Isinitrd | grep clevis-luks

Irwxrwxrwx 1 root root 48 Jan 4 02:56

etc/systemd/system/cryptsetup.target.wants/clevis-luks-askpass.path ->

/usr/lib/systemd/system/clevis-luks-askpass.path

...
```

Additional resources

- clevis-luks-bind(1) and dracut.cmdline(7) man pages on your system
- Network boot options in the Boot options for RHEL Installer document
- Looking forward to Linux network configuration in the initial ramdisk (initrd) (Red Hat Enable Sysadmin)

9.7. CONFIGURING NBDE CLIENTS WITH STATIC IP CONFIGURATION

To use NBDE for clients with static IP configuration (without DHCP), you must pass your network configuration to the **dracut** tool manually.

Prerequisites

- A Tang server is running and available.
- The NBDE client is configured for automated unlocking of encrypted volumes by the Tang server.

For details, see Configuring NBDE clients for automated unlocking of LUKS-encrypted volumes .

Procedure

1. You can provide your static network configuration as a value for the **kernel-cmdline** option in a **dracut** command, for example:

```
# dracut -fv --regenerate-all --kernel-cmdline "ip=192.0.2.10::192.0.2.1:255.255.255.0::ens3:none nameserver=192.0.2.100"
```

2. Alternatively, create a .conf file in the /etc/dracut.conf.d/ directory with the static network information and then, regenerate the initial RAM disk image:

```
# cat /etc/dracut.conf.d/static_ip.conf
kernel_cmdline="ip=192.0.2.10::192.0.2.1:255.255.255.0::ens3:none
nameserver=192.0.2.100"
# dracut -fv --regenerate-all
```

9.8. CONFIGURING MANUAL ENROLLMENT OF LUKS-ENCRYPTED VOLUMES BY USING A TPM 2.0 POLICY

You can configure unlocking of LUKS-encrypted volumes by using a Trusted Platform Module 2.0 (TPM 2.0) policy.

Prerequisites

- An accessible TPM 2.0-compatible device.
- A system with the 64-bit Intel or 64-bit AMD architecture.

Procedure

1. To automatically unlock an existing LUKS-encrypted volume, install the **clevis-luks** subpackage:

```
# dnf install clevis-luks
```

2. Identify the LUKS-encrypted volume for PBD. In the following example, the block device is referred as /dev/sda2:

3. Bind the volume to a TPM 2.0 device using the **clevis luks bind** command, for example:

clevis luks bind -d /dev/sda2 tpm2 '{"hash":"sha256","key":"rsa"}' ...

Do you wish to initialize /dev/sda2? [yn] y
Enter existing LUKS password:

This command performs four steps:

- a. Creates a new key with the same entropy as the LUKS master key.
- b. Encrypts the new key with Clevis.
- c. Stores the Clevis JWE object in the LUKS2 header token or uses LUKSMeta if the non-default LUKS1 header is used.
- d. Enables the new key for use with LUKS.



NOTE

The binding procedure assumes that there is at least one free LUKS password slot. The **clevis luks bind** command takes one of the slots.

Alternatively, if you want to seal data to specific Platform Configuration Registers (PCR) states, add the **pcr_bank** and **pcr_ids** values to the **clevis luks bind** command, for example:

clevis luks bind -d /dev/sda2 tpm2 '{"hash":"sha256","key":"rsa","pcr_bank":"sha256","pcr_ids":"0,1"}'



IMPORTANT

Because the data can only be unsealed if PCR hashes values match the policy used when sealing and the hashes can be rewritten, add a strong passphrase that enable you to unlock the encrypted volume manually when a value in a PCR changes.

If the system cannot automatically unlock your encrypted volume after an upgrade of the **shim-x64** package, follow the steps in the Clevis TPM2 no longer decrypts LUKS devices after a restart KCS article.

- 4. The volume can now be unlocked with your existing password as well as with the Clevis policy.
- 5. To enable the early boot system to process the disk binding, use the **dracut** tool on an already installed system:

dnf install clevis-dracut # dracut -fv --regenerate-all

Verification

1. To verify that the Clevis JWE object is successfully placed in a LUKS header, use the **clevis luks list** command:

-

```
# clevis luks list -d /dev/sda2
1: tpm2 '{"hash":"sha256","key":"rsa"}'
```

Additional resources

• clevis-luks-bind(1), clevis-encrypt-tpm2(1), and dracut.cmdline(7) man pages on your system

9.9. REMOVING A CLEVIS PIN FROM A LUKS-ENCRYPTED VOLUME MANUALLY

You can manually remove the metadata created by the **clevis luks bind** command and also wipe a key slot that contains passphrase added by Clevis.



IMPORTANT

The recommended way to remove a Clevis pin from a LUKS-encrypted volume is through the **clevis luks unbind** command. The removal procedure using **clevis luks unbind** consists of only one step and works for both LUKS1 and LUKS2 volumes. The following example command removes the metadata created by the binding step and wipe the key slot **1** on the /dev/sda2 device:

clevis luks unbind -d /dev/sda2 -s 1

Prerequisites

• A LUKS-encrypted volume with a Clevis binding.

Procedure

1. Check which LUKS version the volume, for example /dev/sda2, is encrypted by and identify a slot and a token that is bound to Clevis:

```
# cryptsetup luksDump /dev/sda2
LUKS header information
Version: 2
...
Keyslots: 0: luks2
...
1: luks2
   Key: 512 bits
   Priority: normal
   Cipher: aes-xts-plain64
...
   Tokens: 0: clevis
   Keyslot: 1
...
```

In the previous example, the Clevis token is identified by **0** and the associated key slot is **1**.

2. In case of LUKS2 encryption, remove the token:

cryptsetup token remove --token-id 0 /dev/sda2

3. If your device is encrypted by LUKS1, which is indicated by the **Version: 1** string in the output of the **cryptsetup luksDump** command, perform this additional step with the **luksmeta wipe** command:

luksmeta wipe -d /dev/sda2 -s 1

4. Wipe the key slot containing the Clevis passphrase:

cryptsetup luksKillSlot /dev/sda2 1

Additional resources

• clevis-luks-unbind(1), cryptsetup(8), and luksmeta(8) man pages on your system

9.10. CONFIGURING AUTOMATED ENROLLMENT OF LUKS-ENCRYPTED VOLUMES BY USING KICKSTART

You can configure an automated installation process that uses Clevis for the enrollment of LUKS-encrypted volumes.

Procedure

1. Instruct Kickstart to partition the disk such that LUKS encryption has enabled for all mount points, other than /boot, with a temporary password. The password is temporary for this step of the enrollment process.

```
part /boot --fstype="xfs" --ondisk=vda --size=256
part / --fstype="xfs" --ondisk=vda --grow --encrypted --passphrase=temppass
```

Note that OSPP-compliant systems require a more complex configuration, for example:

```
part /boot --fstype="xfs" --ondisk=vda --size=256
part / --fstype="xfs" --ondisk=vda --size=2048 --encrypted --passphrase=temppass
part /var --fstype="xfs" --ondisk=vda --size=1024 --encrypted --passphrase=temppass
part /tmp --fstype="xfs" --ondisk=vda --size=1024 --encrypted --passphrase=temppass
part /home --fstype="xfs" --ondisk=vda --size=2048 --grow --encrypted --
passphrase=temppass
part /var/log --fstype="xfs" --ondisk=vda --size=1024 --encrypted --passphrase=temppass
part /var/log/audit --fstype="xfs" --ondisk=vda --size=1024 --encrypted --
passphrase=temppass
```

2. Install the related Clevis packages by listing them in the **%packages** section:

%packages clevis-dracut clevis-luks clevis-systemd %end

- 3. Optional: To ensure that you can unlock the encrypted volume manually when required, add a strong passphrase before you remove the temporary passphrase. See the How to add a passphrase, key, or keyfile to an existing LUKS device article for more information.
- 4. Call **clevis luks bind** to perform binding in the **%post** section. Afterward, remove the temporary password:

```
%post clevis luks bind -y -k - -d /dev/vda2 \ tang '{"url":"http://tang.srv"}' <<< "temppass" cryptsetup luksRemoveKey /dev/vda2 <<< "temppass" dracut -fv --regenerate-all %end
```

If your configuration relies on a Tang pin that requires network during early boot or you use NBDE clients with static IP configurations, you have to modify the **dracut** command as described in Configuring NBDE clients with static IP configuration.



WARNING

The **cryptsetup luksRemoveKey** command prevents any further administration of a LUKS2 device on which you apply it. You can recover a removed master key using the **dmsetup** command only for LUKS1 devices.

You can use an analogous procedure when using a TPM 2.0 policy instead of a Tang server.

Additional resources

- clevis(1), clevis-luks-bind(1), cryptsetup(8), and dmsetup(8) man pages on your system
- Automatically installing RHEL

9.11. CONFIGURING AUTOMATED UNLOCKING OF A LUKS-ENCRYPTED REMOVABLE STORAGE DEVICE

You can set up an automated unlocking process of a LUKS-encrypted USB storage device.

Procedure

- 1. To automatically unlock a LUKS-encrypted removable storage device, such as a USB drive, install the **clevis-udisks2** package:
 - # dnf install clevis-udisks2
- Reboot the system, and then perform the binding step using the clevis luks bind command as described in Configuring NBDE clients for automated unlocking of LUKS-encrypted volumes, for example:

clevis luks bind -d /dev/sdb1 tang '{"url":"http://tang.srv"}'

3. The LUKS-encrypted removable device can be now unlocked automatically in your GNOME desktop session. The device bound to a Clevis policy can be also unlocked by the **clevis luks unlock** command:

clevis luks unlock -d /dev/sdb1

You can use an analogous procedure when using a TPM 2.0 policy instead of a Tang server.

Additional resources

• clevis-luks-unlockers(7) man page on your system

9.12. DEPLOYING HIGH-AVAILABILITY NBDE SYSTEMS

Tang provides two methods for building a high-availability deployment:

Client redundancy (recommended)

Clients should be configured with the ability to bind to multiple Tang servers. In this setup, each Tang server has its own keys and clients can decrypt by contacting a subset of these servers. Clevis already supports this workflow through its **sss** plug-in. Red Hat recommends this method for a high-availability deployment.

Key sharing

For redundancy purposes, more than one instance of Tang can be deployed. To set up a second or any subsequent instance, install the **tang** packages and copy the key directory to the new host using **rsync** over **SSH**. Note that Red Hat does not recommend this method because sharing keys increases the risk of key compromise and requires additional automation infrastructure.

High-available NBDE using Shamir's Secret Sharing

Shamir's Secret Sharing (SSS) is a cryptographic scheme that divides a secret into several unique parts. To reconstruct the secret, a number of parts is required. The number is called threshold and SSS is also referred to as a thresholding scheme.

Clevis provides an implementation of SSS. It creates a key and divides it into a number of pieces. Each piece is encrypted using another pin including even SSS recursively. Additionally, you define the threshold \mathbf{t} . If an NBDE deployment decrypts at least \mathbf{t} pieces, then it recovers the encryption key and the decryption process succeeds. When Clevis detects a smaller number of parts than specified in the threshold, it prints an error message.

Example 1: Redundancy with two Tang servers

The following command decrypts a LUKS-encrypted device when at least one of two Tang servers is available:

```
# clevis luks bind -d /dev/sda1 sss '{"t":1,"pins":{"tang":[{"url":"http://tang1.srv"}, {"url":"http://tang2.srv"}]}}'
```

The previous command used the following configuration scheme:

In this configuration, the SSS threshold **t** is set to **1** and the **clevis luks bind** command successfully reconstructs the secret if at least one from two listed **tang** servers is available.

Example 2: Shared secret on a Tang server and a TPM device

The following command successfully decrypts a LUKS-encrypted device when both the **tang** server and the **tpm2** device are available:

```
# clevis luks bind -d /dev/sda1 sss '{"t":2,"pins":{"tang":[{"url":"http://tang1.srv"}], "tpm2": {"pcr_ids":"0,7"}}}'
```

The configuration scheme with the SSS threshold 't' set to '2' is now:

```
{
    "t":2,
    "pins":{
        "tang":[
            {
                 "url":"http://tang1.srv"
            }
        ],
        "tpm2":{
                 "pcr_ids":"0,7"
        }
    }
}
```

Additional resources

• tang(8) (section High Availability), clevis(1) (section Shamir's Secret Sharing), and clevisencrypt-sss(1) man pages on your system

9.13. DEPLOYMENT OF VIRTUAL MACHINES IN A NBDE NETWORK

The **clevis luks bind** command does not change the LUKS master key. This implies that if you create a LUKS-encrypted image for use in a virtual machine or cloud environment, all the instances that run this image share a master key. This is extremely insecure and should be avoided at all times.

This is not a limitation of Clevis but a design principle of LUKS. If your scenario requires having encrypted root volumes in a cloud, perform the installation process (usually using Kickstart) for each instance of Red Hat Enterprise Linux in the cloud as well. The images cannot be shared without also sharing a LUKS master key.

To deploy automated unlocking in a virtualized environment, use systems such as **lorax** or **virt-install** together with a Kickstart file (see Configuring automated enrollment of LUKS-encrypted volumes using Kickstart) or another automated provisioning tool to ensure that each encrypted VM has a unique master key.

Additional resources

• clevis-luks-bind(1) man page on your system

9.14. BUILDING AUTOMATICALLY-ENROLLABLE VM IMAGES FOR CLOUD ENVIRONMENTS BY USING NBDE

Deploying automatically-enrollable encrypted images in a cloud environment can provide a unique set of challenges. Like other virtualization environments, it is recommended to reduce the number of instances started from a single image to avoid sharing the LUKS master key.

Therefore, the best practice is to create customized images that are not shared in any public repository and that provide a base for the deployment of a limited amount of instances. The exact number of instances to create should be defined by deployment's security policies and based on the risk tolerance associated with the LUKS master key attack vector.

To build LUKS-enabled automated deployments, systems such as Lorax or virt-install together with a Kickstart file should be used to ensure master key uniqueness during the image building process.

Cloud environments enable two Tang server deployment options which we consider here. First, the Tang server can be deployed within the cloud environment itself. Second, the Tang server can be deployed outside of the cloud on independent infrastructure with a VPN link between the two infrastructures.

Deploying Tang natively in the cloud does allow for easy deployment. However, given that it shares infrastructure with the data persistence layer of ciphertext of other systems, it may be possible for both the Tang server's private key and the Clevis metadata to be stored on the same physical disk. Access to this physical disk permits a full compromise of the ciphertext data.



IMPORTANT

Always maintain a physical separation between the location where the data is stored and the system where Tang is running. This separation between the cloud and the Tang server ensures that the Tang server's private key cannot be accidentally combined with the Clevis metadata. It also provides local control of the Tang server if the cloud infrastructure is at risk.

9.15. DEPLOYING TANG AS A CONTAINER

The **tang** container image provides Tang-server decryption capabilities for Clevis clients that run either in OpenShift Container Platform (OCP) clusters or in separate virtual machines.

Prerequisites

- The **podman** package and its dependencies are installed on the system.
- You have logged in on the registry.redhat.io container catalog using the podman login registry.redhat.io command. See Red Hat Container Registry Authentication for more information.
- The Clevis client is installed on systems containing LUKS-encrypted volumes that you want to automatically unlock by using a Tang server.

Procedure

1. Pull the **tang** container image from the **registry.redhat.io** registry:

podman pull registry.redhat.io/rhel10/tang

2. Run the container, specify its port, and specify the path to the Tang keys. The previous example runs the **tang** container, specifies the port *7500*, and indicates a path to the Tang keys of the /var/db/tang directory:

podman run -d -p 7500:7500 -v tang-keys:/var/db/tang --name tang registry.redhat.io/rhel10/tang

Note that Tang uses port 80 by default but this may collide with other services such as the Apache HTTP server.

3. Optional: For increased security, rotate the Tang keys periodically. You can use the **tangd-rotate-keys** script, for example:

podman run --rm -v tang-keys:/var/db/tang registry.redhat.io/rhel10/tang tangd-rotate-keys -v -d /var/db/tang

Rotated key 'rZAMKAseaXBe0rcKXL1hCClq-DY.jwk' -> .'rZAMKAseaXBe0rcKXL1hCClq-DY.jwk'

Rotated key 'x1Alpc6WmnCU-CabD8_4q18vDuw.jwk' -> .'x1Alpc6WmnCU-

CabD8_4q18vDuw.jwk'

Created new key GrMMX_WfdqomIU_4RyjpcdIXb0E.jwk

Created new key dTTfn17sZZqVAp80u3ygFDHtjk.jwk

Keys rotated successfully.

Verification

 On a system that contains LUKS-encrypted volumes for automated unlocking by the presence of the Tang server, check that the Clevis client can encrypt and decrypt a plain-text message using Tang:

echo test | clevis encrypt tang '{"url":"http://localhost:7500"}' | clevis decrypt The advertisement contains the following signing keys:

x1Alpc6WmnCU-CabD8_4q18vDuw

Do you wish to trust these keys? [ynYN] y test

The previous example command shows the **test** string at the end of its output when a Tang server is available on the *localhost* URL and communicates through port *7500*.

Additional resources

• podman(1), clevis(1), and tang(8) man pages on your system

9.16. CONFIGURING NBDE BY USING RHEL SYSTEM ROLES

You can use the **nbde_client** and **nbde_server** RHEL system roles for automated deployments of Policy-Based Decryption (PBD) solutions by using Clevis and Tang. The **rhel-system-roles** package contains these system roles, the related examples, and also the reference documentation.

9.16.1. Using the nbde server RHEL system role for setting up multiple Tang servers

By using the **nbde_server** system role, you can deploy and manage a Tang server as part of an automated disk encryption solution. This role supports the following features:

- Rotating Tang keys
- Deploying and backing up Tang keys

Prerequisites

- You have prepared the control node and the managed nodes
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

```
---
- name: Deploy a Tang server
hosts: tang.server.example.com
tasks:
- name: Install and configure periodic key rotation
ansible.builtin.include_role:
    name: rhel-system-roles.nbde_server
vars:
    nbde_server_rotate_keys: yes
    nbde_server_manage_firewall: true
    nbde_server_manage_selinux: true
```

This example playbook ensures deploying of your Tang server and a key rotation.

The settings specified in the example playbook include the following:

```
nbde_server_manage_firewall: true
```

Use the **firewall** system role to manage ports used by the **nbde_server** role.

```
nbde server manage selinux: true
```

Use the **selinux** system role to manage ports used by the **nbde_server** role. For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.nbde_server/README.md file on the control node.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

 On your NBDE client, verify that your Tang server works correctly by using the following command. The command must return the identical message you pass for encryption and decryption:

ansible managed-node-01.example.com -m command -a 'echo test | clevis encrypt tang '{"url":"<tang.server.example.com>"}' -y | clevis decrypt' test

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.nbde_server/README.md file
- /usr/share/doc/rhel-system-roles/nbde_server/ directory

9.16.2. Setting up Clevis clients with DHCP by using the nbde_client RHEL system role

The **nbde_client** system role enables you to deploy multiple Clevis clients in an automated way.

This role supports binding a LUKS-encrypted volume to one or more Network-Bound (NBDE) servers - Tang servers. You can either preserve the existing volume encryption with a passphrase or remove it. After removing the passphrase, you can unlock the volume only using NBDE. This is useful when a volume is initially encrypted using a temporary key or password that you should remove after you provision the system.

If you provide both a passphrase and a key file, the role uses what you have provided first. If it does not find any of these valid, it attempts to retrieve a passphrase from an existing binding.

Policy-Based Decryption (PBD) defines a binding as a mapping of a device to a slot. This means that you can have multiple bindings for the same device. The default slot is slot 1.



NOTE

The **nbde_client** system role supports only Tang bindings. Therefore, you cannot use it for TPM2 bindings.

Prerequisites

- You have prepared the control node and the managed nodes
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- A volume that is already encrypted by using LUKS.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:



 name: Configure clients for unlocking of encrypted volumes by Tang servers hosts: managed-node-01.example.com tasks:

- name: Create NBDE client bindings ansible.builtin.include role:

name: rhel-system-roles.nbde_client

vars:

nbde_client_bindings:

- device: /dev/rhel/root

encryption key src: /etc/luks/keyfile

nbde_client_early_boot: true

state: present servers:

- http://server1.example.com
- http://server2.example.com
- device: /dev/rhel/swap encryption_key_src: /etc/luks/keyfile servers:
 - http://server1.example.com
 - http://server2.example.com

This example playbook configures Clevis clients for automated unlocking of two LUKS-encrypted volumes when at least one of two Tang servers is available.

The settings specified in the example playbook include the following:

state: present

The values of **state** indicate the configuration after you run the playbook. Use the **present** value for either creating a new binding or updating an existing one. Contrary to a **clevis luks bind** command, you can use **state: present** also for overwriting an existing binding in its device slot. The **absent** value removes a specified binding.

nbde_client_early_boot: true

The **nbde_client** role ensures that networking for a Tang pin is available during early boot by default. If you scenario requires to disable this feature, add the **nbde_client_early_boot: false** variable to your playbook.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.nbde_client/README.md file on the control node.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

Verification

1. On your NBDE client, check that the encrypted volume that should be automatically unlocked by your Tang servers contain the corresponding information in its LUKS pins:

```
# ansible managed-node-01.example.com -m command -a 'clevis luks list -d /dev/rhel/root'
1: tang '{"url":"<http://server1.example.com/>"}'
2: tang '{"url":"<http://server2.example.com/>"}'
```

2. If you do not use the **nbde_client_early_boot: false** variable, verify that the bindings are available for the early boot, for example:

```
# ansible managed-node-01.example.com -m command -a 'lsinitrd | grep clevis-luks' lrwxrwxrwx 1 root root 48 Jan 4 02:56 etc/system/cryptsetup.target.wants/clevis-luks-askpass.path -> /usr/lib/system/clevis-luks-askpass.path ...
```

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.nbde_client/README.md file
- /usr/share/doc/rhel-system-roles/nbde_client/ directory

9.16.3. Setting up static-IP Clevis clients by using the nbde_client RHEL system role

The **nbde_client** RHEL system role supports only scenarios with Dynamic Host Configuration Protocol (DHCP). On an NBDE client with static IP configuration, you must pass your network configuration as a kernel boot parameter.

Typically, administrators want to reuse a playbook and not maintain individual playbooks for each host to which Ansible assigns static IP addresses during early boot. In this case, you can use variables in the playbook and provide the settings in an external file. As a result, you need only one playbook and one file with the settings.

Prerequisites

- You have prepared the control node and the managed nodes
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- A volume that is already encrypted by using LUKS.

Procedure

 Create a file with the network settings of your hosts, for example, static-ip-settingsclients.yml, and add the values you want to dynamically assign to the hosts:

```
clients:
managed-node-01.example.com:
ip_v4: 192.0.2.1
gateway_v4: 192.0.2.254
netmask_v4: 255.255.255.0
interface: enp1s0
managed-node-02.example.com:
ip_v4: 192.0.2.2
```

gateway_v4: 192.0.2.254 netmask_v4: 255.255.255.0

interface: enp1s0

2. Create a playbook file, for example, ~/playbook.yml, with the following content:

```
    name: Configure clients for unlocking of encrypted volumes by Tang servers
hosts: managed-node-01.example.com,managed-node-02.example.com
vars files:
```

- ~/static-ip-settings-clients.yml

tasks:

 name: Create NBDE client bindings ansible.builtin.include role:

name: rhel-system-roles.network

vars:

nbde_client_bindings:

- device: /dev/rhel/root

encryption_key_src: /etc/luks/keyfile

servers:

http://server1.example.com

- http://server2.example.com

- device: /dev/rhel/swap

encryption_key_src: /etc/luks/keyfile

servers:

- http://server1.example.com

- http://server2.example.com

 name: Configure a Clevis client with static IP address during early boot ansible.builtin.include role:

name: rhel-system-roles.bootloader

vars:

bootloader_settings:

kernel: ALL options:name: ip

value: "{{ clients[inventory_hostname]['ip_v4'] }}::{{ clients[inventory_hostname]}

['gateway_v4'] }}:{{ clients[inventory_hostname]['netmask_v4'] }}::{{ clients[inventory_hostname]['interface'] }}:none"

This playbook reads certain values dynamically for each host listed in the ~/static-ip-settings-clients.yml file.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.network/README.md file on the control node.

3. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

4. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.nbde_client/README.md file
- /usr/share/doc/rhel-system-roles/nbde_client/ directory
- Looking forward to Linux network configuration in the initial ramdisk (initrd) (Red Hat Enable Sysadmin)

CHAPTER 10. BLOCKING AND ALLOWING APPLICATIONS BY USING FAPOLICYD

Setting and enforcing a policy that either allows or denies application execution based on a rule set efficiently prevents the execution of unknown and potentially malicious software.

10.1. INTRODUCTION TO FAPOLICYD

The **fapolicyd** software framework controls the execution of applications based on a user-defined policy. This is one of the most efficient ways to prevent running untrusted and possibly malicious applications on the system.

The **fapolicyd** framework provides the following components:

- fapolicyd service
- fapolicyd command-line utilities
- fapolicyd RPM plugin
- fapolicyd rule language
- fagenrules script

The administrator can define the **allow** and **deny** execution rules for any application with the possibility of auditing based on a path, hash, MIME type, or trust.

The **fapolicyd** framework introduces the concept of trust. An application is trusted when it is properly installed by the system package manager, and therefore it is registered in the system RPM database. The **fapolicyd** daemon uses the RPM database as a list of trusted binaries and scripts. The **fapolicyd** RPM plugin registers any system update that is handled by either the {PackageManagerName} package manager or the RPM Package Manager. The plugin notifies the **fapolicyd** daemon about changes in this database. Other ways of adding applications require the creation of custom rules and restarting the **fapolicyd** service.

The **fapolicyd** service configuration is located in the /etc/fapolicyd/ directory with the following structure:

- The /etc/fapolicyd/fapolicyd.trust file contains a list of trusted files. You can also use multiple trust files in the /etc/fapolicyd/trust.d/ directory.
- The /etc/fapolicyd/rules.d/ directory for files containing allow and deny execution rules. The fagenrules script merges these component rules files to the /etc/fapolicyd/compiled.rules file.
- The **fapolicyd.conf** file contains the daemon's configuration options. This file is useful primarily for performance-tuning purposes.

Rules in /etc/fapolicyd/rules.d/ are organized in several files, each representing a different policy goal. The numbers at the beginning of the corresponding file names determine the order in /etc/fapolicyd/compiled.rules:

10

Language rules.

20

Dracut-related Rules.

21 rules for updaters. 30 Patterns. 40 FLF rules. 41 Shared objects rules. 42 Trusted ELF rules. 70 Trusted language rules. 72 Shell rules. 90 Deny execute rules. 95

You can use one of the following ways for **fapolicyd** integrity checking:

• File-size checking

Allow open rules.

- Comparing SHA-256 hashes
- Integrity Measurement Architecture (IMA) subsystem

By default, **fapolicyd** does no integrity checking. Integrity checking based on the file size is fast, but an attacker can replace the content of the file and preserve its byte size. Computing and checking SHA-256 checksums is more secure, but it affects the performance of the system. The **integrity = ima** option in **fapolicyd.conf** requires support for files extended attributes (also known as **xattr**) on all file systems containing executable files.

Additional resources

- fapolicyd(8), fapolicyd.rules(5), fapolicyd.conf(5), fapolicyd.trust(13), fagenrules(8), and fapolicyd-cli(1) man pages on your system
- Enhancing security with the kernel integrity subsystem chapter in the Managing, monitoring, and updating the kernel document
- Documentation installed with the fapolicyd package in the /usr/share/doc/fapolicyd/ directory and the /usr/share/fapolicyd/sample-rules/README-rules file

10.2. DEPLOYING FAPOLICYD

When deploying the **fapolicyd** application allowlisting framework, you can either try your configuration in permissive mode first or directly enable the service in the default configuration.

Procedure

- 1. Install the **fapolicyd** package:
 - # dnf install fapolicyd
- 2. Optional: To try your configuration first, change mode to permissive.
 - a. Open the /etc/fapolicyd/fapolicyd.conf file in a text editor of your choice, for example:
 - # vi /etc/fapolicyd/fapolicyd.conf
 - b. Change the value of the **permissive** option from **0** to **1**, save the file, and exit the editor:
 - permissive = 1

Alternatively, you can debug your configuration by using the **fapolicyd --debug-deny --permissive** command before you start the service. See the Troubleshooting problems related to fapolicyd section for more information.

- 3. Enable and start the **fapolicyd** service:
 - # systemctl enable --now fapolicyd
- 4. If you enabled permissive mode through /etc/fapolicyd/fapolicyd.conf:
 - a. Set the Audit service for recording **fapolicyd** events:
 - # auditctl -w /etc/fapolicyd/ -p wa -k fapolicyd_changes # service try-restart auditd
 - b. Use your applications.
 - c. Check Audit logs for **fanotify** denials, for example:
 - # ausearch -ts recent -m fanotify
 - d. When debugged, disable permissive mode by changing the corresponding value back to **permissive = 0**, and restart the service:
 - # systemctl restart fapolicyd

Verification

1. Verify that the **fapolicyd** service is running correctly:

systemctl status fapolicyd

fapolicyd.service - File Access Policy Daemon
 Loaded: loaded (/usr/lib/systemd/system/fapolicyd.service; enabled; preset: disabled)
 Active: active (running) since Tue 2024-10-08 05:53:50 EDT; 11s ago

Oct 08 05:53:51 machine1.example.com fapolicyd[4974]: Loading trust data from rpmdb backend

Oct 08 05:53:51 machine1.example.com fapolicyd[4974]: Loading trust data from file backend

Oct 08 05:53:51 machine1.example.com fapolicyd[4974]: Starting to listen for events

2. Log in as a user without root privileges, and check that **fapolicyd** is working, for example:

\$ cp /bin/ls /tmp \$ /tmp/ls

bash: /tmp/ls: Operation not permitted

10.3. MARKING FILES AS TRUSTED USING AN ADDITIONAL SOURCE OF TRUST

The **fapolicyd** framework trusts files contained in the RPM database. You can mark additional files as trusted by adding the corresponding entries to the **/etc/fapolicyd/fapolicyd.trust** plain-text file or the **/etc/fapolicyd/trust.d/** directory, which supports separating a list of trusted files into more files. You can modify **fapolicyd.trust** or the files in **/etc/fapolicyd/trust.d** either directly using a text editor or through **fapolicyd-cli** commands.



NOTE

Marking files as trusted using **fapolicyd.trust** or **trust.d**/ is better than writing custom **fapolicyd** rules due to performance reasons.

Prerequisites

• The **fapolicyd** framework is deployed on your system.

Procedure

1. Copy your custom binary to the required directory, for example:

\$ cp /bin/ls /tmp

\$ /tmp/ls

bash: /tmp/ls: Operation not permitted

2. Mark your custom binary as trusted, and store the corresponding entry to the **myapp** file in /etc/fapolicyd/trust.d/:

fapolicyd-cli --file add /tmp/ls --trust-file myapp

- If you skip the **--trust-file** option, then the previous command adds the corresponding line to /etc/fapolicyd/fapolicyd.trust.
- To mark all existing files in a directory as trusted, provide the directory path as an argument of the --file option, for example: fapolicyd-cli --file add /tmp/my_bin_dir/ --trust-file myapp.
- 3. Update the fapolicyd database:

fapolicyd-cli --update



NOTE

Changing the content of a trusted file or directory changes their checksum, and therefore **fapolicyd** no longer considers them trusted.

To make the new content trusted again, refresh the file trust database by using the **fapolicyd-cli --file update** command. If you do not provide any argument, the entire database refreshes. Alternatively, you can specify a path to a specific file or directory. Then, update the database by using **fapolicyd-cli --update**.

Verification

1. Check that your custom binary can be now executed, for example:

\$ /tmp/ls ls

Additional resources

• fapolicyd.trust(13) man page on your system

10.4. ADDING CUSTOM ALLOW AND DENY RULES FOR FAPOLICYD

The default set of rules in the **fapolicyd** package does not affect system functions. For custom scenarios, such as storing binaries and scripts in a non-standard directory or adding applications without the **dnf** or **rpm** installers, you must either mark additional files as trusted or add new custom rules.

For basic scenarios, prefer Marking files as trusted using an additional source of trust. In more advanced scenarios such as allowing to execute a custom binary only for specific user and group identifiers, add new custom rules to the /etc/fapolicyd/rules.d/ directory.

The following steps demonstrate adding a new rule to allow a custom binary.

Prerequisites

• The **fapolicyd** framework is deployed on your system.

Procedure

1. Copy your custom binary to the required directory, for example:

\$ cp /bin/ls /tmp \$ /tmp/ls bash: /tmp/ls: Operation not permitted

2. Stop the **fapolicyd** service:

systemctl stop fapolicyd

3. Use debug mode to identify a corresponding rule. Because the output of the **fapolicyd --debug** command is verbose and you can stop it only by pressing **Ctrl+C** or killing the corresponding process, redirect the error output to a file. In this case, you can limit the output only to access denials by using the **--debug-deny** option instead of **--debug**:

```
# fapolicyd --debug-deny 2> fapolicy.output & [1] 51341
```

Alternatively, you can run fapolicyd debug mode in another terminal.

4. Repeat the command that **fapolicyd** denied:

```
$ /tmp/ls
bash: /tmp/ls: Operation not permitted
```

5. Stop debug mode by resuming it in the foreground and pressing **Ctrl+C**:

```
# fg
fapolicyd --debug 2> fapolicy.output
^C
...
```

Alternatively, kill the process of **fapolicyd** debug mode:

```
# kill 51341
```

6. Find a rule that denies the execution of your application:

```
# cat fapolicy.output | grep 'deny_audit' ...
rule=13 dec=deny_audit perm=execute auid=0 pid=6855 exe=/usr/bin/bash : path=/tmp/ls
ftype=application/x-executable trust=0
```

7. Locate the file that contains a rule that prevented the execution of your custom binary. In this case, the **deny_audit perm=execute** rule belongs to the **90-deny-execute.rules** file:

```
# Is /etc/fapolicyd/rules.d/
10-languages.rules 40-bad-elf.rules 72-shell.rules
20-dracut.rules 41-shared-obj.rules 90-deny-execute.rules
21-updaters.rules 42-trusted-elf.rules 95-allow-open.rules
30-patterns.rules 70-trusted-lang.rules

# cat /etc/fapolicyd/rules.d/90-deny-execute.rules
# Deny execution for anything untrusted

deny_audit perm=execute all : all
```

8. Add a new **allow** rule to the file that lexically *precedes* the rule file that contains the rule that denied the execution of your custom binary in the /etc/fapolicyd/rules.d/ directory:

```
# touch /etc/fapolicyd/rules.d/80-myapps.rules
# vi /etc/fapolicyd/rules.d/80-myapps.rules
```

Insert the following rule to the **80-myapps.rules** file:

allow perm=execute exe=/usr/bin/bash trust=1 : path=/tmp/ls ftype=application/x-executable trust=0

Alternatively, you can allow executions of all binaries in the /tmp directory by adding the following rule to the rule file in /etc/fapolicyd/rules.d/:

allow perm=execute exe=/usr/bin/bash trust=1 : dir=/tmp/ trust=0



IMPORTANT

To make a rule effective recursively on all directories under the specified directory, add a trailing slash to the value of the **dir=** parameter in the rule (/**tmp**/ in the previous example).

9. To prevent changes in the content of your custom binary, define the required rule using an SHA-256 checksum:

\$ sha256sum /tmp/ls 780b75c90b2d41ea41679fcb358c892b1251b68d1927c80fbc0d9d148b25e836 Is

Change the rule to the following definition:

allow perm=execute exe=/usr/bin/bash trust=1 : sha256hash=*780b75c90b2d41ea41679fcb358c892b1251b68d1927c80fbc0d9d148b25e836*

10. Check that the list of compiled differs from the rule set in /etc/fapolicyd/rules.d/, and update the list, which is stored in the /etc/fapolicyd/compiled.rules file:

```
# fagenrules --check
/usr/sbin/fagenrules: Rules have changed and should be updated
# fagenrules --load
```

11. Check that your custom rule is in the list of **fapolicyd** rules before the rule that prevented the execution:

```
# fapolicyd-cli --list
...

13. allow perm=execute exe=/usr/bin/bash trust=1 : path=/tmp/ls ftype=application/x-executable trust=0

14. deny_audit perm=execute all : all
...
```

12. Start the **fapolicyd** service:

systemctl start fapolicyd

Verification

1. Check that your custom binary can be now executed, for example:

```
$ /tmp/ls
ls
```

Additional resources

- fapolicyd.rules(5) and fapolicyd-cli(1) man pages on your system
- Documentation installed with the fapolicyd package in the /usr/share/fapolicyd/samplerules/README-rules file

10.5. ENABLING FAPOLICYD INTEGRITY CHECKS

By default, **fapolicyd** does not perform integrity checking. You can configure **fapolicyd** to perform integrity checks by comparing either file sizes or SHA-256 hashes. You can also set integrity checks by using the Integrity Measurement Architecture (IMA) subsystem.

Prerequisites

• The **fapolicyd** framework is deployed on your system.

Procedure

- 1. Open the /etc/fapolicyd/fapolicyd.conf file in a text editor of your choice, for example:
 - # vi /etc/fapolicyd/fapolicyd.conf
- 2. Change the value of the **integrity** option from **none** to **sha256**, save the file, and exit the editor:
 - integrity = sha256
- 3. Restart the **fapolicyd** service:
 - # systemctl restart fapolicyd

Verification

- 1. Back up the file used for the verification:
 - # cp /bin/more /bin/more.bak
- 2. Change the content of the /bin/more binary:
 - # cat /bin/less > /bin/more
- 3. Use the changed binary as a regular user:

su *example.user* \$ /bin/more /etc/redhat-release bash: /bin/more: Operation not permitted

4. Revert the changes:

mv -f /bin/more.bak /bin/more

10.6. TROUBLESHOOTING PROBLEMS RELATED TO FAPOLICYD

The **fapolicyd** application framework provides tools for troubleshooting the most common problems and you can also add applications installed with the **rpm** command to the trust database.

Installing applications by using rpm

- If you install an application by using the **rpm** command, you have to perform a manual refresh of the **fapolicyd** RPM database:
 - 1. Install your application:
 - # rpm -i application.rpm
 - 2. Refresh the database:
 - # fapolicyd-cli --update

If you skip this step, the system can freeze and must be restarted.

Service status

- If **fapolicyd** does not work correctly, check the service status:
 - # systemctl status fapolicyd

fapolicyd-cli checks and listings

• The **--check-config**, **--check-watch_fs**, and **--check-trustdb** options help you find syntax errors, not-yet-watched file systems, and file mismatches, for example:

```
# fapolicyd-cli --check-config
Daemon config is OK

# fapolicyd-cli --check-trustdb

/etc/selinux/targeted/contexts/files/file_contexts miscompares: size sha256

/etc/selinux/targeted/policy/policy.31 miscompares: size sha256
```

• Use the **--list** option to check the current list of rules and their order:

```
# fapolicyd-cli --list
...

9. allow perm=execute all : trust=1
10. allow perm=open all : ftype=%languages trust=1
11. deny_audit perm=any all : ftype=%languages
12. allow perm=any all : ftype=text/x-shellscript
13. deny_audit perm=execute all : all
...
```

Debug mode

- Debug mode provides detailed information about matched rules, database status, and more. To switch **fapolicyd** to debug mode:
 - 1. Stop the **fapolicyd** service:

systemctl stop fapolicyd

2. Use debug mode to identify a corresponding rule:

fapolicyd --debug

Because the output of the **fapolicyd --debug** command is verbose, you can redirect the error output to a file:

fapolicyd --debug 2> fapolicy.output

Alternatively, to limit the output only to entries when **fapolicyd** denies access, use the **-- debug-deny** option:

fapolicyd --debug-deny

Removing the fapolicyd database

• To solve problems related to the **fapolicyd** database, try to remove the database file:

systemctl stop fapolicyd # fapolicyd-cli --delete-db



WARNING

Do not remove the /var/lib/fapolicyd/ directory. The fapolicyd framework automatically restores only the database file in this directory.

Dumping the fapolicyd database

 The fapolicyd contains entries from all enabled trust sources. You can check the entries after dumping the database:

fapolicyd-cli --dump-db

Application pipe

- In rare cases, removing the **fapolicyd** pipe file can solve a lockup:
 - # rm -f /var/run/fapolicyd/fapolicyd.fifo

Additional resources

• fapolicyd-cli(1) man page on your system

10.7. PREVENTING USERS FROM EXECUTING UNTRUSTWORTHY CODE BY USING THE FAPOLICYD RHEL SYSTEM ROLE

You can automate the installation and configuration of the **fapolicyd** service by using the **fapolicyd** RHEL system role. With this role, you can remotely configure the service to allow users to execute only trusted applications, for example, the ones which are listed in the RPM database and in an allow list. Additionally, the service can perform integrity checks before it executes an allowed application.

Prerequisites

- You have prepared the control node and the managed nodes
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

 name: Configuring fapolicyd hosts: managed-node-01.example.com tasks:

 name: Allow only executables installed from RPM database and specific files ansible.builtin.include_role:

name: rhel-system-roles.fapolicyd

vars:

fapolicyd_setup_permissive: false fapolicyd_setup_integrity: sha256 fapolicyd_setup_trust: rpmdb,file fapolicyd_add_trusted_file: - <path_to_allowed_command>

- <path to allowed service>

The settings specified in the example playbook include the following:

fapolicyd_setup_permissive: <true|false>

Enables or disables sending policy decisions to the kernel for enforcement. Set this variable for debugging and testing purposes to **false**.

fapolicyd_setup_integrity: <type_type>

Defines the integrity checking method. You can set one of the following values:

- none (default): Disables integrity checking.
- **size**: The service compares only the file sizes of allowed applications.
- **ima**: The service checks the SHA-256 hash that the kernel's Integrity Measurement Architecture (IMA) stored in a file's extended attribute. Additionally, the service performs a size check. Note that the role does not configure the IMA kernel subsystem. To use this option, you must manually configure the IMA subsystem.
- **sha256**: The service compares the SHA-256 hash of allowed applications.

fapolicyd_setup_trust: <trust_backends>

Defines the list of trust backends. If you include the **file** backend, specify the allowed executable files in the **fapolicyd_add_trusted_file** list.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.fapolicyd.README.md file on the control node.

2. Validate the playbook syntax:

\$ ansible-playbook ~/playbook.yml --syntax-check

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

• Execute a binary application that is not on the allow list as a user:

\$ ansible managed-node-01.example.com -m command -a 'su -c "/bin/not_authorized_application " <user_name>' bash: line 1: /bin/not_authorized_application: Operation not permitted non-zero return code

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.fapolicyd/README.md file
- /usr/share/doc/rhel-system-roles/fapolicyd/ directory

10.8. ADDITIONAL RESOURCES

• fapolicyd-related man pages listed by using the man -k fapolicyd command on your system

CHAPTER 11. PROTECTING SYSTEMS AGAINST INTRUSIVE USB DEVICES

USB devices can be loaded with spyware, malware, or trojans, which can steal your data or damage your system. As a Red Hat Enterprise Linux administrator, you can prevent such USB attacks with **USBGuard**.

11.1. USBGUARD

With the USBGuard software framework, you can protect your systems against intrusive USB devices by using basic lists of permitted and forbidden devices based on the USB device authorization feature in the kernel.

The USBGuard framework provides the following components:

- The system service component with an inter-process communication (IPC) interface for dynamic interaction and policy enforcement
- The command-line interface to interact with a running usbguard system service
- The rule language for writing USB device authorization policies
- The C++ API for interacting with the system service component implemented in a shared library

The **usbguard** system service configuration file (/etc/usbguard/usbguard-daemon.conf) includes the options to authorize the users and groups to use the IPC interface.



IMPORTANT

The system service provides the USBGuard public IPC interface. In Red Hat Enterprise Linux, the access to this interface is limited to only the root user by default.

Consider setting either the **IPCAccessControlFiles** option (recommended) or the **IPCAllowedUsers** and **IPCAllowedGroups** options to limit access to the IPC interface.

Ensure that you do not leave the Access Control List (ACL) unconfigured because this exposes the IPC interface to all local users and allows them to manipulate the authorization state of USB devices and modify the USBGuard policy.

11.2. INSTALLING USBGUARD

Use this procedure to install and initiate the USBGuard framework.

Procedure

- 1. Install the **usbguard** package:
 - # dnf install usbguard
- 2. Create an initial rule set:
 - # usbguard generate-policy > /etc/usbguard/rules.conf
- 3. Start the **usbquard** daemon and ensure that it starts automatically on boot:

systemctl enable --now usbguard

Verification

1. Verify that the **usbguard** service is running:

systemctl status usbguard

• usbguard.service - USBGuard daemon

 $Loaded: loaded \ (/usr/lib/systemd/system/usbguard.service; enabled; vendor \ preset: \\$

disabled)

Active: active (running) since Thu 2019-11-07 09:44:07 CET; 3min 16s ago

Docs: man:usbguard-daemon(8)
Main PID: 6122 (usbguard-daemon)

Tasks: 3 (limit: 11493)

Memory: 1.2M

CGroup: /system.slice/usbguard.service

6122 /usr/sbin/usbguard-daemon -f -s -c /etc/usbguard/usbguard-daemon.conf

Nov 07 09:44:06 localhost.localdomain systemd[1]: Starting USBGuard daemon... Nov 07 09:44:07 localhost.localdomain systemd[1]: Started USBGuard daemon.

2. List USB devices recognized by USBGuard:

usbguard list-devices

4: allow id 1d6b:0002 serial "0000:02:00.0" name "xHCl Host Controller" hash...

Additional resources

usbguard(1) and usbguard-daemon.conf(5) man pages on your system

11.3. BLOCKING AND AUTHORIZING A USB DEVICE BY USING THE CLI

You can set USBGuard to allow, block, or reject a specific USB device by using the **usbguard** command in your terminal. This setting persists as long as USBGuard is running. USBGuard uses the terms **block** and **reject** with the following meanings:

block

Do not interact with this device for now.

reject

Ignore this device as if it does not exist.

Prerequisites

• The **usbguard** service is installed and running.

Procedure

1. Determine the ID of the USB device by listing the devices recognized by USBGuard:

usbguard list-devices

1: allow id 1d6b:0002 serial "0000:00:06.7" name "EHCI Host Controller" hash

"JDOb0BiktYs2ct3mSQKopnOOV2h9MGYADwhT+oUtF2s=" parent-hash

"4PHGcaDKWtPjKDwYpIRG722cB9SlGz9l9lea93+Gt9c=" via-port "usb1" with-interface 09:00:00

. . .

6: block id 1b1c:1ab1 serial "000024937962" name "Voyager" hash "CrXgiaWlf2bZAU+5WkzOE7y0rdSO82XMzubn7HDb95Q=" parent-hash "JDOb0BiktYs2ct3mSQKopnOOV2h9MGYADwhT+oUtF2s=" via-port "1-3" with-interface 08:06:50

- 2. Authorize a device to interact with the system:
 - # usbguard allow-device <ID>
- 3. Deauthorize and remove a device:
 - # usbguard reject-device <ID>
- 4. Deauthorize and retain a device:
 - # usbguard block-device <ID>

Additional resources

- usbguard(1) man page on your system
- Built-in help listed by using the **usbguard --help** command

11.4. PERMANENTLY BLOCKING AND AUTHORIZING A USB DEVICE

You can permanently block and authorize a USB device by using the **-p** option. This adds a device-specific rule to the current policy and persists across restarts and reboots. USBGuard uses the terms **block** and **reject** with the following meanings:

block

Do not interact with this device for now.

reject

Ignore this device as if it does not exist.

Prerequisites

• The **usbquard** service is installed and running.

Procedure

- 1. Configure SELinux to allow the **usbguard** daemon to write rules.
 - a. Display the **semanage** Booleans relevant to **usbguard**.

```
# semanage boolean -I | grep usbguard usbguard_daemon_write_conf (off , off) Allow usbguard to daemon write conf usbguard_daemon_write_rules (on , on) Allow usbguard to daemon write rules
```

b. If the **usbquard daemon write rules** Boolean is turned off, turn it on.

semanage boolean -m --on usbguard_daemon_write_rules

2. Determine the ID of the USB device by listing the devices recognized by USBGuard:

usbguard list-devices

1: allow id 1d6b:0002 serial "0000:00:06.7" name "EHCI Host Controller" hash

"JDOb0BiktYs2ct3mSQKopnOOV2h9MGYADwhT+oUtF2s=" parent-hash

"4PHGcaDKWtPjKDwYpIRG722cB9SlGz9l9lea93+Gt9c=" via-port "usb1" with-interface 09:00:00

. . .

6: block id 1b1c:1ab1 serial "000024937962" name "Voyager" hash

"CrXgiaWlf2bZAU+5WkzOE7y0rdSO82XMzubn7HDb95Q=" parent-hash

"JDOb0BiktYs2ct3mSQKopnOOV2h9MGYADwhT+oUtF2s=" via-port "1-3" with-interface 08:06:50

3. Permanently authorize a device to interact with the system:

usbguard allow-device <ID> -p

4. Permanently deauthorize and remove a device:

usbguard reject-device <ID> -p

5. Permanently deauthorize and retain a device:

usbguard block-device <ID> -p

Verification

1. Check that the USBGuard rules include the changes you made.

usbguard list-rules

Additional resources

- usbguard(1) man page on your system
- Built-in help listed by using the **usbguard --help** command

11.5. CREATING A CUSTOM POLICY FOR USB DEVICES

The following procedure contains steps for creating a rule set for USB devices that reflects the requirements of your scenario.

Prerequisites

- The **usbguard** service is installed and running.
- The /etc/usbguard/rules.conf file contains an initial rule set generated by the usbguard generate-policy command.

Procedure

1. Create a policy which authorizes the currently connected USB devices, and store the generated rules to the **rules.conf** file:

usbguard generate-policy --no-hashes > ./rules.conf

The **--no-hashes** option does not generate hash attributes for devices. Avoid hash attributes in your configuration settings because they might not be persistent.

2. In the **rules.conf** file, add, remove, or edit the rules as required by using a text editor. For example, the following rule allows only devices with a single mass storage interface to interact with the system:

allow with-interface equals { 08:*:* }

See the **usbguard-rules.conf(5)** man page for a detailed rule-language description and more examples.

3. Install the updated policy:

install -m 0600 -o root -g root rules.conf /etc/usbguard/rules.conf

4. Restart the **usbguard** daemon to apply your changes:

systemctl restart usbguard

Verification

1. Check that your custom rules are in the active policy, for example:

```
# usbguard list-rules
...
4: allow with-interface 08:*:*
...
```

Additional resources

• usbguard-rules.conf(5) man page on your system

11.6. CREATING A STRUCTURED CUSTOM POLICY FOR USB DEVICES

You can organize your custom USBGuard policy in several **.conf** files within the **/etc/usbguard/rules.d/** directory. The **usbguard-daemon** then combines the main **rules.conf** file with the **.conf** files within the directory in alphabetical order.

Prerequisites

• The **usbquard** service is installed and running.

Procedure

1. Create a policy which authorizes the currently connected USB devices, and store the generated rules to a new **.conf** file, for example, **<policy.conf>**.

usbguard generate-policy --no-hashes > ./<policy.conf>

The **--no-hashes** option does not generate hash attributes for devices. Avoid hash attributes in your configuration settings because they might not be persistent.

2. Open the *<policy.conf>* file with a text editor of your choice, and select the lines with the rules that you want to record, for example:

```
... allow id 04f2:0833 serial "" name "USB Keyboard" via-port "7-2" with-interface { 03:01:01 03:00:00 } with-connect-type "unknown" ...
```

3. Copy the selected lines into a separate .conf file.



NOTE

The two digits at the beginning of the file name specify the order in which the daemon reads the configuration files.

For example, to copy the rules for your keyboards into a new .conf file:

grep "USB Keyboard" ./<policy.conf> > ./<10keyboards.conf>

4. Install the new policy to the /etc/usbguard/rules.d/ directory.

install -m 0600 -o root -g root <10keyboards.conf> /etc/usbguard/rules.d/<10keyboards.conf>

5. Move the rest of the lines to the main **rules.conf** file.

grep -v "USB Keyboard" ./policy.conf > ./rules.conf

6. Install the remaining rules.

install -m 0600 -o root -g root rules.conf /etc/usbguard/rules.conf

7. Restart the **usbguard** daemon to apply your changes.

systemctl restart usbguard

Verification

1. Display all active USBGuard rules.

```
# usbguard list-rules
...

15: allow id 04f2:0833 serial "" name "USB Keyboard" hash
"kxM/iddRe/WSCocgiuQlVs6Dn0VEza7KiHoDeTz0fyg=" parent-hash
"2i6ZBJfTl5BakXF7Gba84/Cp1gslnNc1DM6vWQpie3s=" via-port "7-2" with-interface {
03:01:01 03:00:00 } with-connect-type "unknown"
...
```

- 2. Display the contents of the **rules.conf** file and all the **.conf** files in the **/etc/usbguard/rules.d/** directory.
 - # cat /etc/usbguard/rules.conf /etc/usbguard/rules.d/*.conf
- 3. Verify that the active rules contain all the rules from the files and are in the correct order.

Additional resources

• usbguard-rules.conf(5) man page.

11.7. AUTHORIZING USERS AND GROUPS TO USE THE USBGUARD IPC INTERFACE

By default, only the root user can use the USBGuard public IPC interface interface. You can authorize a specific user or a group to use this interface in addition to root. You can do that either by editing the /etc/usbguard/usbguard-daemon.conf file or by using the usbguard add-user subcommand.

Prerequisites

- The **usbguard** service is installed and running.
- The /etc/usbguard/rules.conf file contains an initial rule set generated by the usbguard generate-policy command.

Procedure

- 1. Edit the /etc/usbguard/usbguard-daemon.conf file with the rules you want to add. For example, to allow all users in the wheel group to use the IPC interface, add this line:
 - IPCAllowGroups=wheel
- 2. You can add users or groups also with the **usbguard** command. For example, the following command enables a user to have full access to the **Devices** and **Exceptions** sections and to list and modify the current policy:
 - # usbguard add-user <user_name> --devices ALL --policy modify,list --exceptions ALL

Replace **<user_name>** with the user name that should receive these permissions.

You can remove the granted permissions for a user by using the **usbguard remove-user <user_name>** command.

- 3. Restart the **usbguard** daemon to apply your changes:
 - # systemctl restart usbguard

Additional resources

• usbguard(1) and usbguard-rules.conf(5) man pages

11.8. LOGGING USBGUARD AUTHORIZATION EVENTS TO THE LINUX AUDIT LOG

By default, the **usbguard** daemon logs events to the **/var/log/usbguard/usbguard-audit.log** file. You can integrate logging of USBguard authorization events to the standard Linux Audit log.

Prerequisites

- The **usbguard** service is installed and running.
- The **auditd** service is running.

Procedure

- In the /etc/usbguard/usbguard-daemon.conf file, change the AuditBackend option from FileAudit to LinuxAudit:
 - AuditBackend=LinuxAudit
- 2. Restart the **usbguard** daemon to apply the configuration change:
 - # systemctl restart usbguard

Verification

- 1. Query the **audit** daemon log for a USB authorization event, for example:
 - # ausearch -ts recent -m USER_DEVICE

Additional resources

• usbguard-daemon.conf(5) man page on your system.

11.9. ADDITIONAL RESOURCES

- usbguard(1), usbguard-rules.conf(5), usbguard-daemon(8), and usbguard-daemon.conf(5) man pages on your system.
- USBGuard Homepage.