Common errors

Missing authentication

`401 Unauthorized`

The `Authorization` header is required, with its value set to `Bearer your-access-key-token`.

Missing scopes

`403 Forbidden - { message: 'Missing access key scope(s): [scopes]' }`

This means your access key was not correctly set up for accessing a specific resource. Access key scopes cannot be updated so you should create a new key with the correct scopes and revoke the old key.

Generally, `GET` requests require `read` access, `POST/PUT/PATCH/DELETE` requests require `write` access.

Missing parameters

`400 Bad Request`

When omitting a required parameter (e.g. a query key, body key or header), you'll usually receive a 400. Refer to the documentation for the API to make sure your request is correct.

The error object returned may be a single message (e.g. `{ message: Something went wrong }`) or an error object, which includes a key for every invalid/missing key:

```
errors: {
  events: ['events is missing from the request body']
}
```

Rate-limiting

`429 Too Many Requests`

Receiving this status means you've hit Talo's rate limit. Rate limits use a fixed window (resets every minute),

so you should aim to make less than 100 requests per minute, per player. You can achieve this by, for example, batching events and stat updates.

Authentication endpoints (e.g. `/v1/players/auth/*`, `/v1/players/identify` and `/v1/socket-tickets`) are limited to 20 requests per minute, per player.

The `Retry-After` header will return how many seconds to wait before retrying - typically this will be set to '60' (the remaining seconds until the window resets).

Missing or invalid session

`401 Authorized - { message: 'The x-talo-session header is required for this player', errorCode: 'MISSING_SESSION' }`

`401 Authorized - { message: 'The x-talo-session header is invalid', errorCode: 'INVALID_SESSION' }`

When calling API endpoints on behalf of a player (i.e. using the `x-talo-player` or `x-talo-alias` header) that is using player authentication you must also send a valid `x-talo-session` header.

You'll need to include both the `x-talo-player` and the `x-talo-alias` headers as well as the `x-talo-session` header which should be set to the token you receive from registering or logging-in a player.