Modifying Existing Tables

After creating a table with Hive or Impala, you might need to modify the table definition. This might be because there was a mistake in your CREATE TABLE statement, or because the structure of the underlying data has changed, or perhaps because you need to use a different naming convention.

To modify a table definition, use the ALTER TABLE statement. The general syntax is

ALTER TABLE tablename ACTION parameters

The keyword used in place of *ACTION* depends on what kind of modification you want to make. The following sections present some of the most common modifications. There are other possibilities in addition to the ones presented here. You can look at the documentation (Impala ALTER TABLE statement or Hive Language Manual DDL: Alter Table) if you want more information, but at this point in the course, the options presented here probably are sufficient.

Note: Sometimes it's easier to just drop your table and recreate it, rather than making changes to the table—but you must be careful not to delete your data in the process. In traditional RDBMSs this is not feasible, but in the big data systems, the data and metadata are separated. If you created an externally managed table using EXTERNAL, then dropping the data is purely a metadata operation and does not affect the data. If you have an internally managed table, you could make it externally managed first (see the "Changing to an Unmanaged (External) Table" section below). It's up to you whether you would rather make the changes to a table, or drop it and recreate the table.

Renaming a Table

To rename a table, use

ALTER TABLE old tablename RENAME TO new tablename;

For example, this renames the table customers to clients:

ALTER TABLE customers RENAME TO clients;

When you rename a table, Hive or Impala changes the table's name in the metastore, and if the table is internally managed, it also renames the table's directory in HDFS.

Moving a Table to a Different Database

To move a table to a different database, you also use RENAME TO, and you specify the fully qualified names of the old (existing) and new tables, including the database names:

ALTER TABLE old_database.tablename RENAME TO new_database.tablename;

For example, this moves the existing table named clients from the default database to the dig database:

ALTER TABLE default.clients RENAME TO dig.clients;

When you move a table to a different database, Hive or Impala changes the associated metadata in the metastore, and if the table is managed, it also moves the table's directory in HDFS into the subdirectory for the different database.

Changing Column Name or Data Type

To change the name or data type of a column, use

ALTER TABLE tablename CHANGE old_colname new_colname type;

If you are not changing the data type, you still need to supply the type. If you are not changing the column name—only the data type—then repeat the column name.

For example, the following changes the first_name column (of type STRING) in the employees table to given_name (but keeps it a STRING column).

ALTER TABLE employees CHANGE first_name given_name STRING;

The following example changes salary from INT to BIGINT without changing the column name:

ALTER TABLE employees CHANGE salary salary BIGINT;

Changing Column Order (Hive only)

When you create a table for existing data, your columns need to be provided in the same order that they appear in the data files. If you have made a mistake and put them in a different order in the CREATE TABLE statement, you can fix it with the ALTER TABLE statement.

To change where a column goes using Hive, use the CHANGE keyword just as if you were changing the column name and add either AFTER *column* or FIRST at the end.

For example, the employees table in the VM has columns in this order: empl_id, first_name, last_name, salary, office_id. Suppose you discover that the file data actually lists the office ID before the employee's salary. The following moves the salary after the office id column:

ALTER TABLE employees CHANGE salary salary INT AFTER office id;

If the column to move needs to be the first (leftmost) column, then the statement would be

ALTER TABLE tablename CHANGE col_name col_name col_type FIRST;

Notes

This feature is available in Hive but not Impala. For Impala, see "Replacing All Columns" for an alternative method.

You always need to give the "old" and "new" names of the column you're moving, along with its data type, even if those details are not changing.

This does not change the data files. If you change the order of columns to something *different* from the order in the files, you'll need to recreate the data files using the new order.

Adding or Removing Columns

You can add one or more columns to the end of the column list using ADD COLUMNS, or (with Impala only) you can delete columns using DROP COLUMN. The general syntax is

ALTER TABLE tablename ADD COLUMNS (col1 TYPE1,col2 TYPE2,...);

ALTER TABLE tablename DROP COLUMN colname;

For example, you can add a bonus integer column to the employees table:

ALTER TABLE employees ADD COLUMNS (bonus INT);

Or you can drop the office_id column from the employees table:

ALTER TABLE employees DROP COLUMN office id;

Notes

DROP COLUMN is not available in Hive, only in Impala. However, see "Replacing All Columns" below.

You can only drop one column at a time. To drop multiple columns, use multiple statements or use the method to replace columns (see below).

You cannot add a column in the middle of the list rather than at the end. You can, however, add the column then change the order (see above) or use the method to replace columns (see below).

As with changing the column order, these do not change the data files.

- If the table definition agrees with the data files before you drop any column other than the last one, you will need to recreate the data files without the dropped column's values.
- If you drop the last column, the data will still exist but it will be ignored when a query is issued.
- If you add columns for which no data exists, those columns will be NULL in each row.

Replacing All Columns

You can also completely replace all the columns with a new column list. This is helpful for dropping multiple columns, or if you need to add columns in the middle of the list. The general syntax is

ALTER TABLE tablename REPLACE COLUMNS (col1 TYPE1,col2 TYPE2,...);

This completely removes the existing list of columns and replaces it with the new list. Only the columns you specify in the ALTER TABLE statement will exist, and they will be in the order you provide.

Note

Again, this does not change the data files, only the metadata for the table, so you'll either want the new list to match the data files or need to recreate the data files to match the new list.

Changing to an Unmanaged (External) Table

If you have created a table as a managed table (without the EXTERNAL keyword) and later realize you want it unmanaged, you can use ALTER TABLE with TBLPROPERTIES to make it unmanaged. This is particularly helpful if you want to drop a table without losing the data.

The general syntax is

ALTER TABLE tablename SET TBLPROPERTIES('EXTERNAL'='TRUE');

Notes

Both EXTERNAL and TRUE are in quotes, and they must be uppercase, here.

You can also use SET TBLPROPERTIES with other properties that were not set at creation.

Try It!

Test these out with the investors table.

The first thing you'll do is verify that the table is unmanaged (external) so you can drop the table without losing the data, in case you make a mistake. You can then recreate the table using the exercise from "The ROW FORMAT Clause" reading in "The CREATE TABLE Statement" lesson, where you first created the investors table. (You can leave this alteration, no need to change it back.) If it's *not* unmanaged, then you should change it.

1. In Hive or Impala, execute the following on the customers table so you can see what a *managed* table looks like. Be sure the default database is your active database.

DESCRIBE FORMATTED customers:

Look down the results for Table Type; the value should be MANAGED_TABLE. This means it was created without the EXTERNAL keyword.

2. Now run the same command on the investorstable, and note what the value is for Table Type. If it's also MANAGED_TABLE, execute the following to change it to an unmanaged table, then run the DESCRIBE FORMATTED statement again and check the value for Table Type. (If the value is not MANAGED_TABLE, you don't need to run this command—though it does no harm if you do.)

ALTER TABLE investors SET TBLPROPERTIES('EXTERNAL'='TRUE');

Next, try changing the name.

3. Execute the following statement:

ALTER TABLE investors RENAME TO companies;

- 4. Verify that the table name changed in the data source panel (refresh the display if necessary), or by running SELECT * FROM companies;
- 5. Change the name back to investors and verify the change.

Now move it to the dig database.

6. Execute the following statement:

ALTER TABLE default.investors RENAME TO dig.investors;

- 7. Verify that the table is no longer in the default database, and that it *is* in the dig database.
- 8. Check the Hive warehouse directory. The investors subdirectory has not moved to the dig.db directory—it is still in the default database. Do you know why? (See the "Postscript" section below for the answer!)
- 9. Change the directory back to default and verify the change.

Change the column amount to holdings.

10. Execute the following statement:

ALTER TABLE investors CHANGE amount holdings INT;

- 11. Verify that the column's name has changed, using the data source panel or by running DESCRIBE investors;
- 12. Change the column name back to amountand verify the change.

Change the column amount from INT to BIGINT.

13. Execute the following statement:

ALTER TABLE investors CHANGE amount amount BIGINT;

- 14. Verify that the column's type has changed, using the data source panel or by running DESCRIBE investors;
- 15. Change the column type back to INT and verify the change.

Use Hive (not Impala) to put the amount column at the end instead of the middle, and see the effect.

- 16. First take a look at the data by running SELECT * FROM investors;
- 17. Execute the following statement:

ALTER TABLE investors CHANGE name name STRING AFTER amount:

18. Verify that the columns have been reordered in the metadata but not in the data itself by running

SELECT * FROM investors;

Notice that amount is NULL in each row—this is because the data being loaded is the non-numeric character data that used to go into name. Since amount is anINT column, the data isn't valid. The integer data meant for amount is valid for the STRING column name, so those values are not NULL. (The point here is that the data itself did not change.)

19. Change the column order back by executing

ALTER TABLE investors CHANGE name name STRING FIRST:

20. Verify that the columns are back to normal using the SELECT * guery.

Use Impala to drop a column and then add it back. (You can add with Hive or Impala, but Hive doesn't recognize the DROP COLUMN keyword, so to make things easier, use Impala for both.)

21. First drop the share column:

ALTER TABLE investors DROP COLUMN share;

22. Run the SELECT * query to verify the column has been dropped. The values in the other columns has not changed.

23. Add the share column back:

ALTER TABLE investors ADD COLUMNS (share DECIMAL(4,3));

24. Verify that the column has been restored.

Finally, change the columns completely!

25. Execute the following statement:

ALTER TABLE investors REPLACE COLUMNS (company STRING, holdings BIGINT, share DOUBLE);

- 26. Verify the table columns have changed using DESCRIBE investors;
- 27. Restore the original columns:

ALTER TABLE investors REPLACE COLUMNS

(name STRING, amount INT, share DECIMAL(4,3));

28. Verify that the table has changed back.

Postscript

The investors table directory didn't move when moved to a different database because it's an unmanaged table. Just as dropping the table won't delete the data, changing the database will not move the data.

Try moving customers, which is managed, to thedig database, and confirm that the table directory moved in that case. (That is, /user/hive/warehouse/ should no longer have the customers/ subdirectory, but /user/hive/warehouse/dig.db/ should have it instead.) You might need to refresh the display. Be sure to move the table back to the default database when you're done.