

PROCEDURES PROC-16

QUIKCLOT

Page 1 of 1 Last Revision: 08/01/2017

Indications:

• For the control of moderate to severe bleeding.

Procedure:

- 1. Expose the injury by removing/cutting away clothing.
- 2. If on an extremity, place a tourniquet proximal to the injury.
- 3. Remove any excess blood from the wound while preserving any clots that have formed.
- 4. Locate the source of the most active bleeding
- 5. Remove the combat gauze from the packing and pack it tightly into the wound directly over the site of the most active bleeding.
- 6. Apply direct pressure to the bleeding site while packing the gauze and apply enough force to stop the bleeding.
- 7. After the gauze has been packed, continue to hold direct pressure for **AT LEAST** 3 minutes.
- 8. Reassess for bleeding control.
- 9. **DO NOT REMOVE** combat gauze, leave in place.
- 10. Cover with roller gauze, or other securing method.
- 11. More than one package of gauze may be used to control the hemorrhage.
- 12. If the gauze becomes over saturated and bleeding is continuing, remove the combat gauze and repeat above steps.

Considerations:

- When extremities are involved, first use a tourniquet proximal to the bleeding site.
- Transport to a Level I or II Trauma Facility.
- Advise ER staff that combat gauze was used.
- QuikClot Combat Gauze is impregnated with Kaolin an inert mineral promotes the activation of Factor XII
 and results in activation of Factor XI allowing for the formation of a fibrin clot. There is NO exothermic
 reaction.