

Requirements Analysis

Task: Decompose each requirement into atomic blocks and write them down below.

Requirement	Atomic block
Requirement ID: FR-1	1 The interface must have an input field labeled "From".
	2 The interface must have an input field labeled "To".
	3 The interface must have a mode option labeled "Optimal".
	4 The interface must have a mode option labeled "Fastest".
	5 The interface must have a mode option labeled "Custom".
	6 The interface must have an icon for going on foot.
	7 The interface must have an icon for the user's car.
	8 The interface must have an icon for car-sharing.
	9 The interface must have an icon for a taxi.
	10 The interface must have an icon for a scooter.
	11 The interface must have an icon for a bicycle.
Requirement ID: FR-2	1 The interface must have an input field for the departure point.
	2 The interface must have an input field for the destination.
	3 The interface must allow spaces at the beginning of the departure point address.
	4 The interface must allow spaces at the end of the departure point address.
	5 The interface must allow spaces at the beginning of the destination address.
	6 The interface must allow spaces at the end of the destination address.
	7 The interface must delete spaces from the departure field when it is not in focus.
	8 The interface must delete spaces from the destination field when it is not in focus.
Requirement ID: FR-3	1 The interface must have an empty initial state for the "From" input field.
	2 The interface must have an empty initial state for the "To" input field.
	3 The interface must have an unselected initial state for the "Optimal" mode option.

Requirement ID: FR-3	4 The interface must have an unselected initial state for the "Fastest" mode option.
	5 The interface must have an unselected initial state for the "Custom" mode option.
	6 The interface must have an inactive initial state for the transport panel.
Requirement ID: FR-4	1 The interface must allow numbers to be entered in the "From" field.
	2 The interface must allow numbers to be entered in the "To" field.
	3 The interface must allow spaces to be entered in the "From" field.
	4 The interface must allow spaces to be entered in the "To" field.
	5 The interface must allow dashes to be entered in the "From" field.
	6 The interface must allow dashes to be entered in the "To" field.
	7 The interface must allow periods to be entered in the "From" field.
	8 The interface must allow periods to be entered in the "To" field.
	9 The interface must allow commas to be entered in the "From" field.
	10 The interface must allow commas to be entered in the "To" field.
	11 The interface must allow Latin characters to be entered in the "From" field.
	12 The interface must allow Latin characters to be entered in the "To" field.
	13 The interface must enforce a maximum length of 50 characters for the "From" field.
	14 The interface must enforce a maximum length of 50 characters for the "To" field.
	15 The interface must delete spaces from the "From" field when it is not in focus.
	16 The interface must delete spaces from the "To" field when it is not in focus.
	17 The interface must display the error message "Incorrect address." if the data in the "From" field
	18 The interface must display the error message "Incorrect address." if the data in the "To" field is
	19 The interface must prevent form submission if the "From" field data is invalid.
	20 The interface must prevent form submission if the "To" field data is invalid.

Test Planning

Task: Scan the test plan and fill out the table by writing down the number and the name of the section where you found the relevant information. The first row has been filled out as an example.

Information	The section it can be found in
Description of software being tested	1.2 <i>Application summary</i>
Person/people responsible for communicating strategic changes to the team	4.2 Test Lead
Digital infrastructure used in testing	5. SOFTWARE AND HARDWARE RESOURCES
Application's features and functionalities	1.2 Application Summary
Measures that should be taken to avoid delays	6. RISK & MITIGATION

Equivalence partitions/classes and boundary values

Stage 1: Define equivalence partitions/classes and boundary values

Feature Under Test	Equivalence Class	Boundary Values
From	Numbers	
	Spaces	
	Dashes	
	Periods	
	Commas	
	Latin Characters	
	Non Latin Characters	
	Special Characters	
	0-50 Characters	0,1,49,50,51
	51+ Characters	49,50,51
	Leading Spaces	
	Trailing Spaces	

--

To	Numbers	
	Spaces	
	Dashes	
	Periods	
	Commas	
	Latin Characters	
	Non Latin Characters	
	Special Characters	
	0-50 Characters	0,1,49,50,51
	51+ Characters	49,50,51
	Leading Spaces	
	Trailing Spaces	

Test Data for Equivalence Class	Test Data for Boundary Values	Comments
123 Creston Street		
123 Creston Street		
123-B Creston Street		
123 Creston Street.		
123 Creston Street, Kalamazoo		
123 Creston Street		
123 Крестон Стрит		
#123 Creston Street		
123 Creston Street (13)	"" (0) A (1) 123 Creston Street, Kalamazoo, Michigan, MI, 4900 (49) 123 Creston Street, Kalamazoo, Michigan, MI, 49002 (50) 123 Creston Street, Kalamazoo, Michigan, MI, 49002- (51)	
123 Creston Street, Kalamazoo, Michigan, MI, 49002----- (53)	123 Creston Street, Kalamazoo, Michigan, MI, 4900 (49) 123 Creston Street, Kalamazoo, Michigan, MI, 49002 (50) 123 Creston Street, Kalamazoo, Michigan, MI, 49002- (51)	
" 123 Creston Street"		
"123 Creston Street "		

123 Creston Street		
123 Creston Street		
123-B Creston Street		
123 Creston Street.		
123 Creston Street, Kalamazoo		
123 Creston Street		
123 Крестон Стрит		
#123 Creston Street		
123 Creston Street (13)	"" (0) A (1) 123 Creston Street, Kalamazoo, Michigan, MI, 4900 (49) 123 Creston Street, Kalamazoo, Michigan, MI, 49002 (50) 123 Creston Street, Kalamazoo, Michigan, MI, 49002- (51)	
123 Creston Street, Kalamazoo, Michigan, MI, 49002---- (53)	123 Creston Street, Kalamazoo, Michigan, MI, 4900 (49) 123 Creston Street, Kalamazoo, Michigan, MI, 49002 (50) 123 Creston Street, Kalamazoo, Michigan, MI, 49002- (51)	
" 123 Creston Street"		
"123 Creston Street "		

Test Cases


Stage 2: Write test cases

id	Test Case	Precondition	Steps
Example	Verify the user can enter numbers in To address field	- The Server has already started. - To field is empty.	- Enter numbers in the To field
Example	Verify the user can enter numbers in the From address field	- The Server has already started. - From field is empty.	- Enter numbers in the From field
t-1	Verify the user can enter spaces in From address field	- The Server has already started. - From field is empty.	- Enter an address with spaces in the From field
t-2	Verify the user can enter dashes in From address field	- The Server has already started. - From field is empty.	- Enter an address with a dash in the From field
t-3	Verify the user can enter periods in From address field	- The Server has already started. - From field is empty.	- Enter an address with a period in the From field
t-4	Verify the user can enter commas in From address field	- The Server has already started. - From field is empty.	- Enter an address with a comma in the From field
t-5	Verify the user can enter Latin characters in From address field	- The Server has already started. - From field is empty.	- Enter an Latin characters in the From field
t-6	Verify error when entering non-Latin characters in From field	- The Server has already started. - From field is empty.	- Enter non-Latin characters in the From field
t-7	Verify error when entering special characters in From field	- The Server has already started. - From field is empty.	- Enter special characters in the From field
t-8	Verify behavior when From field is empty (0 characters)	- The Server has already started. - From field is empty.	- Attempt to submit or validate an empty From field
t-9	Verify valid minimum boundary of 1 character in From field	- The Server has already started. - From field is empty.	- Enter exactly 1 allowed character in the From field
t-10	Verify validation at 49 characters in From field	- The Server has already started. - From field is empty.	- Enter a 49-character valid string in the From field

t-11	Verify validation at maximum boundary of 50 characters in From field	- The Server has already started. - From field is empty.	- Enter a 50-character valid string in the From field
t-12	Verify error at first invalid boundary of 51 characters in From field	- The Server has already started. - From field is empty.	- Enter a 51-character string in the From field
t-13	Verify error when input exceeds length drastically in From field	- The Server has already started. - From field is empty.	- Enter a 53-character string in the From field
t-14	Verify leading spaces remain visible when From field is in focus	- The Server has already started. - From field is empty. - Click into From field	- Enter text with leading spaces
t-15	Verify leading spaces are deleted when From field loses focus	- The Server has already started. - From field is empty. - Click into From field	- Enter text with leading spaces - Click outside of the From field to remove focus
t-16	Verify trailing spaces remain visible when From field is in focus	- The Server has already started. - From field is empty. - Click into From field	- Enter text with trailing spaces
t-17	Verify trailing spaces are deleted when From field loses focus	- The Server has already started. - From field is empty. - Click into From field	- Enter text with trailing spaces - Click outside of the From field to remove focus
t-18	Verify behavior when From field contains only spaces	- The Server has already started. - From field is empty.	- Enter only spaces in the From field - Click outside of the From field to remove focus
t-19	Verify the user can enter spaces in To address field	- The Server has already started. - To field is empty.	- Enter an address with spaces in the To field
t-20	Verify the user can enter dashes in To address field	- The Server has already started. - To field is empty.	- Enter an address with a dash in the To field
t-21	Verify the user can enter periods in To address field	- The Server has already started. - To field is empty.	- Enter an address with a period in the To field
t-22	Verify the user can enter commas in To address field	- The Server has already started. - To field is empty.	- Enter an address with a comma in the To field

t-23	Verify the user can enter Latin characters in To address field	- The Server has already started. - To field is empty.	- Enter Latin characters in the To field
t-24	Verify error when entering non-Latin characters in To field	- The Server has already started. - To field is empty.	- Enter non-Latin characters in the To field
t-25	Verify error when entering special characters in To field	- The Server has already started. - To field is empty.	- Enter special characters in the To field
t-26	Verify behavior when To field is empty (0 characters)	- The Server has already started. - To field is empty.	- Attempt to submit or validate an empty To field
t-27	Verify valid minimum boundary of 1 character in To field	- The Server has already started. - To field is empty.	- Enter exactly 1 allowed character in the To field
t-28	Verify validation at 49 characters in To field	- The Server has already started. - To field is empty.	- Enter a 49-character valid string in the To field
t-29	Verify validation at maximum boundary of 50 characters in To field	- The Server has already started. - To field is empty.	- Enter a 50-character valid string in the To field
t-30	Verify error at first invalid boundary of 51 characters in To field	- The Server has already started. - To field is empty.	- Enter a 51-character string in the To field
t-31	Verify error when input exceeds length drastically in To field	- The Server has already started. - To field is empty.	- Enter a 53-character string in the To field
t-32	Verify leading spaces remain visible when To field is in focus	- The Server has already started. - To field is empty.	- Click into To field - Enter text with leading spaces
t-33	Verify leading spaces are deleted when To field loses focus	- The Server has already started. - To field is empty.	- Click into To field - Enter text with leading spaces - Click outside of the To field to remove focus
t-34	Verify trailing spaces remain visible when To field is in focus	- The Server has already started. - To field is empty.	- Click into To field - Enter text with trailing spaces

t-35	Verify trailing spaces are deleted when To field loses focus	- The Server has already started. - To field is empty.	- Click into To field - Enter text with trailing spaces - Click outside of the To field to remove focus
t-36	Verify behavior when To field contains only spaces	- The Server has already started. - To field is empty.	- Enter only spaces in the To field - Click outside of the To field to remove focus



Test Technique	Test Data	Expected Result	Environment
positive testing	East 2nd Street, 601	Numbers are accepted in the To address field	Version 148.0.7778.217 (Official Build) (64-bit)
positive testing	1300 1st Street	Numbers are accepted in the From address field	Version 148.0.7778.217 (Official Build) (64-bit)
positive testing	123 Creston Street	Spaces are accepted in the From address field	Version 148.0.7778.217 (Official Build) (64-bit)
positive testing	123-B Creston Street	Dashes are accepted in the From address field	Version 148.0.7778.217 (Official Build) (64-bit)
positive testing	123 Creston Street.	Periods are accepted in the From address field	Version 148.0.7778.217 (Official Build) (64-bit)
positive testing	123 Creston Street, Kalamazoo	Commas are accepted in the From address field	Version 148.0.7778.217 (Official Build) (64-bit)
positive testing	123 Creston Street	Latin Characters are accepted in the From address field	Version 148.0.7778.217 (Official Build) (64-bit)
negative testing	123 Крестон Стрит	The software displays the error message "Incorrect address."	Version 148.0.7778.217 (Official Build) (64-bit)
negative testing	#123 Creston Street	The software displays the error message "Incorrect address."	Version 148.0.7778.217 (Official Build) (64-bit)
negative testing	""	The software displays the error message "Incorrect address"	Version 148.0.7778.217 (Official Build) (64-bit)
positive testing	A	The 1-character address is successfully accepted	Version 148.0.7778.217 (Official Build) (64-bit)
positive testing	123 Creston Street, Kalamazoo, Michigan, MI, 4900 (49)	The 49-character address is successfully accepted	Version 148.0.7778.217 (Official Build) (64-bit)

positive testing	123 Creston Street, Kalamazoo, Michigan, MI, 49002 (50)	The 50-character address is successfully accepted	Version 148.0.7778.217 (Official Build) (64-bit)
negative testing	123 Creston Street, Kalamazoo, Michigan, MI, 49002- (51)	The software displays the error message "Incorrect address."	Version 148.0.7778.217 (Official Build) (64-bit)
negative testing	123 Creston Street, Kalamazoo, Michigan, MI, 49002---- (53)	The software displays the error message "Incorrect address."	Version 148.0.7778.217 (Official Build) (64-bit)
positive testing	" 123 Creston Street"	Leading spaces remain visible while the field is in focus	Version 148.0.7778.217 (Official Build) (64-bit)
positive testing	" 123 Creston Street"	Leading spaces are automatically deleted when not in focus	Version 148.0.7778.217 (Official Build) (64-bit)
positive testing	"123 Creston Street "	Trailing spaces remain visible while the field is in focus	Version 148.0.7778.217 (Official Build) (64-bit)
positive testing	"123 Creston Street "	Trailing spaces are automatically deleted when not in focus	Version 148.0.7778.217 (Official Build) (64-bit)
negative testing	" "	The system trims the spaces, recognizing the field as empty / Triggers error	Version 148.0.7778.217 (Official Build) (64-bit)
positive testing	123 Creston Street	Spaces are accepted in the To address field	Version 148.0.7778.217 (Official Build) (64-bit)
positive testing	123-B Creston Street	Dashes are accepted in the To address field	Version 148.0.7778.217 (Official Build) (64-bit)
positive testing	123 Creston Street.	Periods are accepted in the To address field	Version 148.0.7778.217 (Official Build) (64-bit)
positive testing	123 Creston Street, Kalamazoo	Commas are accepted in the To address field	Version 148.0.7778.217 (Official Build) (64-bit)

positive testing	123 Creston Street	Latin characters are accepted in the To address field	Version 148.0.7778.217 (Official Build) (64-bit)
negative testing	123 Крестон Стрит	The software displays the error message "Incorrect address."	Version 148.0.7778.217 (Official Build) (64-bit)
negative testing	#123 Creston Street	The software displays the error message "Incorrect address."	Version 148.0.7778.217 (Official Build) (64-bit)
negative testing	""	The software displays the error message "Incorrect address"	Version 148.0.7778.217 (Official Build) (64-bit)
positive testing	A	The 1-character address is successfully accepted	Version 148.0.7778.217 (Official Build) (64-bit)
positive testing	123 Creston Street, Kalamazoo, Michigan, MI, 4900 (49)	The 49-character address is successfully accepted	Version 148.0.7778.217 (Official Build) (64-bit)
positive testing	123 Creston Street, Kalamazoo, Michigan, MI, 49002 (50)	The 50-character address is successfully accepted	Version 148.0.7778.217 (Official Build) (64-bit)
negative testing	123 Creston Street, Kalamazoo, Michigan, MI, 49002- (51)	The software displays the error message "Incorrect address."	Version 148.0.7778.217 (Official Build) (64-bit)
negative testing	123 Creston Street, Kalamazoo, Michigan, MI, 49002---- (53)	The software displays the error message "Incorrect address."	Version 148.0.7778.217 (Official Build) (64-bit)
positive testing	" 123 Creston Street"	Leading spaces remain visible while the field is in focus	Version 148.0.7778.217 (Official Build) (64-bit)
positive testing	" 123 Creston Street"	Leading spaces are automatically deleted when not in focus	Version 148.0.7778.217 (Official Build) (64-bit)
positive testing	"123 Creston Street "	Trailing spaces remain visible while the field is in focus	Version 148.0.7778.217 (Official Build) (64-bit)

positive testing	"123 Creston Street "	Trailing spaces are automatically deleted when not in focus	Version 148.0.7778.217 (Official Build) (64-bit)
negative testing	" "	The system trims the spaces, recognizing the field as empty / Triggers error	Version 148.0.7778.217 (Official Build) (64-bit)

Actual Result	Test Status (Pass / Fail)	Jira Bug Link (Not required for Project 2)
Numbers are accepted in the To address field	Pass	N/A
Numbers are accepted in the From address field	Pass	N/A
Spaces are not accepted in the From address field	Fail	
Dashes are not accepted in the From address field	Fail	
Periods are not accepted in the From address field	Fail	
Commas are not accepted in the From address field	Fail	
Latin Characters are not accepted in the From address field	Fail	
The software does not display the error message "Incorrect address."	Fail	
The software does not display the error message "Incorrect address."	Fail	
The software does not display the error message "Incorrect address."	Fail	
The 1-character address is not accepted	Fail	
The 49 character address is not accepted	Fail	

The 50 character address is not accepted	Fail	
The software does not display the error message "Incorrect address."	Fail	
The software does not display the error message "Inccorrect address."	Fail	
Leading spaces remain visible while the field is in focus	Pass	
Leading spaces are not automatically deleted when not in focus	Fail	
Trailing spaces remain visible while the field is in focus	Pass	
Trailing spaces are not automatically deleted when not in focus	Fail	
The system does not trim the spaces, does not recognize the field as empty / Triggers error	Fail	
Spaces are not accepted in the To address field	Fail	
Dashes are not accepted in the To address field	Fail	
Periods are not accepted in the To address field	Fail	
Commas are not accepted in the To address field	Fail	

Latin characters are not accepted in the To address field	Fail	
The software does not display the error message "Incorrect address."	Fail	
The software does not display the error message "Incorrect address."	Fail	
The software does not display the error message "Incorrect address."	Fail	
The 1-character address is not accepted	Fail	
The 49-character address is not accepted	Fail	
The 50-character address is not accepted	Fail	
The software does not display the error message "Incorrect address."	Fail	
The software does not display the error message "Incorrect address."	Fail	
Leading spaces remain visible while the field is in focus	Pass	
Leading spaces are not automatically deleted when not in focus	Fail	
Trailing spaces remain visible while the field is in focus	Pass	

Trailing spaces are not automatically deleted when not in focus	Fail	
The system does not trim the spaces, does not recognize the field as empty / Triggers error	Fail	

Report

	Value	% (Automatic)
Number of Test Cases	35	100%
Number of Passes	5	14%
Number of Fails	30	86%

Document: Project 2 EC,BV,TC

Project Version: v3.0