MongoDB 모니터링 PMM 구성

1. PMM 구성 전 Docker 설치

1-1 . Yum-utils 업데이트

yum install -y yum-utils

1-2 Docker-ce 레포 추가

yum-config-manager --add-repo https://download.docker.com/linux/centos/docker-ce.repo

1-3 Docker 설치

yum install docker-ce docker-ce-cli containerd.io -y

1-4 Docker 시작 및 서비스 등록

- # systemctl start docker
- # systemctl enable docker
- # systemctl status docker

```
| Corough - 172 - 32 - 114 - 98 centos | # systemctl status docker
| docker.service - Docker Application Container Engine
| Loaded: loaded (/usr/lib/systemd/system/docker.service; enabled; vendor preset: disabled)
| Active: active (running) since Wed 2022 - 11 - 02 05:13:40 UTC; 31s ago
| Docs: https://docs.docker.com
| Main PID: 22578 (dockerd)
| CGroup: /system.slice/docker.service
| L22578 /usr/bin/dockerd - H fd:// --containerd=/run/containerd/containerd.sock
```

2. 서버 설치

2-1. 데이터 볼륨 생성


docker create -v /srv --name pmm-data percona/pmm-server:2 /bin/true

2-2. PMM-Server 도커 컨테이너 생성

docker run -d -p 80:80 -p 443:443 --volumes-from pmm-data --name pmm-server --restart always percona/pmm-server:2

2-3 서버 접속

<u>https://localhost:443</u> or https://<Public_IP>:443 으로 접속 → 초기 ID / 비밀번호 admin/admin



3. 클라이언트 설치

3-1. PMM Client docker 이미지 설치

docker pull ₩

> percona/pmm-client:2

3-2 Use the image as a template to create a persistent data store that preserves local data when the image is updated.

docker create ₩

- > --volume /srv ₩
- > --name pmm-client-data ₩
- > percona/pmm-client:2 /bin/true
- 3-3. PMM Agent setup mode 로 container 를 실행해준다.

PMM SERVER=X.X.X.X:443 ← 서버 IP 를 입력해주어야한다.

docker run ₩

- > --rm ₩
- > --name pmm-client \text{\text{\$\psi}}
- > -e PMM AGENT SERVER ADDRESS=\${PMM SERVER} ₩
- > -e PMM_AGENT_SERVER_USERNAME=admin ₩
- > -e PMM_AGENT_SERVER_PASSWORD=admin ₩

← 비밀번호를

- 수정했다면 바꿔주자
- > -e PMM_AGENT_SERVER_INSECURE_TLS=1 ₩
- > -e PMM AGENT SETUP=1 ₩
- > -e PMM_AGENT_CONFIG_FILE=config/pmm-agent.yaml \text{\psi}
- > --volumes-from pmm-client-data ₩
- > percona/pmm-client:2

docker run --rm --name pmm-client -e
PMM AGENT SERVER ADDRESS=\${PMM SERVER} -e

PMM AGENT SERVER USERNAME=admin -e

PMM_AGENT_SERVER_PASSWORD=124578 -e

PMM_AGENT_SERVER_INSECURE_TLS=1 -e PMM_AGENT_SETUP=1 -e

PMM_AGENT_CONFIG_FILE=config/pmm-agent.yaml --volumes-from pmm-client-data percona/pmm-client:2 &

ctrl + c 를 누르고

docker exec pmm-client ₩ > pmm-admin status

로 상태를 확인해볼 수 있다.