CHALMERS | UNIVERSITY OF GOTHENBURG

Real-Time Systems

Lecture #2

Professor Jan Jonsson

Department of Computer Science and Engineering
Chalmers University of Technology

CHALMERS | UNIVERSITY OF GOTHENBURG

Real-time systems

Specification

Implementation

Verification

• Programming paradigm
• Concurrent programming

CHALMERS | UNIVERSITY OF GOTHENBURG

Real-time programming

Recommended programming paradigm:

- Concurrent programming
  - Reduces unnecessary dependencies between tasks
  - Enables a composable schedulability analysis

- Reactive programming
  - Certifies that tasks are activated only when work should be done; tasks are kept idle otherwise
  - Maps directly to the task model used in schedulability analysis

- Timing-aware programming
  - Certifies that timing constraints are visible at the task level
  - Enables priority-based scheduling of tasks, which in turn facilitates schedulability analysis

---

CHALMERS | UNIVERSITY OF GOTHENBURG

Real-time programming

Desired properties of a real-time programming language:

- Support for partitioning software into units of concurrency
  - tasks or threads (Ada95, Java or POSIX C)
  - object methods (C/C++ using the TinyTimber kernel)

- Support for communication with the environment
  - access to I/O hardware (e.g. view I/O registers as variables)
  - machine-level data types (e.g. bit-field type, address pointers)

- Support for the schedulability analysis
  - notion of (high-resolution) time ($\Rightarrow$ timing-aware programming)
  - task priorities (reflects constraints $\Rightarrow$ timing-aware programming)
  - task delays (idle while not doing useful work $\Rightarrow$ reactive model)
  - hardware interrupt handlers (event generators $\Rightarrow$ reactive model)

CHALMERS | UNIVERSITY OF GOTHENBURG

Real-time programming

What programming languages are suitable?
- C, C++
  - Support for machine-level programming
  - Concurrent programming via run-time system (POSIX, TinyTimber)
  - Priorities and notion of time via run-time system (POSIX, TinyTimber)
- Java
  - Support for machine-level programming
  - Support for concurrent programming (threads)
  - Support for priorities and notion of time (Real-Time Java)
- Ada 95
  - Support for machine-level programming
  - Support for concurrent programming (tasks)
  - Support for priorities and notion of time

CHALMERS | UNIVERSITY OF GOTHENBURG

Why concurrent programming?

Most real-time applications are inherently parallel
- Events in the target system's environment often occur in parallel
- By viewing the application as consisting of multiple tasks, this parallel reality can be reflected
- While a task is waiting for an event (e.g., I/O or access to a shared resource) other tasks may execute

Enables a composable schedulability analysis
- First, the local timing properties of each task are derived
- Then, the interference between tasks are analyzed

System can obtain reliability properties
- Redundant copies of the same task makes system fault-tolerant

---

CHALMERS | UNIVERSITY OF GOTHENBURG

Issues with concurrent programming

Access to shared resources
- Many hardware and software resources can only be used by one task at a time (e.g., processor, data structures)
- Only pseudo-parallel access is possible in many cases

Synchronization and information exchange
- System modeling using concurrent tasks also introduces a need for synchronization and information exchange.

Concurrent programming must hence be supported by an advanced run-time system that handles the scheduling of shared resources and communication between tasks.

CHALMERS | UNIVERSITY OF GOTHENBURG

Support for concurrent programming

Support in the programming language:
- Program is easier to read and comprehend, which means simpler program maintenance
- Program code can be easily moved to another operating system
- For some embedded systems, a full-fledged operating system is unnecessarily expensive and complicated
- Examples: Ada 95, Java, Modula, Occam, ...

Example:

Ada 95 offers support via task, rendezvous & protected objects

Java offers support via threads & synchronized methods

CHALMERS | UNIVERSITY OF GOTHENBURG

Support for concurrent programming

Support in the run-time system:
- Simpler to combine programs written in different languages whose concurrent programming models are incompatible
- There may not exist a simple one-to-one mapping between the language's model and the run-time system's model
- Operating systems become more and more standardized, which makes program code more portable between OS's (e.g., POSIX for UNIX, Linux, Mac OS X, and Windows)

Example:
UNIX, Linux, etc offer support via fork, semctl & msgctl
POSIX offers support via threads & mutex methods
TinyTimber offers support via reactive objects & mutex methods

---

CHALMERS | UNIVERSITY OF GOTHENBURG

Example: a simple control system

Objective: Keep temperature and pressure for a chemical process within given bounds.

Thermometer — ADC
Pressure sensor
Switch — T — P — ADC
Heater
S
Screen — DAC — Pump/valve

CHALMERS | UNIVERSITY OF GOTHENBURG

Sequential solution (Ada95)

```
procedure Controller is
  TR : Temp_Reading;
  PR : Pressure_Reading;
  HS : Heater_Setting;
  PS : Pressure_Setting;
begin
  loop
    T_Read(TR);                 -- read temperature
    Temp_Convert(TR,HS);        -- convert to temperature setting
    T_Write(HS);                -- to temperature switch
    PrintLine("Temperature: ", TR); -- to screen

    P_Read(PR);                 -- read pressure
    Pressure_Convert(PR,PS);    -- convert to pressure setting
    P_Write(PS);                -- to pressure control
    PrintLine("Pressure: ", PR);  -- to screen
  end loop;
end Controller;
```

CHALMERS | UNIVERSITY OF GOTHENBURG

Sequential solution (C)

```
void Controller() {
  Temp_Reading TR;
  Pressure_Reading PR;
  Heater_Setting HS;
  Pressure_Setting PS;

  while (1) {
    T_Read(&TR);                 -- read temperature
    Temp_Convert(TR,&HS);        -- convert to heater setting
    T_Write(HS);                 -- set temperature switch
    PrintLine("Temperature: ", TR); -- write to screen

    P_Read(&PR);                 -- read pressure
    Pressure_Convert(PR,&PS);    -- convert to pressure setting
    P_Write(PS);                 -- set pressure control
    PrintLine("Pressure: ", PR);  -- write to screen
  }
}
```

CHALMERS | UNIVERSITY OF GOTHENBURG

Sequential solution

Drawback:
- the inherent parallelism of the application is not exploited
  - Procedures `T_Read` and `P_Read` block the execution until a new temperature or pressure sample is available from the sensor
  - while waiting to read the temperature, no attention can be given to the pressure (and vice versa)
  - if the call for reading the temperature does not return because of a fault, it is no longer possible to read the pressure
- the independence of the control functions are not considered
  - temperature and pressure must be read with the same interval
  - the iteration frequency of the loop is mainly determined by the blocking time of the calls to `T_Read` and `P_Read`.

CHALMERS | UNIVERSITY OF GOTHENBURG

Improved sequential solution (C)

The Boolean function **Ready_Temp** indicates whether a sample from the sensor is available

```
void Controller() {
 ...;

 while (1) {
  if (Ready_Temp()) {
   T_Read(&TR);              -- read temperature
   Temp_Convert(TR,&HS);     -- convert to heater setting
   T_Write(HS);              -- set temperature switch
   PrintLine("Temperature: ", TR);
  }

  if (Ready_Pres()) {
   P_Read(&PR);              -- read pressure
   Pressure_Convert(PR,&PS); -- convert to pressure setting
   P_Write(PS);              -- set pressure control
   PrintLine("Pressure: ", PR);
  }
 }
}
```

CHALMERS | UNIVERSITY OF GOTHENBURG

Improved sequential solution

Advantages:
- the inherent parallelism of the application is exploited
  - pressure and temperature control do not block each other

Drawbacks:
- the program spends a large amount of time in "busy wait" loops
  - processor capacity is unnecessarily wasted
  - schedulability analysis is made complicated/impossible
- the independence of the control functions is not considered
  - if the call for reading the temperature does not return because of a fault, it is no longer possible to read the pressure

---

CHALMERS | UNIVERSITY OF GOTHENBURG

Concurrent solution

Step 1: Make concurrent:
- Partition the software into units of concurrency

  Ada95:
  Create two units of type **task**, `T_Controller` and `P_Controller`, each containing the code for handling the data from respective sensor.

  TinyTimber: First create two objects, `T_Obj` and `P_Obj`, each with one method (`T_Controller` and `P_Controller`) containing the code for handling the data from respective sensor. Then create two interrupt handlers, one for each sensor, that calls the respective object method when data becomes available.

CHALMERS | UNIVERSITY OF GOTHENBURG

Concurrent solution

Step 2: Make reactive:

– Tasks should be idle if there is no work to be done

Ada95: Call the blocking procedures `T_Read` and `P_Read` to idle.

TinyTimber: Since methods `T_Controller` and `P_Controller` must be called to be activated they are by default idle.

– Activate task as a reaction to an incoming event

Ada95: A call to procedure `T_Read` or `P_Read` unblocks when data becomes available at a sensor, thus activating the calling task.

TinyTimber: An interrupt handler calls (activates) its corresponding method when data becomes available at a sensor.

CHALMERS | UNIVERSITY OF GOTHENBURG

Concurrent solution (Ada95)

```
procedure Controller is
task T_Controller;
task P_Controller;

task body T_Controller is
begin
   loop
      T_Read(TR);
      Temp_Convert(TR,HS);
      T_Write(HS);
      PrintLine("Temperature: ", TR);
   end loop;
end T_Controller;

task body P_Controller is
begin
   loop
      P_Read(PR);
      Pressure_Convert(PR,PS);
      P_Write(PS);
      PrintLine("Pressure: ", PR);
   end loop;
end P_Controller;

begin
   null;        -- begin parallel execution
end Controller;
```

CHALMERS | UNIVERSITY OF GOTHENBURG

Concurrent solution (TinyTimber)

```
// Define two new objects of TinyTimber basic class Object

Object T_Obj = InitObject();
Object P_Obj = InitObject();

// Declare the methods for each new object

void T_Controller(Object*, int);
void P_Controller(Object*, int);

// Define two new objects of class Sensor (definition not shown here),
// representing the sensors

Sensor sensor_t = initSensor(SENSOR_PORT0, &T_Obj, T_Controller);
Sensor sensor_p = initSensor(SENSOR_PORT1, &P_Obj, P_Controller);

...
```

CHALMERS | UNIVERSITY OF GOTHENBURG

Concurrent solution (TinyTimber)

```
// Define the methods for handling the input data. Each method is
// called with the data from the sensor as parameter.

void T_Controller(Object *self, int data) {
  Heater_Setting HS;

  Temp_Convert(data, &HS);        -- convert to heater setting
  T_Write(HS);                    -- set temperature switch
  PrintLine("Temperature: ", data);
}

void P_Controller(Object *self, int data) {
  Pressure_Setting PS;

  Temp_Convert(data, &PS);        -- convert to pressure setting
  P_Write(PS);                    -- set pressure control
  PrintLine("Pressure: ", data);
}

...
```

CHALMERS | UNIVERSITY OF GOTHENBURG

Concurrent solution (TinyTimber)

```
...

// Initialize the two sensor objects

void kickoff(Object *self, int unused) {
  SENSOR_INIT(&sensor_t);
  SENSOR_INIT(&sensor_p);
}

// Install interrupt handlers for the sensors, and then kick off
// the TinyTimber run-time system

int main() {
    INSTALL(&sensor_t, sensor_interrupt, SENSOR_INT0);
    INSTALL(&sensor_p, sensor_interrupt, SENSOR_INT1);
    TINYTIMBER(&P_Obj, kickoff, 0);
    return 0;
}
```

CHALMERS | UNIVERSITY OF GOTHENBURG

Concurrent solution

Advantages:
- the inherent parallelism of the application is fully exploited
  - pressure and temperature control do not block each other
  - the control functions can work at different frequencies
  - no processor capacity are unnecessarily consumed
  - the application becomes more reliable

Drawbacks:
- the parallel tasks share a common resource
  - the screen can only be used by one task at a time
  - a resource handler must be implemented, for controlling the access to the screen (to avoid garbled text)
  - the resource handler must guarantee *mutual exclusion* (*mutex*)

CHALMERS | UNIVERSITY OF GOTHENBURG

Example: control system

CHALMERS | UNIVERSITY OF GOTHENBURG

Solid concurrent solution (Ada95)

```
-- Protected objects in Ada95 guarantee mutual exclusion for their
   declared procedures: a calling task will be blocked if any of the
   procedures in the object are already being used.

protected type Screen_Controller is
  procedure T_Printline(data: in Temp_Reading);
  procedure P_Printline(data: in Pressure_Reading);
end Screen_Controller;

protected body Screen_Controller is
begin
  procedure T_Printline(data : in Temp_Reading) is
  begin
    Printline("Temperature: ", data);
  end T_Printline;

  procedure P_Printline(data : in Pressure_Reading) is
  begin
    Printline("Pressure: ", data);
  end P_Printline;
end Screen_Controller;
```

CHALMERS | UNIVERSITY OF GOTHENBURG

Solid concurrent solution (Ada95)

```
procedure Controller is
task T_Controller;
task P_Controller;

task body T_Controller is
begin
   loop
      T_Read(TR);
      Temp_Convert(TR,HS);
      T_Write(HS);
      Screen_Controller.T_PrintLine(TR);
   end loop;
end T_Controller;

task body P_Controller is
begin
   loop
      P_Read(PR);
      Pressure_Convert(PR,PS);
      P_Write(PS);
      Screen_Controller.P_PrintLine(PR);
   end loop;
end P_Controller;

begin
   null;        -- begin parallel execution
end Controller;
```

CHALMERS | UNIVERSITY OF GOTHENBURG

Solid concurrent solution (TinyTimber)

```
/*
 * TinyTimber objects guarantee mutual exclusion for their declared
 * methods: a call to the method will be blocked if any of the methods
 * in the object are already being used.
 */

// Define a new object of TinyTimber basic class Object

Object Screen_Controller = InitObject();

// Define mutex methods for the new object

void T_Printline(Object *self, int data) {
    PrintLine("Temperature: ", data);
}

void P_Printline(Object *self, int data) {
    PrintLine("Pressure: ", data);
}
```

CHALMERS | UNIVERSITY OF GOTHENBURG

Solid concurrent solution (TinyTimber)

```
/*
 * TinyTimber supports synchronous calls: the caller will be blocked
 * if any of the methods in the object are already being used.
 */

void T_Controller(Object *self, int data) {
  Heater_Setting HS;

  Temp_Convert(data, &HS);        -- convert to heater setting
  T_Write(HS);                    -- set temperature switch
  SYNC(&Screen_Controller, T_PrintLine, data);
}

void P_Controller(Object *self, int data) {
  Pressure_Setting PS;

  Temp_Convert(data, &PS);        -- convert to pressure setting
  P_Write(PS);                    -- set pressure control
  SYNC(&Screen_Controller, P_PrintLine, data);
}
```

CHALMERS | UNIVERSITY OF GOTHENBURG

Solid concurrent solution (TinyTimber)

```
/*
 * TinyTimber also supports asynchronous calls: the caller can continue
 * immediately after posting the method call, regardless of whether any
 * of the methods in the object are already being used or not.
 */

void T_Controller(Object *self, int data) {
  Heater_Setting HS;

  Temp_Convert(data, &HS);        -- convert to heater setting
  T_Write(HS);                    -- set temperature switch
  ASYNC(&Screen_Controller, T_PrintLine, data);
}

void P_Controller(Object *self, int data) {
  Pressure_Setting PS;

  Temp_Convert(data, &PS);        -- convert to pressure setting
  P_Write(PS);                    -- set pressure control
  ASYNC(&Screen_Controller, P_PrintLine, data);
}
```