Mouse Epithelium Dataset


SINGLE-CELL RNA-SEQ WITH BIOCONDUCTOR IN R




Fanny Perraudeau Senior Data Scientist, Whole Biome



Typical workflow




Stem Cell Differentiation in the Mouse Olfactory Epithelium



¹ Cell Stem Cell, Fletcher et al, Deconstructing Olfactory Stem Cell Trajectories at Single ² Cell Resolution (2017)



Stem Cell Differentiation in the Mouse Olfactory Epithelium



¹ Cell Stem Cell, Fletcher et al, Deconstructing Olfactory Stem Cell Trajectories at Single ² Cell Resolution (2017)



Let's practice!

SINGLE-CELL RNA-SEQ WITH BIOCONDUCTOR IN R



Visualization


SINGLE-CELL RNA-SEQ WITH BIOCONDUCTOR IN R



Fanny Perraudeau Senior Data Scientist, Whole Biome



Dimensionality reduction



¹ Cell Stem Cell, Fletcher et al, Deconstructing Olfactory Stem Cell Trajectories at Single ² Cell Resolution (2017)




Dimensionality reduction methods

- Principal component analysis (PCA)
- t-Distributed Stochastic Neighbor Embedding (tSNE)
- Zero inflated factor analysis (ZIFA) [1]
- Zero-inflated negative binomial wanted variation extraction (ZINB-WaVE) [2]

¹ ZIFA, Dimensionality reduction for zero ² inflated single ³ cell gene expression analysis (Emma Pierson and Christopher Yau) Genome Biology ⁴ A general and flexible method for signal extraction from single ⁵ cell RNA ⁶




Plot PCA



Plot t-SNE

```
plotTSNE(sce, exprs_values = "logcounts", shape_by = "Batch",
    colour_by = "publishedClusters", perplexity = 5)
```



Let's practice!

SINGLE-CELL RNA-SEQ WITH BIOCONDUCTOR IN R



Dimensionality Reduction

SINGLE-CELL RNA-SEQ WITH BIOCONDUCTOR IN R



Fanny Perraudeau Senior Data Scientist, Whole Biome



Most variable genes

```
library(magrittr)
vars <- assay(sce) %>% log1p %>% rowVars
names(vars) <- rownames(sce)
vars <- sort(vars, decreasing = TRUE)
head(vars)</pre>
```

```
      Cyp2g1
      Sec14l3
      Rgs5
      Sdc4
      Cbr2
      Cyp2f2

      15.40474
      14.72372
      14.08343
      13.25418
      13.10627
      12.68986
```

Subset sce

```
sce_sub <- sce[names(vars[1:50]),]
sce_sub</pre>
```

```
class: SingleCellExperiment
dim: 50 94
metadata(0):
assays(1): counts
rownames(50): Cyp2g1 Sec14l3 ... Calb2 Tmprss13
rowData names(0):
colnames(94): OEL19_N724_S503 OEL19_N719_S502 ...
  OEL23_N701_S511 OEL23_N703_S502
colData names(20): Experiment Batch ... ERCC_reads
  colPublishedClusters
reducedDimNames(0):
spikeNames(0):
```

Perform PCA

```
logcounts <- log1p(assay(sce_sub))
pca <- prcomp(t(logcounts))

reducedDims(sce_sub) <- SimpleList(PCA = pca$x)
sce_sub</pre>
```

```
class: SingleCellExperiment
dim: 50 94
metadata(0):
assays(1): counts
rownames(50): Cyp2g1 Sec14l3 ... Calb2 Tmprss13
rowData names(0):
colnames(94): OEL19_N724_S503 OEL19_N719_S502 ...
    OEL23_N701_S511 OEL23_N703_S502
colData names(20): Experiment Batch ... ERCC_reads
    colPublishedClusters
reducedDimNames(1): PCA
spikeNames(0):
```



Perform PCA

```
head(reducedDim(sce_sub, "PCA")[, 1:2])
```

```
PC1 PC2

OEL19_N724_S503 -18.63651 3.7905674

OEL19_N719_S502 21.53071 1.2738851


OEL21_N712_S507 20.93405 -0.1382121

OEL19_N723_S506 -17.60803 4.7438350

OEL19_N720_S507 20.69562 2.5815635

OEL19_N721_S510 -18.62802 4.7205441
```

Plot PCA



Let's practice!

SINGLE-CELL RNA-SEQ WITH BIOCONDUCTOR IN R

