# 21.17. smtplib — SMTP protocol client

Source code: Lib/smtplib.py

The smtplib module defines an SMTP client session object that can be used to send mail to any Internet machine with an SMTP or ESMTP listener daemon. For details of SMTP and ESMTP operation, consult RFC 821 (Simple Mail Transfer Protocol) and RFC 1869 (SMTP Service Extensions).

```
class smtplib. SMTP(host=", port=0, local_hostname=None, [timeout, ]
source_address=None)
```

An SMTP instance encapsulates an SMTP connection. It has methods that support a full repertoire of SMTP and ESMTP operations. If the optional host and port parameters are given, the SMTP connect() method is called with those parameters during initialization. If specified, <code>local\_hostname</code> is used as the FQDN of the local host in the HELO/EHLO command. Otherwise, the local hostname is found using <code>socket.getfqdn()</code>. If the <code>connect()</code> call returns anything other than a success code, an <code>SMTPConnectError</code> is raised. The optional <code>timeout</code> parameter specifies a timeout in seconds for blocking operations like the connection attempt (if not specified, the global default timeout setting will be used). If the timeout expires, <code>socket.timeout</code> is raised. The optional source\_address parameter allows binding to some specific source address in a machine with multiple network interfaces, and/or to some specific source TCP port. It takes a 2-tuple (host, port), for the socket to bind to as its source address before connecting. If omitted (or if host or port are '' and/or 0 respectively) the OS default behavior will be used

For normal use, you should only require the initialization/connect, sendmail(), and quit() methods. An example is included below.

The SMTP class supports the with statement. When used like this, the SMTP QUIT command is issued automatically when the with statement exits. E.g.:

```
>>> from smtplib import SMTP
>>> with SMTP("domain.org") as smtp:
... smtp.noop()
...
(250, b'Ok')
>>>
```

Changed in version 3.3: Support for the with statement was added.

Changed in version 3.3: source\_address argument was added.

New in version 3.5: The SMTPUTF8 extension (RFC 6531) is now supported.

class smtplib. SMTP\_SSL(host=", port=0, local\_hostname=None, keyfile=None, certfile=None, [timeout, ]context=None, source\_address=None)

An SMTP\_SSL instance behaves exactly the same as instances of SMTP. SMTP\_SSL should be used for situations where SSL is required from the beginning of the connection and using starttls() is not appropriate. If host is not specified, the local host is used. If port is zero, the standard SMTP-over-SSL port (465) is used. The optional arguments local\_hostname, timeout and source\_address have the same meaning as they do in the SMTP class. context, also optional, can contain a SSLContext and allows configuring various aspects of the secure connection. Please read Security considerations for best practices.

*keyfile* and *certfile* are a legacy alternative to *context*, and can point to a PEM formatted private key and certificate chain file for the SSL connection.

Changed in version 3.3: context was added.

Changed in version 3.3: source address argument was added.

Changed in version 3.4: The class now supports hostname check with ssl.SSLContext.check\_hostname and Server Name Indication (see ssl.HAS SNI).

Deprecated since version 3.6: keyfile and certfile are deprecated in favor of context. Please use ssl.SSLContext.load\_cert\_chain() instead, or let ssl.create\_default\_context() select the system's trusted CA certificates for you.

class smtplib. LMTP(host=", port=LMTP\_PORT, local\_hostname=None,
source\_address=None)

The LMTP protocol, which is very similar to ESMTP, is heavily based on the standard SMTP client. It's common to use Unix sockets for LMTP, so our connect() method must support that as well as a regular host:port server. The optional arguments local\_hostname and source\_address have the same meaning as they do in the SMTP class. To specify a Unix socket, you must use an absolute path for *host*, starting with a '/'.

Authentication is supported, using the regular SMTP mechanism. When using a Unix socket, LMTP generally don't support or require any authentication, but your mileage might vary.

A nice selection of exceptions is defined as well:

## exception smtplib. SMTPException

Subclass of OSError that is the base exception class for all the other exceptions provided by this module.

Changed in version 3.4: SMTPException became subclass of OSError

## exception smtplib. SMTPServerDisconnected

This exception is raised when the server unexpectedly disconnects, or when an attempt is made to use the SMTP instance before connecting it to a server.

## exception smtplib. SMTPResponseException

Base class for all exceptions that include an SMTP error code. These exceptions are generated in some instances when the SMTP server returns an error code. The error code is stored in the smtp\_code attribute of the error, and the smtp\_error attribute is set to the error message.

## exception smtplib. SMTPSenderRefused

Sender address refused. In addition to the attributes set by on all SMTPResponseException exceptions, this sets 'sender' to the string that the SMTP server refused.

## exception smtplib. SMTPRecipientsRefused

All recipient addresses refused. The errors for each recipient are accessible through the attribute recipients, which is a dictionary of exactly the same sort as SMTP.sendmail() returns.

#### exception smtplib. SMTPDataError

The SMTP server refused to accept the message data.

## exception smtplib. SMTPConnectError

Error occurred during establishment of a connection with the server.

#### exception smtplib. SMTPHeloError

The server refused our HELO message.

## exception smtplib. SMTPNotSupportedError

The command or option attempted is not supported by the server.

New in version 3.5.

#### exception smtplib. SMTPAuthenticationError

SMTP authentication went wrong. Most probably the server didn't accept the username/password combination provided.

#### See also:

#### **RFC 821 - Simple Mail Transfer Protocol**

Protocol definition for SMTP. This document covers the model, operating procedure, and protocol details for SMTP.

#### RFC 1869 - SMTP Service Extensions

Definition of the ESMTP extensions for SMTP. This describes a framework for extending SMTP with new commands, supporting dynamic discovery of the commands provided by the server, and defines a few additional commands.

## 21.17.1. SMTP Objects

An SMTP instance has the following methods:

## SMTP. set\_debuglevel(level)

Set the debug output level. A value of 1 or True for *level* results in debug messages for connection and for all messages sent to and received from the server. A value of 2 for *level* results in these messages being timestamped.

Changed in version 3.5: Added debuglevel 2.

## SMTP. docmd(cmd, args=")

Send a command *cmd* to the server. The optional argument *args* is simply concatenated to the command, separated by a space.

This returns a 2-tuple composed of a numeric response code and the actual response line (multiline responses are joined into one long line.)

In normal operation it should not be necessary to call this method explicitly. It is used to implement other methods and may be useful for testing private extensions.

If the connection to the server is lost while waiting for the reply, SMTPServerDisconnected will be raised.

## SMTP. **connect**(host='localhost', port=0)

Connect to a host on a given port. The defaults are to connect to the local host at the standard SMTP port (25). If the hostname ends with a colon (':') followed by a number, that suffix will be stripped off and the number interpreted as the port number to use. This method is automatically invoked by the constructor if a host is specified during instantiation. Returns a 2-tuple of the response code and message sent by the server in its connection response.

## SMTP. **helo**(name=")

Identify yourself to the SMTP server using HELO. The hostname argument defaults to the fully qualified domain name of the local host. The message returned by the server is stored as the helo resp attribute of the object.

In normal operation it should not be necessary to call this method explicitly. It will be implicitly called by the sendmail() when necessary.

## SMTP. ehlo(name=")

Identify yourself to an ESMTP server using EHLO. The hostname argument defaults to the fully qualified domain name of the local host. Examine the response for ESMTP option and store them for use by has\_extn(). Also sets several informational attributes: the message returned by the server is stored as the ehlo\_resp attribute, does\_esmtp is set to true or false depending on whether the server supports ESMTP, and esmtp\_features will be a dictionary containing the names of the SMTP service extensions this server supports, and their parameters (if any).

Unless you wish to use has\_extn() before sending mail, it should not be necessary to call this method explicitly. It will be implicitly called by sendmail() when necessary.

## SMTP.ehlo\_or\_helo\_if\_needed()

This method call ehlo() and or helo() if there has been no previous EHLO or HELO command this session. It tries ESMTP EHLO first.

#### SMTPHeloError

The server didn't reply properly to the HELO greeting.

## SMTP. has extn(name)

Return True if *name* is in the set of SMTP service extensions returned by the server, False otherwise. Case is ignored.

## SMTP. verify(address)

Check the validity of an address on this server using SMTP VRFY. Returns a tuple consisting of code 250 and a full **RFC 822** address (including human name) if the user address is valid. Otherwise returns an SMTP error code of 400 or greater and an error string.

**Note:** Many sites disable SMTP VRFY in order to foil spammers.

## SMTP. login(user, password, \*, initial\_response\_ok=True)

Log in on an SMTP server that requires authentication. The arguments are the username and the password to authenticate with. If there has been no previous EHLO or HELO command this session, this method tries ESMTP EHLO first. This

method will return normally if the authentication was successful, or may raise the following exceptions:

#### SMTPHeloError

The server didn't reply properly to the HELO greeting.

#### SMTPAuthenticationError

The server didn't accept the username/password combination.

#### SMTPNotSupportedError

The AUTH command is not supported by the server.

#### **SMTPException**

No suitable authentication method was found.

Each of the authentication methods supported by smtplib are tried in turn if they are advertised as supported by the server. See auth() for a list of supported authentication methods. *initial\_response\_ok* is passed through to auth().

Optional keyword argument *initial\_response\_ok* specifies whether, for authentication methods that support it, an "initial response" as specified in **RFC 4954** can be sent along with the AUTH command, rather than requiring a challenge/response.

Changed in version 3.5: SMTPNotSupportedError may be raised, and the initial\_response\_ok parameter was added.

## SMTP. auth(mechanism, authobject, \*, initial response ok=True)

Issue an SMTP AUTH command for the specified authentication *mechanism*, and handle the challenge response via *authobject*.

mechanism specifies which authentication mechanism is to be used as argument to the AUTH command; the valid values are those listed in the auth element of esmtp features.

authobject must be a callable object taking an optional single argument:

data = authobject(challenge=None)

If optional keyword argument <code>initial\_response\_ok</code> is true, <code>authobject()</code> will be called first with no argument. It can return the RFC 4954 "initial response" bytes which will be encoded and sent with the AUTH command as below. If the <code>authobject()</code> does not support an initial response (e.g. because it requires a challenge), it should return <code>None</code> when called with <code>challenge=None</code>. If <code>initial\_response\_ok</code> is false, then <code>authobject()</code> will not be called first with <code>None</code>.

If the initial response check returns None, or if <code>initial\_response\_ok</code> is false, <code>authobject()</code> will be called to process the server's challenge response; the <code>challenge</code> argument it is passed will be a bytes. It should return bytes <code>data</code> that will be base64 encoded and sent to the server.

The SMTP class provides authobjects for the CRAM-MD5, PLAIN, and LOGIN mechanisms; they are named SMTP.auth\_cram\_md5, SMTP.auth\_plain, and SMTP.auth\_login respectively. They all require that the user and password properties of the SMTP instance are set to appropriate values.

User code does not normally need to call auth directly, but can instead call the login() method, which will try each of the above mechanisms in turn, in the order listed. auth is exposed to facilitate the implementation of authentication methods not (or not yet) supported directly by smtplib.

New in version 3.5.

## SMTP. **starttls**(*keyfile=None*, *certfile=None*, *context=None*)

Put the SMTP connection in TLS (Transport Layer Security) mode. All SMTP commands that follow will be encrypted. You should then call ehlo() again.

If *keyfile* and *certfile* are provided, these are passed to the socket module's ssl() function.

Optional *context* parameter is a ssl.SSLContext object; This is an alternative to using a keyfile and a certfile and if specified both *keyfile* and *certfile* should be None.

If there has been no previous EHLO or HELO command this session, this method tries ESMTP EHLO first.

#### SMTPHeloError

The server didn't reply properly to the HELO greeting.

#### SMTPNotSupportedError

The server does not support the STARTTLS extension.

#### RuntimeError

SSL/TLS support is not available to your Python interpreter.

Changed in version 3.3: context was added.

Changed in version 3.4: The method now supports hostname check with SSLContext.check hostname and Server Name Indicator (see HAS SNI).

Changed in version 3.5: The error raised for lack of STARTTLS support is now the SMTPNotSupportedError subclass instead of the base SMTPException.

SMTP. sendmail(from addr, to addrs, msg, mail options=[], rcpt options=[])

Send mail. The required arguments are an RFC 822 from-address string, a list of RFC 822 to-address strings (a bare string will be treated as a list with 1 address), and a message string. The caller may pass a list of ESMTP options (such as 8bitmime) to be used in MAIL FROM commands as mail\_options. ESMTP options (such as DSN commands) that should be used with all RCPT commands can be passed as rcpt\_options. (If you need to use different ESMTP options to different recipients you have to use the low-level methods such as mail(), rcpt() and data() to send the message.)

**Note:** The *from\_addr* and *to\_addrs* parameters are used to construct the message envelope used by the transport agents. sendmail does not modify the message headers in any way.

msg may be a string containing characters in the ASCII range, or a byte string. A string is encoded to bytes using the ascii codec, and lone \r and \n characters are converted to \r\n characters. A byte string is not modified.

If there has been no previous EHLO or HELO command this session, this method tries ESMTP EHLO first. If the server does ESMTP, message size and each of the specified options will be passed to it (if the option is in the feature set the server advertises). If EHLO fails, HELO will be tried and ESMTP options suppressed.

This method will return normally if the mail is accepted for at least one recipient. Otherwise it will raise an exception. That is, if this method does not raise an exception, then someone should get your mail. If this method does not raise an exception, it returns a dictionary, with one entry for each recipient that was refused. Each entry contains a tuple of the SMTP error code and the accompanying error message sent by the server.

If SMTPUTF8 is included in *mail\_options*, and the server supports it, *from\_addr* and *to addrs* may contain non-ASCII characters.

This method may raise the following exceptions:

#### SMTPRecipientsRefused

All recipients were refused. Nobody got the mail. The recipients attribute of the exception object is a dictionary with information about the refused recipients (like the one returned when at least one recipient was accepted).

#### SMTPHeloError

The server didn't reply properly to the HELO greeting.

#### **SMTPSenderRefused**

The server didn't accept the from addr.

#### SMTPDataError

The server replied with an unexpected error code (other than a refusal of a recipient).

#### SMTPNotSupportedError

SMTPUTF8 was given in the *mail\_options* but is not supported by the server.

Unless otherwise noted, the connection will be open even after an exception is raised.

Changed in version 3.2: msg may be a byte string.

Changed in version 3.5: SMTPUTF8 support added, and SMTPNotSupportedError may be raised if SMTPUTF8 is specified but the server does not support it.

SMTP. send\_message(msg, from\_addr=None, to\_addrs=None, mail\_options=[], rcpt\_options=[])

This is a convenience method for calling <code>sendmail()</code> with the message represented by an <code>email.message.Message</code> object. The arguments have the same meaning as for <code>sendmail()</code>, except that <code>msg</code> is a Message object.

If from\_addr is None or to\_addrs is None, send\_message fills those arguments with addresses extracted from the headers of msg as specified in RFC 5322: from\_addr is set to the Sender field if it is present, and otherwise to the From field. to\_addrs combines the values (if any) of the To, Cc, and Bcc fields from msg. If exactly one set of Resent-\* headers appear in the message, the regular headers are ignored and the Resent-\* headers are used instead. If the message contains more than one set of Resent-\* headers, a ValueError is raised, since there is no way to unambiguously detect the most recent set of Resent- headers.

send\_message serializes *msg* using BytesGenerator with \r\n as the *linesep*, and calls sendmail() to transmit the resulting message. Regardless of the values of *from\_addr* and *to\_addrs*, send\_message does not transmit any *Bcc* or *Resent-Bcc* headers that may appear in *msg*. If any of the addresses in *from\_addr* and *to\_addrs* contain non-ASCII characters and the server does not advertise SMTPUTF8 support, an SMTPNotSupported error is raised. Otherwise the Message is serialized with a clone of its policy with the utf8 attribute set to True, and SMTPUTF8 and BODY=8BITMIME are added to *mail\_options*.

New in version 3.2.

New in version 3.5: Support for internationalized addresses (SMTPUTF8).

```
SMTP.quit()
```

Terminate the SMTP session and close the connection. Return the result of the SMTP QUIT command.

Low-level methods corresponding to the standard SMTP/ESMTP commands HELP, RSET, NOOP, MAIL, RCPT, and DATA are also supported. Normally these do not need to be called directly, so they are not documented here. For details, consult the module code.

## 21.17.2. SMTP Example

This example prompts the user for addresses needed in the message envelope ('To' and 'From' addresses), and the message to be delivered. Note that the headers to be included with the message must be included in the message as entered; this example doesn't do any processing of the RFC 822 headers. In particular, the 'To' and 'From' addresses must be included in the message headers explicitly.

```
import smtplib
def prompt(prompt):
    return input(prompt).strip()
fromaddr = prompt("From: ")
toaddrs = prompt("To: ").split()
print("Enter message, end with ^D (Unix) or ^Z (Windows):")
# Add the From: and To: headers at the start!
msg = ("From: %s\r\nTo: %s\r\n"
       % (fromaddr, ", ".join(toaddrs)))
while True:
   try:
        line = input()
   except EOFError:
        break
   if not line:
        break
   msg = msg + line
print("Message length is", len(msg))
server = smtplib.SMTP('localhost')
server.set debuglevel(1)
server.sendmail(fromaddr, toaddrs, msg)
server.quit()
```

**Note:** In general, you will want to use the email package's features to construct an email message, which you can then send via send\_message(); see email: Examples.