29.2. sysconfig — Provide access to Python's configuration information

New in version 3.2.

Source code: Lib/sysconfig.py

The sysconfig module provides access to Python's configuration information like the list of installation paths and the configuration variables relevant for the current platform.

29.2.1. Configuration variables

A Python distribution contains a Makefile and a pyconfig.h header file that are necessary to build both the Python binary itself and third-party C extensions compiled using distutils.

sysconfig puts all variables found in these files in a dictionary that can be accessed using get config vars() or get config var().

Notice that on Windows, it's a much smaller set.

```
sysconfig.get_config_vars(*args)
```

With no arguments, return a dictionary of all configuration variables relevant for the current platform.

With arguments, return a list of values that result from looking up each argument in the configuration variable dictionary.

For each argument, if the value is not found, return None.

```
sysconfig.get_config_var(name)
```

Return the value of a single variable *name*. Equivalent to get_config_vars ().get(name).

If name is not found, return None.

Example of usage:

```
>>> import sysconfig
>>> sysconfig.get_config_var('Py_ENABLE_SHARED')
0
>>> sysconfig.get_config_var('LIBDIR')
```

```
'/usr/local/lib'
>>> sysconfig.get_config_vars('AR', 'CXX')
['ar', 'g++']
```

29.2.2. Installation paths

Python uses an installation scheme that differs depending on the platform and on the installation options. These schemes are stored in sysconfig under unique identifiers based on the value returned by os.name.

Every new component that is installed using distutils or a Distutils-based system will follow the same scheme to copy its file in the right places.

Python currently supports seven schemes:

- posix_prefix: scheme for Posix platforms like Linux or Mac OS X. This is the default scheme used when Python or a component is installed.
- *posix_home*: scheme for Posix platforms used when a *home* option is used upon installation. This scheme is used when a component is installed through Distutils with a specific home prefix.
- *posix_user*: scheme for Posix platforms used when a component is installed through Distutils and the *user* option is used. This scheme defines paths located under the user home directory.
- nt: scheme for NT platforms like Windows.
- nt_user: scheme for NT platforms, when the user option is used.

Each scheme is itself composed of a series of paths and each path has a unique identifier. Python currently uses eight paths:

- *stdlib*: directory containing the standard Python library files that are not platform-specific.
- platstdlib: directory containing the standard Python library files that are platform-specific.
- platlib: directory for site-specific, platform-specific files.
- purelib: directory for site-specific, non-platform-specific files.
- include: directory for non-platform-specific header files.
- platinclude: directory for platform-specific header files.
- scripts: directory for script files.
- · data: directory for data files.

sysconfig provides some functions to determine these paths.

```
sysconfig.get_scheme_names()
```

Return a tuple containing all schemes currently supported in sysconfig.

```
sysconfig.get_path_names()
```

Return a tuple containing all path names currently supported in sysconfig.

```
sysconfig.get_path(name[, scheme[, vars[, expand]]])
```

Return an installation path corresponding to the path *name*, from the install scheme named *scheme*.

name has to be a value from the list returned by get_path_names().

sysconfig stores installation paths corresponding to each path name, for each platform, with variables to be expanded. For instance the *stdlib* path for the *nt* scheme is: {base}/Lib.

get_path() will use the variables returned by get_config_vars() to expand the path. All variables have default values for each platform so one may call this function and get the default value.

If *scheme* is provided, it must be a value from the list returned by get_scheme_names(). Otherwise, the default scheme for the current platform is used.

If *vars* is provided, it must be a dictionary of variables that will update the dictionary return by get_config_vars().

If expand is set to False, the path will not be expanded using the variables.

If name is not found, return None.

```
sysconfig.get_paths([scheme[, vars[, expand]]])
```

Return a dictionary containing all installation paths corresponding to an installation scheme. See get path() for more information.

If *scheme* is not provided, will use the default scheme for the current platform.

If *vars* is provided, it must be a dictionary of variables that will update the dictionary used to expand the paths.

If *expand* is set to false, the paths will not be expanded.

If scheme is not an existing scheme, get paths() will raise a KeyError.

29.2.3. Other functions

```
sysconfig.get_python_version()
```

Return the MAJOR.MINOR Python version number as a string. Similar to '%d.%d' % sys.version_info[:2].

sysconfig.get_platform()

Return a string that identifies the current platform.

This is used mainly to distinguish platform-specific build directories and platform-specific built distributions. Typically includes the OS name and version and the architecture (as supplied by os.uname()), although the exact information included depends on the OS; e.g. for IRIX the architecture isn't particularly important (IRIX only runs on SGI hardware), but for Linux the kernel version isn't particularly important.

Examples of returned values:

- linux-i586
- linux-alpha (?)
- solaris-2.6-sun4u
- irix-5.3
- irix64-6.2

Windows will return one of:

- win-amd64 (64bit Windows on AMD64 (aka x86_64, Intel64, EM64T, etc)
- win-ia64 (64bit Windows on Itanium)
- win32 (all others specifically, sys.platform is returned)

Mac OS X can return:

- macosx-10.6-ppc
- macosx-10.4-ppc64
- macosx-10.3-i386
- macosx-10.4-fat

For other non-POSIX platforms, currently just returns sys.platform.

sysconfig.is_python_build()

Return True if the running Python interpreter was built from source and is being run from its built location, and not from a location resulting from e.g. running make install or installing via a binary installer.

sysconfig. $parse_config_h(fp[, vars])$

Parse a config.h-style file.

fp is a file-like object pointing to the config.h-like file.

A dictionary containing name/value pairs is returned. If an optional dictionary is passed in as the second argument, it is used instead of a new dictionary, and updated with the values read in the file.

```
sysconfig.get_config_h_filename()
Return the path of pyconfig.h.

sysconfig.get_makefile_filename()
Return the path of Makefile.
```

29.2.4. Using sysconfig as a script

You can use sysconfig as a script with Python's -m option:

```
$ python -m sysconfig
Platform: "macosx-10.4-i386"
Python version: "3.2"
Current installation scheme: "posix_prefix"
Paths:
        data = "/usr/local"
        include = "/Users/tarek/Dev/svn.python.org/py3k/Include"
        platinclude = "."
        platlib = "/usr/local/lib/python3.2/site-packages"
        platstdlib = "/usr/local/lib/python3.2"
        purelib = "/usr/local/lib/python3.2/site-packages"
        scripts = "/usr/local/bin"
        stdlib = "/usr/local/lib/python3.2"
Variables:
        AC APPLE UNIVERSAL BUILD = "0"
        AIX GENUINE CPLUSPLUS = "0"
        AR = "ar"
        ARFLAGS = "rc"
```

This call will print in the standard output the information returned by get_platform (), get_python_version(), get_path() and get_config_vars().