Type Objects

Perhaps one of the most important structures of the Python object system is the structure that defines a new type: the PyTypeObject structure. Type objects can be handled using any of the PyObject_*() or PyType_*() functions, but do not offer much that's interesting to most Python applications. These objects are fundamental to how objects behave, so they are very important to the interpreter itself and to any extension module that implements new types.

Type objects are fairly large compared to most of the standard types. The reason for the size is that each type object stores a large number of values, mostly C function pointers, each of which implements a small part of the type's functionality. The fields of the type object are examined in detail in this section. The fields will be described in the order in which they occur in the structure.

Typedefs: unaryfunc, binaryfunc, ternaryfunc, inquiry, intargfunc, intintargfunc, intobjargproc, intintobjargproc, objobjargproc, destructor, freefunc, printfunc, getattrfunc, getattrofunc, setattrfunc, setattrofunc, reprfunc, hashfunc

The structure definition for PyTypeObject can be found in Include/object.h. For convenience of reference, this repeats the definition found there:

```
typedef struct _typeobject {
   PyObject_VAR_HEAD
   const char *tp_name; /* For printing, in format "<module>.<name>"
   Py_ssize_t tp_basicsize, tp_itemsize; /* For allocation */
   /* Methods to implement standard operations */
   destructor tp_dealloc;
   printfunc tp_print;
   getattrfunc tp_getattr;
   setattrfunc tp setattr;
   PyAsyncMethods *tp_as_async; /* formerly known as tp_compare (Pyth
                                    or tp reserved (Python 3) */
   reprfunc tp repr;
   /* Method suites for standard classes */
   PyNumberMethods *tp_as_number;
   PySequenceMethods *tp_as_sequence;
   PyMappingMethods *tp_as_mapping;
   /* More standard operations (here for binary compatibility) */
   hashfunc tp hash;
   ternaryfunc tp call;
```

```
reprfunc tp str;
getattrofunc tp getattro;
setattrofunc tp setattro;
/* Functions to access object as input/output buffer */
PyBufferProcs *tp as buffer;
/* Flags to define presence of optional/expanded features */
unsigned long tp flags;
const char *tp doc; /* Documentation string */
/* call function for all accessible objects */
traverseproc tp traverse;
/* delete references to contained objects */
inquiry tp clear;
/* rich comparisons */
richcmpfunc tp richcompare;
/* weak reference enabler */
Py ssize t tp weaklistoffset;
/* Iterators */
getiterfunc tp iter;
iternextfunc tp_iternext;
/* Attribute descriptor and subclassing stuff */
struct PyMethodDef *tp_methods;
struct PyMemberDef *tp members;
struct PyGetSetDef *tp getset;
struct _typeobject *tp_base;
PyObject *tp dict;
descrigetfunc to descriget;
descrsetfunc tp_descr_set;
Py_ssize_t tp_dictoffset;
initproc tp init;
allocfunc tp alloc;
newfunc tp new;
freefunc tp free; /* Low-level free-memory routine */
inquiry tp_is_gc; /* For PyObject_IS_GC */
PyObject *tp bases;
PyObject *tp mro; /* method resolution order */
PyObject *tp cache;
PyObject *tp subclasses;
PyObject *tp weaklist;
destructor tp_del;
/* Type attribute cache version tag. Added in version 2.6 */
unsigned int tp_version_tag;
```

```
destructor tp_finalize;
} PyTypeObject;
```

The type object structure extends the PyVarObject structure. The ob_size field is used for dynamic types (created by type_new(), usually called from a class statement). Note that PyType_Type (the metatype) initializes tp_itemsize, which means that its instances (i.e. type objects) *must* have the ob_size field.

```
PyObject* PyObject._ob_next
PyObject* PyObject._ob_prev
```

These fields are only present when the macro Py_TRACE_REFS is defined. Their initialization to *NULL* is taken care of by the PyObject_HEAD_INIT macro. For statically allocated objects, these fields always remain *NULL*. For dynamically allocated objects, these two fields are used to link the object into a doubly-linked list of *all* live objects on the heap. This could be used for various debugging purposes; currently the only use is to print the objects that are still alive at the end of a run when the environment variable PYTHONDUMPREFS is set.

These fields are not inherited by subtypes.

Py_ssize_t PyObject.ob_refcnt

This is the type object's reference count, initialized to 1 by the PyObject_HEAD_INIT macro. Note that for statically allocated type objects, the type's instances (objects whose ob_type points back to the type) do *not* count as references. But for dynamically allocated type objects, the instances *do* count as references.

This field is not inherited by subtypes.

PyTypeObject* PyObject.ob_type

This is the type's type, in other words its metatype. It is initialized by the argument to the PyObject HEAD INIT macro, and its value should normally be &PyType Type. However, for dynamically loadable extension modules that must be usable on Windows (at least), the compiler complains that this is not a valid initializer. Therefore. the convention is to pass **NULL** to the PyObject HEAD INIT macro and to initialize this field explicitly at the start of the module's initialization function, before doing anything else. This is typically done like this:

```
Foo_Type.ob_type = &PyType_Type;
```

This should be done before any instances of the type are created. PyType_Ready() checks if ob_type is *NULL*, and if so, initializes it to the

ob_type field of the base class. PyType_Ready() will not change this field if it is non-zero.

This field is inherited by subtypes.

Py_ssize_t PyVarObject.ob_size

For statically allocated type objects, this should be initialized to zero. For dynamically allocated type objects, this field has a special internal meaning.

This field is not inherited by subtypes.

const char* PyTypeObject.tp_name

Pointer to a NUL-terminated string containing the name of the type. For types that are accessible as module globals, the string should be the full module name, followed by a dot, followed by the type name; for built-in types, it should be just the type name. If the module is a submodule of a package, the full package name is part of the full module name. For example, a type named T defined in module M in subpackage Q in package P should have the tp_name initializer "P.Q.M.T".

For dynamically allocated type objects, this should just be the type name, and the module name explicitly stored in the type dict as the value for key '__module__'.

For statically allocated type objects, the tp_name field should contain a dot. Everything before the last dot is made accessible as the __module__ attribute, and everything after the last dot is made accessible as the __name__ attribute.

If no dot is present, the entire <code>tp_name</code> field is made accessible as the <code>__name__</code> attribute, and the <code>__module__</code> attribute is undefined (unless explicitly set in the dictionary, as explained above). This means your type will be impossible to pickle. Additionally, it will not be listed in module documentations created with pydoc.

This field is not inherited by subtypes.

Py_ssize_t PyTypeObject.tp_basicsize Py_ssize_t PyTypeObject.tp_itemsize

These fields allow calculating the size in bytes of instances of the type.

There are two kinds of types: types with fixed-length instances have a zero tp_itemsize field, types with variable-length instances have a non-zero tp_itemsize field. For a type with fixed-length instances, all instances have the same size, given in tp_basicsize.

For a type with variable-length instances, the instances must have an ob_size field, and the instance size is tp_basicsize plus N times tp_itemsize, where N is the "length" of the object. The value of N is typically stored in the instance's ob_size field. There are exceptions: for example, ints use a negative ob_size to indicate a negative number, and N is abs(ob_size) there. Also, the presence of an ob_size field in the instance layout doesn't mean that the instance structure is variable-length (for example, the structure for the list type has fixed-length instances, yet those instances have a meaningful ob_size field).

The basic size includes the fields in the instance declared by the macro PyObject_HEAD or PyObject_VAR_HEAD (whichever is used to declare the instance struct) and this in turn includes the _ob_prev and _ob_next fields if they are present. This means that the only correct way to get an initializer for the tp_basicsize is to use the sizeof operator on the struct used to declare the instance layout. The basic size does not include the GC header size.

These fields are inherited separately by subtypes. If the base type has a non-zero tp_itemsize, it is generally not safe to set tp_itemsize to a different non-zero value in a subtype (though this depends on the implementation of the base type).

A note about alignment: if the variable items require a particular alignment, this should be taken care of by the value of tp_basicsize. Example: suppose a type implements an array of double. tp_itemsize is sizeof(double). It is the programmer's responsibility that tp_basicsize is a multiple of sizeof(double) (assuming this is the alignment requirement for double).

destructor PyTypeObject.tp_dealloc

A pointer to the instance destructor function. This function must be defined unless the type guarantees that its instances will never be deallocated (as is the case for the singletons None and Ellipsis).

The destructor function is called by the Py_DECREF() and Py_XDECREF() macros when the new reference count is zero. At this point, the instance is still in existence, but there are no references to it. The destructor function should free all references which the instance owns, free all memory buffers owned by the instance (using the freeing function corresponding to the allocation function used to allocate the buffer), and finally (as its last action) call the type's tp_free function. If the type is not subtypable (doesn't have the Py_TPFLAGS_BASETYPE flag bit set), it is permissible to call the object deallocator directly instead of via tp_free. The object deallocator should be the one used to allocate the instance; this is normally PyObject_Del() if the instance was allocated using PyObject_New() or PyObject_GC_Del() if the instance was allocated using PyObject_GC_New() or PyObject_GC_New().

This field is inherited by subtypes.

printfunc PyTypeObject.tp_print

Reserved slot, formerly used for print formatting in Python 2.x.

getattrfunc PyTypeObject.tp_getattr

An optional pointer to the get-attribute-string function.

This field is deprecated. When it is defined, it should point to a function that acts the same as the tp_getattro function, but taking a C string instead of a Python string object to give the attribute name. The signature is

```
PyObject * tp_getattr(PyObject *o, char *attr_name);
```

This field is inherited by subtypes together with tp_getattro: a subtype inherits both tp_getattr and tp_getattro from its base type when the subtype's tp_getattr and tp_getattro are both *NULL*.

setattrfunc PyTypeObject.tp_setattr

An optional pointer to the function for setting and deleting attributes.

This field is deprecated. When it is defined, it should point to a function that acts the same as the tp_setattro function, but taking a C string instead of a Python string object to give the attribute name. The signature is

```
PyObject * tp_setattr(PyObject *o, char *attr_name, PyObject *v);
```

The *v* argument is set to *NULL* to delete the attribute. This field is inherited by subtypes together with tp_setattro: a subtype inherits both tp_setattr and tp_setattro from its base type when the subtype's tp_setattr and tp_setattro are both *NULL*.

PyAsyncMethods* tp_as_async

Pointer to an additional structure that contains fields relevant only to objects which implement awaitable and asynchronous iterator protocols at the C-level. See Async Object Structures for details.

New in version 3.5: Formerly known as tp_compare and tp_reserved.

reprfunc PyTypeObject.tp_repr

An optional pointer to a function that implements the built-in function repr().

The signature is the same as for PyObject_Repr(); it must return a string or a Unicode object. Ideally, this function should return a string that, when passed to eval(), given a suitable environment, returns an object with the same value. If

this is not feasible, it should return a string starting with '<' and ending with '>' from which both the type and the value of the object can be deduced.

When this field is not set, a string of the form <%s object at %p> is returned, where %s is replaced by the type name, and %p by the object's memory address.

This field is inherited by subtypes.

PyNumberMethods* tp_as_number

Pointer to an additional structure that contains fields relevant only to objects which implement the number protocol. These fields are documented in Number Object Structures.

The tp_as_number field is not inherited, but the contained fields are inherited individually.

PySequenceMethods* tp as sequence

Pointer to an additional structure that contains fields relevant only to objects which implement the sequence protocol. These fields are documented in Sequence Object Structures.

The tp_as_sequence field is not inherited, but the contained fields are inherited individually.

PyMappingMethods* tp_as_mapping

Pointer to an additional structure that contains fields relevant only to objects which implement the mapping protocol. These fields are documented in Mapping Object Structures.

The tp_as_mapping field is not inherited, but the contained fields are inherited individually.

hashfunc PyTypeObject.tp_hash

An optional pointer to a function that implements the built-in function hash().

The signature is the same as for PyObject_Hash(); it must return a value of the type Py_hash_t. The value -1 should not be returned as a normal return value; when an error occurs during the computation of the hash value, the function should set an exception and return -1.

This field can be set explicitly to PyObject_HashNotImplemented() to block inheritance of the hash method from a parent type. This is interpreted as the equivalent of __hash__ = None at the Python level, causing isinstance(o, collections.Hashable) to correctly return False. Note that the converse is

also true - setting __hash__ = None on a class at the Python level will result in the tp_hash slot being set to PyObject_HashNotImplemented().

When this field is not set, an attempt to take the hash of the object raises TypeError.

This field is inherited by subtypes together with tp_richcompare: a subtype inherits both of tp_richcompare and tp_hash, when the subtype's tp_richcompare and tp_hash are both *NULL*.

ternaryfunc PyTypeObject.tp_call

An optional pointer to a function that implements calling the object. This should be *NULL* if the object is not callable. The signature is the same as for PyObject_Call().

This field is inherited by subtypes.

reprfunc PyTypeObject.tp str

An optional pointer to a function that implements the built-in operation str(). (Note that str is a type now, and str() calls the constructor for that type. This constructor calls PyObject_Str() to do the actual work, and PyObject_Str() will call this handler.)

The signature is the same as for PyObject_Str(); it must return a string or a Unicode object. This function should return a "friendly" string representation of the object, as this is the representation that will be used, among other things, by the print() function.

When this field is not set, PyObject_Repr() is called to return a string representation.

This field is inherited by subtypes.

getattrofunc PyTypeObject.tp_getattro

An optional pointer to the get-attribute function.

The signature is the same as for PyObject_GetAttr(). It is usually convenient to set this field to PyObject_GenericGetAttr(), which implements the normal way of looking for object attributes.

This field is inherited by subtypes together with tp_getattr: a subtype inherits both tp_getattr and tp_getattro from its base type when the subtype's tp_getattr and tp_getattro are both *NULL*.

setattrofunc PyTypeObject.tp_setattro

An optional pointer to the function for setting and deleting attributes.

The signature is the same as for $PyObject_SetAttr()$, but setting v to NULL to delete an attribute must be supported. It is usually convenient to set this field to $PyObject_GenericSetAttr()$, which implements the normal way of setting object attributes.

This field is inherited by subtypes together with tp_setattr: a subtype inherits both tp_setattr and tp_setattro from its base type when the subtype's tp_setattr and tp_setattro are both *NULL*.

PyBufferProcs* PyTypeObject.tp_as_buffer

Pointer to an additional structure that contains fields relevant only to objects which implement the buffer interface. These fields are documented in Buffer Object Structures.

The tp_as_buffer field is not inherited, but the contained fields are inherited individually.

unsigned long PyTypeObject.tp_flags

This field is a bit mask of various flags. Some flags indicate variant semantics for certain situations; others are used to indicate that certain fields in the type object (or in the extension structures referenced via tp_as_number, tp_as_sequence, tp_as_mapping, and tp_as_buffer) that were historically not always present are valid; if such a flag bit is clear, the type fields it guards must not be accessed and must be considered to have a zero or *NULL* value instead.

Inheritance of this field is complicated. Most flag bits are inherited individually, i.e. if the base type has a flag bit set, the subtype inherits this flag bit. The flag bits that pertain to extension structures are strictly inherited if the extension structure is inherited, i.e. the base type's value of the flag bit is copied into the subtype together with a pointer to the extension structure. The Py_TPFLAGS_HAVE_GC flag bit is inherited together with the tp_traverse and tp_clear fields, i.e. if the Py_TPFLAGS_HAVE_GC flag bit is clear in the subtype and the tp_traverse and tp_clear fields in the subtype exist and have NULL values.

The following bit masks are currently defined; these can be ORed together using the | operator to form the value of the tp_flags field. The macro PyType_HasFeature() takes a type and a flags value, tp and f, and checks whether tp->tp flags & f is non-zero.

Py_TPFLAGS_HEAPTYPE

This bit is set when the type object itself is allocated on the heap. In this case, the ob_type field of its instances is considered a reference to the type, and the type object is INCREF'ed when a new instance is created, and DECREF'ed when an instance is destroyed (this does not apply to instances of subtypes; only the type referenced by the instance's ob_type gets INCREF'ed or DECREF'ed).

Py_TPFLAGS_BASETYPE

This bit is set when the type can be used as the base type of another type. If this bit is clear, the type cannot be subtyped (similar to a "final" class in Java).

Py TPFLAGS READY

This bit is set when the type object has been fully initialized by PyType_Ready().

Py_TPFLAGS_READYING

This bit is set while PyType_Ready() is in the process of initializing the type object.

Py TPFLAGS HAVE GC

This bit is set when the object supports garbage collection. If this bit is set, instances must be created using PyObject_GC_New() and destroyed using PyObject_GC_Del(). More information in section Supporting Cyclic Garbage Collection. This bit also implies that the GC-related fields tp_traverse and tp_clear are present in the type object.

Py_TPFLAGS_DEFAULT

This is a bitmask of all the bits that pertain to the existence of certain fields in the type object and its extension structures. Currently, it includes the following bits: Py_TPFLAGS_HAVE_STACKLESS_EXTENSION, Py_TPFLAGS_HAVE_VERSION_TAG.

Py_TPFLAGS_LONG_SUBCLASS

Py_TPFLAGS_LIST_SUBCLASS

Py_TPFLAGS_TUPLE_SUBCLASS

Py_TPFLAGS_BYTES_SUBCLASS

Py_TPFLAGS_UNICODE_SUBCLASS

Py_TPFLAGS_DICT_SUBCLASS

Py_TPFLAGS_BASE_EXC_SUBCLASS

Py TPFLAGS TYPE SUBCLASS

These flags are used by functions such as PyLong_Check() to quickly determine if a type is a subclass of a built-in type; such specific checks are faster than a generic check, like PyObject_IsInstance(). Custom types that inherit from built-ins should have their tp_flags set appropriately, or the code that interacts with such types will behave differently depending on what kind of check is used.

Py_TPFLAGS_HAVE_FINALIZE

This bit is set when the tp_finalize slot is present in the type structure.

New in version 3.4.

const char* PyTypeObject.tp_doc

An optional pointer to a NUL-terminated C string giving the docstring for this type object. This is exposed as the __doc__ attribute on the type and instances of the type.

This field is *not* inherited by subtypes.

traverseproc PyTypeObject.tp_traverse

An optional pointer to a traversal function for the garbage collector. This is only used if the Py_TPFLAGS_HAVE_GC flag bit is set. More information about Python's garbage collection scheme can be found in section Supporting Cyclic Garbage Collection.

The tp_traverse pointer is used by the garbage collector to detect reference cycles. A typical implementation of a tp_traverse function simply calls Py_VISIT() on each of the instance's members that are Python objects. For example, this is function local_traverse() from the _thread extension module:

```
static int
local_traverse(localobject *self, visitproc visit, void *arg)
{
    Py_VISIT(self->args);
    Py_VISIT(self->kw);
    Py_VISIT(self->dict);
    return 0;
}
```

Note that Py_VISIT() is called only on those members that can participate in reference cycles. Although there is also a self->key member, it can only be *NULL* or a Python string and therefore cannot be part of a reference cycle.

On the other hand, even if you know a member can never be part of a cycle, as a debugging aid you may want to visit it anyway just so the gc module's get_referents() function will include it.

Note that Py_VISIT() requires the *visit* and *arg* parameters to local_traverse () to have these specific names; don't name them just anything.

This field is inherited by subtypes together with tp_clear and the Py_TPFLAGS_HAVE_GC flag bit: the flag bit, tp_traverse, and tp_clear are all inherited from the base type if they are all zero in the subtype.

inquiry PyTypeObject.tp_clear

An optional pointer to a clear function for the garbage collector. This is only used if the Py_TPFLAGS_HAVE_GC flag bit is set.

The tp_clear member function is used to break reference cycles in cyclic garbage detected by the garbage collector. Taken together, all tp_clear functions in the system must combine to break all reference cycles. This is subtle, and if in any doubt supply a tp_clear function. For example, the tuple type does not implement a tp_clear function, because it's possible to prove that no reference cycle can be composed entirely of tuples. Therefore the tp_clear functions of other types must be sufficient to break any cycle containing a tuple. This isn't immediately obvious, and there's rarely a good reason to avoid implementing tp_clear.

Implementations of tp_clear should drop the instance's references to those of its members that may be Python objects, and set its pointers to those members to *NULL*, as in the following example:

```
static int
local_clear(localobject *self)
{
    Py_CLEAR(self->key);
    Py_CLEAR(self->args);
    Py_CLEAR(self->kw);
    Py_CLEAR(self->kw);
    return 0;
}
```

The Py_CLEAR() macro should be used, because clearing references is delicate: the reference to the contained object must not be decremented until after the pointer to the contained object is set to *NULL*. This is because decrementing the reference count may cause the contained object to become trash, triggering a chain of reclamation activity that may include invoking arbitrary Python code (due to finalizers, or weakref callbacks, associated with the contained object). If

it's possible for such code to reference *self* again, it's important that the pointer to the contained object be *NULL* at that time, so that *self* knows the contained object can no longer be used. The Py_CLEAR() macro performs the operations in a safe order.

Because the goal of tp_clear functions is to break reference cycles, it's not necessary to clear contained objects like Python strings or Python integers, which can't participate in reference cycles. On the other hand, it may be convenient to clear all contained Python objects, and write the type's tp_dealloc function to invoke tp_clear.

More information about Python's garbage collection scheme can be found in section Supporting Cyclic Garbage Collection.

This field is inherited by subtypes together with tp_traverse and the Py_TPFLAGS_HAVE_GC flag bit: the flag bit, tp_traverse, and tp_clear are all inherited from the base type if they are all zero in the subtype.

richcmpfunc PyTypeObject.tp_richcompare

An optional pointer to the rich comparison function, whose signature is PyObject *tp_richcompare(PyObject *a, PyObject *b, int op). The first parameter is guaranteed to be an instance of the type that is defined by PyTypeObject.

The function should return the result of the comparison (usually Py_True or Py_False). If the comparison is undefined, it must return Py_NotImplemented, if another error occurred it must return NULL and set an exception condition.

Note: If you want to implement a type for which only a limited set of comparisons makes sense (e.g. == and !=, but not < and friends), directly raise TypeError in the rich comparison function.

This field is inherited by subtypes together with tp_hash: a subtype inherits tp_richcompare and tp_hash when the subtype's tp_richcompare and tp_hash are both *NULL*.

The following constants are defined to be used as the third argument for tp_richcompare and for PyObject_RichCompare():

omparison

Constant	Comparison
Py_NE	!=
Py_GT	>
Py_GE	>=

Py_ssize_t PyTypeObject.tp_weaklistoffset

If the instances of this type are weakly referenceable, this field is greater than zero and contains the offset in the instance structure of the weak reference list head (ignoring the GC header, if present); this offset is used by PyObject_ClearWeakRefs() and the PyWeakref_*() functions. The instance structure needs to include a field of type PyObject* which is initialized to NULL.

Do not confuse this field with tp_weaklist; that is the list head for weak references to the type object itself.

This field is inherited by subtypes, but see the rules listed below. A subtype may override this offset; this means that the subtype uses a different weak reference list head than the base type. Since the list head is always found via tp_weaklistoffset, this should not be a problem.

When a type defined by a class statement has no __slots__ declaration, and none of its base types are weakly referenceable, the type is made weakly referenceable by adding a weak reference list head slot to the instance layout and setting the tp_weaklistoffset of that slot's offset.

When a type's __slots__ declaration contains a slot named __weakref__, that slot becomes the weak reference list head for instances of the type, and the slot's offset is stored in the type's tp_weaklistoffset.

When a type's __slots__ declaration does not contain a slot named __weakref__, the type inherits its tp_weaklistoffset from its base type.

getiterfunc PyTypeObject.tp_iter

An optional pointer to a function that returns an iterator for the object. Its presence normally signals that the instances of this type are iterable (although sequences may be iterable without this function).

This function has the same signature as PyObject GetIter().

This field is inherited by subtypes.

iternextfunc PyTypeObject.tp iternext

An optional pointer to a function that returns the next item in an iterator. When the iterator is exhausted, it must return *NULL*; a StopIteration exception may

or may not be set. When another error occurs, it must return *NULL* too. Its presence signals that the instances of this type are iterators.

Iterator types should also define the tp_iter function, and that function should return the iterator instance itself (not a new iterator instance).

This function has the same signature as PyIter_Next().

This field is inherited by subtypes.

struct PyMethodDef* PyTypeObject.tp_methods

An optional pointer to a static *NULL*-terminated array of PyMethodDef structures, declaring regular methods of this type.

For each entry in the array, an entry is added to the type's dictionary (see tp_dict below) containing a method descriptor.

This field is not inherited by subtypes (methods are inherited through a different mechanism).

struct PyMemberDef* PyTypeObject.tp_members

An optional pointer to a static *NULL*-terminated array of PyMemberDef structures, declaring regular data members (fields or slots) of instances of this type.

For each entry in the array, an entry is added to the type's dictionary (see tp_dict below) containing a member descriptor.

This field is not inherited by subtypes (members are inherited through a different mechanism).

struct PyGetSetDef* PyTypeObject.tp_getset

An optional pointer to a static *NULL*-terminated array of PyGetSetDef structures, declaring computed attributes of instances of this type.

For each entry in the array, an entry is added to the type's dictionary (see tp dict below) containing a getset descriptor.

This field is not inherited by subtypes (computed attributes are inherited through a different mechanism).

PyTypeObject* PyTypeObject.tp_base

An optional pointer to a base type from which type properties are inherited. At this level, only single inheritance is supported; multiple inheritance require dynamically creating a type object by calling the metatype.

This field is not inherited by subtypes (obviously), but it defaults to &PyBaseObject_Type (which to Python programmers is known as the type object).

PyObject* PyTypeObject.tp_dict

The type's dictionary is stored here by PyType_Ready().

This field should normally be initialized to *NULL* before PyType_Ready is called; it may also be initialized to a dictionary containing initial attributes for the type. Once PyType_Ready() has initialized the type, extra attributes for the type may be added to this dictionary only if they don't correspond to overloaded operations (like __add__()).

This field is not inherited by subtypes (though the attributes defined in here are inherited through a different mechanism).

Warning: It is not safe to use PyDict_SetItem() on or otherwise modify tp_dict with the dictionary C-API.

descrgetfunc PyTypeObject.tp_descr_get

An optional pointer to a "descriptor get" function.

The function signature is

```
Py0bject * tp_descr_get(Py0bject *self, Py0bject *obj, Py0bject *t
```

This field is inherited by subtypes.

descrsetfunc PyTypeObject.tp_descr_set

An optional pointer to a function for setting and deleting a descriptor's value.

The function signature is

```
int tp_descr_set(PyObject *self, PyObject *obj, PyObject *value);
```

The *value* argument is set to *NULL* to delete the value. This field is inherited by subtypes.

Py_ssize_t PyTypeObject.tp_dictoffset

If the instances of this type have a dictionary containing instance variables, this field is non-zero and contains the offset in the instances of the type of the instance variable dictionary; this offset is used by PyObject_GenericGetAttr().

Do not confuse this field with tp_dict; that is the dictionary for attributes of the type object itself.

If the value of this field is greater than zero, it specifies the offset from the start of the instance structure. If the value is less than zero, it specifies the offset from the *end* of the instance structure. A negative offset is more expensive to use, and should only be used when the instance structure contains a variable-length part. This is used for example to add an instance variable dictionary to subtypes of str or tuple. Note that the tp_basicsize field should account for the dictionary added to the end in that case, even though the dictionary is not included in the basic object layout. On a system with a pointer size of 4 bytes, tp_dictoffset should be set to -4 to indicate that the dictionary is at the very end of the structure.

The real dictionary offset in an instance can be computed from a negative tp_dictoffset as follows:

```
dictoffset = tp_basicsize + abs(ob_size)*tp_itemsize + tp_dictoffs
if dictoffset is not aligned on sizeof(void*):
    round up to sizeof(void*)
```

where tp_basicsize, tp_itemsize and tp_dictoffset are taken from the type object, and ob_size is taken from the instance. The absolute value is taken because into use the sign of ob_size to store the sign of the number. (There's never a need to do this calculation yourself; it is done for you by _PyObject_GetDictPtr().)

This field is inherited by subtypes, but see the rules listed below. A subtype may override this offset; this means that the subtype instances store the dictionary at a difference offset than the base type. Since the dictionary is always found via tp_dictoffset, this should not be a problem.

When a type defined by a class statement has no __slots__ declaration, and none of its base types has an instance variable dictionary, a dictionary slot is added to the instance layout and the tp_dictoffset is set to that slot's offset.

When a type defined by a class statement has a __slots__ declaration, the type inherits its tp_dictoffset from its base type.

(Adding a slot named __dict__ to the __slots__ declaration does not have the expected effect, it just causes confusion. Maybe this should be added as a feature just like __weakref__ though.)

An optional pointer to an instance initialization function.

This function corresponds to the __init__() method of classes. Like __init__(), it is possible to create an instance without calling __init__(), and it is possible to reinitialize an instance by calling its __init__() method again.

The function signature is

```
int tp_init(PyObject *self, PyObject *args, PyObject *kwds)
```

The self argument is the instance to be initialized; the *args* and *kwds* arguments represent positional and keyword arguments of the call to <u>init</u> ().

The tp_init function, if not *NULL*, is called when an instance is created normally by calling its type, after the type's tp_new function has returned an instance of the type. If the tp_new function returns an instance of some other type that is not a subtype of the original type, no tp_init function is called; if tp_new returns an instance of a subtype of the original type, the subtype's tp_init is called.

This field is inherited by subtypes.

allocfunc PyTypeObject.tp_alloc

An optional pointer to an instance allocation function.

The function signature is

```
PyObject *tp_alloc(PyTypeObject *self, Py_ssize_t nitems)
```

The purpose of this function is to separate memory allocation from memory initialization. It should return a pointer to a block of memory of adequate length for the instance, suitably aligned, and initialized to zeros, but with ob_refcnt set to 1 and ob_type set to the type argument. If the type's tp_itemsize is non-zero, the object's ob_size field should be initialized to *nitems* and the length of the allocated memory block should be tp_basicsize + nitems*tp_itemsize, rounded up to a multiple of sizeof(void*); otherwise, *nitems* is not used and the length of the block should be tp_basicsize.

Do not use this function to do any other instance initialization, not even to allocate additional memory; that should be done by tp_new.

This field is inherited by static subtypes, but not by dynamic subtypes (subtypes created by a class statement); in the latter, this field is always set to PyType_GenericAlloc(), to force a standard heap allocation strategy. That is also the recommended value for statically defined types.

newfunc PyTypeObject.tp_new

An optional pointer to an instance creation function.

If this function is *NULL* for a particular type, that type cannot be called to create new instances; presumably there is some other way to create instances, like a factory function.

The function signature is

```
PyObject *tp_new(PyTypeObject *subtype, PyObject *args, PyObject *
```

The subtype argument is the type of the object being created; the *args* and *kwds* arguments represent positional and keyword arguments of the call to the type. Note that subtype doesn't have to equal the type whose tp_new function is called; it may be a subtype of that type (but not an unrelated type).

The tp_new function should call subtype->tp_alloc(subtype, nitems) to allocate space for the object, and then do only as much further initialization as is absolutely necessary. Initialization that can safely be ignored or repeated should be placed in the tp_init handler. A good rule of thumb is that for immutable types, all initialization should take place in tp_new, while for mutable types, most initialization should be deferred to tp_init.

This field is inherited by subtypes, except it is not inherited by static types whose tp_base is *NULL* or &PyBaseObject_Type.

destructor PyTypeObject.tp_free

An optional pointer to an instance deallocation function. Its signature is freefunc:

```
void tp_free(void *)
```

An initializer that is compatible with this signature is PyObject Free().

This field is inherited by static subtypes, but not by dynamic subtypes (subtypes created by a class statement); in the latter, this field is set to a deallocator suitable to match PyType_GenericAlloc() and the value of the Py_TPFLAGS_HAVE_GC flag bit.

inquiry PyTypeObject.tp_is_gc

An optional pointer to a function called by the garbage collector.

The garbage collector needs to know whether a particular object is collectible or not. Normally, it is sufficient to look at the object's type's tp_flags field, and

check the Py_TPFLAGS_HAVE_GC flag bit. But some types have a mixture of statically and dynamically allocated instances, and the statically allocated instances are not collectible. Such types should define this function; it should return 1 for a collectible instance, and 0 for a non-collectible instance. The signature is

```
int tp_is_gc(PyObject *self)
```

(The only example of this are types themselves. The metatype, PyType_Type, defines this function to distinguish between statically and dynamically allocated types.)

This field is inherited by subtypes.

PyObject* PyTypeObject.tp_bases

Tuple of base types.

This is set for types created by a class statement. It should be *NULL* for statically defined types.

This field is not inherited.

PyObject* PyTypeObject.tp mro

Tuple containing the expanded set of base types, starting with the type itself and ending with object, in Method Resolution Order.

This field is not inherited; it is calculated fresh by PyType Ready().

destructor PyTypeObject.tp finalize

An optional pointer to an instance finalization function. Its signature is destructor:

```
void tp_finalize(PyObject *)
```

If tp_finalize is set, the interpreter calls it once when finalizing an instance. It is called either from the garbage collector (if the instance is part of an isolated reference cycle) or just before the object is deallocated. Either way, it is guaranteed to be called before attempting to break reference cycles, ensuring that it finds the object in a sane state.

tp_finalize should not mutate the current exception status; therefore, a recommended way to write a non-trivial finalizer is:

```
static void
local_finalize(PyObject *self)
{
    PyObject *error_type, *error_value, *error_traceback;
```

```
/* Save the current exception, if any. */
PyErr_Fetch(&error_type, &error_value, &error_traceback);

/* ... */

/* Restore the saved exception. */
PyErr_Restore(error_type, error_value, error_traceback);
}
```

For this field to be taken into account (even through inheritance), you must also set the Py_TPFLAGS_HAVE_FINALIZE flags bit.

This field is inherited by subtypes.

New in version 3.4.

```
See also: "Safe object finalization" (PEP 442)
```

PyObject* PyTypeObject.tp_cache

Unused. Not inherited. Internal use only.

PyObject* PyTypeObject.tp_subclasses

List of weak references to subclasses. Not inherited. Internal use only.

PyObject* PyTypeObject.tp_weaklist

Weak reference list head, for weak references to this type object. Not inherited. Internal use only.

The remaining fields are only defined if the feature test macro COUNT_ALLOCS is defined, and are for internal use only. They are documented here for completeness. None of these fields are inherited by subtypes.

```
Py_ssize_t PyTypeObject.tp_allocs
Number of allocations.
```

```
Py_ssize_t PyTypeObject.tp_frees
Number of frees.
```

Py_ssize_t PyTypeObject.tp_maxalloc

Maximum simultaneously allocated objects.

PyTypeObject* PyTypeObject.tp_next

Pointer to the next type object with a non-zero tp_allocs field.

Also, note that, in a garbage collected Python, tp_dealloc may be called from any Python thread, not just the thread which created the object (if the object becomes part of a refcount cycle, that cycle might be collected by a garbage collection on any thread). This is not a problem for Python API calls, since the thread on which tp_dealloc is called will own the Global Interpreter Lock (GIL). However, if the object being destroyed in turn destroys objects from some other C or C++ library, care should be taken to ensure that destroying those objects on the thread which called tp_dealloc will not violate any assumptions of the library.

Number Object Structures

PyNumberMethods

This structure holds pointers to the functions which an object uses to implement the number protocol. Each function is used by the function of similar name documented in the Number Protocol section.

Here is the structure definition:

```
typedef struct {
     binaryfunc nb_add;
     binaryfunc nb_subtract;
     binaryfunc nb multiply;
     binaryfunc nb_remainder;
     binaryfunc nb divmod;
     ternaryfunc nb power;
     unaryfunc nb negative;
     unaryfunc nb positive;
     unaryfunc nb absolute;
     inquiry nb bool;
     unaryfunc nb invert;
     binaryfunc nb lshift;
     binaryfunc nb rshift;
     binaryfunc nb and;
     binaryfunc nb xor;
     binaryfunc nb or;
     unaryfunc nb int;
     void *nb reserved;
     unaryfunc nb float;
     binaryfunc nb inplace add;
     binaryfunc nb inplace subtract;
     binaryfunc nb inplace multiply;
     binaryfunc nb_inplace_remainder;
     ternaryfunc nb inplace power;
     binaryfunc nb inplace lshift;
     binaryfunc nb inplace rshift;
     binaryfunc nb_inplace_and;
```

```
binaryfunc nb_inplace_xor;
binaryfunc nb_inplace_or;

binaryfunc nb_floor_divide;
binaryfunc nb_true_divide;
binaryfunc nb_inplace_floor_divide;
binaryfunc nb_inplace_true_divide;

unaryfunc nb_index;

binaryfunc nb_matrix_multiply;
binaryfunc nb_inplace_matrix_multiply;
}
```

Note: Binary and ternary functions must check the type of all their operands, and implement the necessary conversions (at least one of the operands is an instance of the defined type). If the operation is not defined for the given operands, binary and ternary functions must return Py_NotImplemented, if another error occurred they must return NULL and set an exception.

Note: The nb_reserved field should always be NULL. It was previously called nb_long, and was renamed in Python 3.0.1.

Mapping Object Structures

PyMappingMethods

This structure holds pointers to the functions which an object uses to implement the mapping protocol. It has three members:

lenfunc PyMappingMethods.mp_length

This function is used by PyMapping_Size() and PyObject_Size(), and has the same signature. This slot may be set to *NULL* if the object has no defined length.

binaryfunc PyMappingMethods.mp_subscript

This function is used by PyObject_GetItem() and PySequence_GetSlice(), and has the same signature as PyObject_GetItem(). This slot must be filled for the PyMapping Check() function to return 1, it can be NULL otherwise.

objobjargproc PyMappingMethods.mp_ass_subscript

This function is used by PyObject_SetItem(), PyObject_DelItem(), PyObject_SetSlice() and PyObject_DelSlice(). It has the same signature as PyObject_SetItem(), but *v* can also be set to *NULL* to delete an item. If this slot is *NULL*, the object does not support item assignment and deletion.

Sequence Object Structures

PySequenceMethods

This structure holds pointers to the functions which an object uses to implement the sequence protocol.

lenfunc PySequenceMethods.sq_length

This function is used by PySequence_Size() and PyObject_Size(), and has the same signature. It is also used for handling negative indices via the sq_item and the sq_ass_item slots.

binaryfunc PySequenceMethods.sq_concat

This function is used by PySequence_Concat() and has the same signature. It is also used by the + operator, after trying the numeric addition via the nb_add slot.

ssizeargfunc PySequenceMethods.sq_repeat

This function is used by PySequence_Repeat() and has the same signature. It is also used by the * operator, after trying numeric multiplication via the nb_multiply slot.

ssizeargfunc PySequenceMethods.sq_item

This function is used by PySequence_GetItem() and has the same signature. It is also used by PyObject_GetItem(), after trying the subscription via the mp_subscript slot. This slot must be filled for the PySequence_Check() function to return 1, it can be NULL otherwise.

Negative indexes are handled as follows: if the sq_length slot is filled, it is called and the sequence length is used to compute a positive index which is passed to sq_item. If sq_length is *NULL*, the index is passed as is to the function.

$ssize objarg proc\ \textbf{PySequenceMethods.sq_ass_item}$

This function is used by PySequence_SetItem() and has the same signature. It is also used by PyObject_SetItem() and PyObject_DelItem(), after trying the item assignment and deletion via the mp_ass_subscript slot. This slot may be left to NULL if the object does not support item assignment and deletion.

objobjproc PySequenceMethods.sq_contains

This function may be used by PySequence_Contains() and has the same signature. This slot may be left to *NULL*, in this case PySequence_Contains() simply traverses the sequence until it finds a match.

binaryfunc PySequenceMethods.sq inplace concat

This function is used by PySequence_InPlaceConcat() and has the same signature. It should modify its first operand, and return it. This slot may be left to NULL, in this case PySequence_InPlaceConcat() will fall back to PySequence_Concat(). It is also used by the augmented assignment +=, after trying numeric inplace addition via the nb_inplace_add slot.

ssizeargfunc PySequenceMethods.sq_inplace_repeat

This function is used by PySequence_InPlaceRepeat() and has the same signature. It should modify its first operand, and return it. This slot may be left to NULL, in this case PySequence_InPlaceRepeat() will fall back to PySequence_Repeat(). It is also used by the augmented assignment *=, after trying numeric inplace multiplication via the nb_inplace_multiply slot.

Buffer Object Structures

PyBufferProcs

This structure holds pointers to the functions required by the Buffer protocol. The protocol defines how an exporter object can expose its internal data to consumer objects.

getbufferproc PyBufferProcs.bf_getbuffer

The signature of this function is:

```
int (PyObject *exporter, Py_buffer *view, int flags);
```

Handle a request to *exporter* to fill in *view* as specified by *flags*. Except for point (3), an implementation of this function MUST take these steps:

- 1. Check if the request can be met. If not, raise PyExc_BufferError, set view->obj to NULL and return -1.
- 2. Fill in the requested fields.
- 3. Increment an internal counter for the number of exports.
- 4. Set view->obj to exporter and increment view->obj.
- 5. Return 0.

If *exporter* is part of a chain or tree of buffer providers, two main schemes can be used:

- Re-export: Each member of the tree acts as the exporting object and sets view->obj to a new reference to itself.
- Redirect: The buffer request is redirected to the root object of the tree. Here, view->obj will be a new reference to the root object.

The individual fields of *view* are described in section Buffer structure, the rules how an exporter must react to specific requests are in section Buffer request types.

All memory pointed to in the Py_buffer structure belongs to the exporter and must remain valid until there are no consumers left. format, shape, strides, suboffsets and internal are read-only for the consumer.

PyBuffer_FillInfo() provides an easy way of exposing a simple bytes buffer while dealing correctly with all request types.

PyObject_GetBuffer() is the interface for the consumer that wraps this function.

releasebufferproc PyBufferProcs.bf_releasebuffer

The signature of this function is:

```
void (PyObject *exporter, Py_buffer *view);
```

Handle a request to release the resources of the buffer. If no resources need to be released, PyBufferProcs.bf_releasebuffer may be *NULL*. Otherwise, a standard implementation of this function will take these optional steps:

- 1. Decrement an internal counter for the number of exports.
- 2. If the counter is 0, free all memory associated with *view*.

The exporter MUST use the internal field to keep track of buffer-specific resources. This field is guaranteed to remain constant, while a consumer MAY pass a copy of the original buffer as the *view* argument.

This function MUST NOT decrement view->obj, since that is done automatically in PyBuffer_Release() (this scheme is useful for breaking reference cycles).

PyBuffer Release() is the interface for the consumer that wraps this function.

Async Object Structures

New in version 3.5

PyAsyncMethods

This structure holds pointers to the functions required to implement awaitable and asynchronous iterator objects.

Here is the structure definition:

```
typedef struct {
    unaryfunc am_await;
    unaryfunc am_aiter;
    unaryfunc am_anext;
} PyAsyncMethods;
```

unaryfunc PyAsyncMethods.am_await

The signature of this function is:

```
PyObject *am_await(PyObject *self)
```

The returned object must be an iterator, i.e. PyIter_Check() must return 1 for it.

This slot may be set to *NULL* if an object is not an awaitable.

unaryfunc PyAsyncMethods.am_aiter

The signature of this function is:

```
PyObject *am_aiter(PyObject *self)
```

Must return an awaitable object. See __anext__() for details.

This slot may be set to *NULL* if an object does not implement asynchronous iteration protocol.

unaryfunc PyAsyncMethods.am_anext

The signature of this function is:

```
PyObject *am_anext(PyObject *self)
```

Must return an awaitable object. See __anext__() for details. This slot may be set to *NULL*.