IB Fluid Dynamics

Ishan Nath, Lent 2023

Based on Lectures by Prof. John Lister

February 2, 2023

Page 1 CONTENTS

Contents

0	Intr	roduction	2
1	Kin	Kinematics	
	1.1	Pathlines and Streamlines	3
	1.2	The Material Derivative	
	1.3	Conservation of Mass	4
	1.4	Kinematic Boundary Condition	6
	1.5	Stream Function for 2D Incompressible Flow	6
2	Dynamics of Inviscid Flow		9
	2.1	Surface and Volume Forces	9
	2.2	The Euler Momentum Equation	10
	2.3	Bernoulli's Equation for Steady Flow with Potential Forces	11
	2.4	Hydrostatic Pressure and Archimedes Principle	16
	2.5	Vorticity	16
		2.5.1 Interpretation of Vorticity	17
Index			19

0 Introduction

This course focuses on *fluids*: we can think of these are liquids or gases, or more rigorously objects which are described well by the Navier-Stokes equations.

Studying fluids puts us in the realm of *continuum mechanics*, where materials are modelled with continuous mass; of course, we know in reality they are discrete particles. Areas of continuum mechanics include:

- Fluid dynamics, concerned with liquids and gases.
- Solid mechanics, where we look at solids and their properties, and fracture mechanics.
- Other materials, such as complex fluid, soft matter, biomechanics, porous media, granular flow, and so on.

To obtain the continuum hypothesis, we average over the irrelevant molecular detail to get a continuous description in terms of *fields*. Important examples are *velocity* $\mathbf{u}(\mathbf{x},t)$, *pressure* $p(\mathbf{x},t)$ and *density* $\rho(\mathbf{x},t)$

In this course, we take ideas in physics: mass, momentum, Newton's laws, vector calculus, and other methods and combine them to find properties of the fields and accompanying forces.

This course starts looking at *kinematics*: properties of how fluids move, including velocities and trajectories. Then we delve into more serious *dynamics*, involving forces and equations of motions.

For simplicity, we consider *inviscid flow*. This gives a good approximation for water and air, apart from on small scales.

The obvious reason to study fluids is that fluids are everywhere: from our environment, in the oceans and atmosphere, to molecular biology; from aerosols to astrophysics.

Page 3 1 KINEMATICS

1 Kinematics

1.1 Pathlines and Streamlines

There are two natural perspectives to view a fluid $\mathbf{u}(\mathbf{x},t)$:

- 1. A passive approach; as a stationary observer watching the flow go past (the *Eulerian picture*).
- 2. An active approach; as a moving observer, travelling along with (same part of) the flow (the *Lagrangian picture*).

Taking the passive approach, one way to visualise the fluid is using *streamlines*. Streamlines are curves that are everywhere parallel to the flow at a given instant. These are given parametrically as

$$\mathbf{x} = \mathbf{x}(s; x_0, t_0), \text{ derived from } \frac{\mathrm{d}\mathbf{x}}{\mathrm{d}s} = \mathbf{u}(\mathbf{x}, t_0),$$

subject to initial condition $\mathbf{x} = \mathbf{x}_0$ at s = 0. These are similar to *characteristics* (which we will see later). At a given time, the set of streamlines shows the direction of flow at that instant - it shows all particles, at a fixed time. For $\mathbf{u} = (1, t)$, we get the streamlines seen in figure 1.

Figure 1: Streamlines of $\mathbf{u} = (1, t)$ for different t



In contrast, a *pathline* is when we look at the trajectory of a fluid 'particle' (which we can think of as a very small part of the fluid). The pathline $\mathbf{x} = \mathbf{x}(t; \mathbf{x}_0)$ of the particle that starts at \mathbf{x}_0 at t = 0 is found from

$$\frac{\mathrm{d}\mathbf{x}}{\mathrm{d}t} = \mathbf{u}(\mathbf{x}, t),$$


with initial conditions $\mathbf{x} = \mathbf{x}_0$ at t = 0. The set of pathlines give the flow of one particle, at all times. The pathline of $\mathbf{u} = (1, t)$ is graphed in figure 2.

We can consider many particles, such as all \mathbf{x}_0 in a given region, to see how the shape and position of a dyed patch of fluid evolves. This is useful for thinking about transport and mixing problems.

For steady-state flows, streamlines and pathlines are the same.

Page 4 1 KINEMATICS

Figure 2: Pathlines of $\mathbf{u} = (1, t)$ for three initial points



1.2 The Material Derivative

Both streamlines and pathlines are taken from the Eulerian picture: we are sitting outside and watching the fluid go by. Things are different if we are drifting with the fluid.

In particular, for a field $F(\mathbf{x},t)$, which may be density or velocity or something else we want to know, we can measure it with respect to some fixed position. However, if we are moving along with the fluid, then this field is changing: we can parametrize it as $F(\mathbf{x}(t),t)$. We can calculate

$$\delta F = F(\mathbf{x} + \delta \mathbf{x}, t + \delta t) - F(\mathbf{x}, t)$$
$$= \delta \mathbf{x} \cdot \nabla F + \delta t \frac{\partial F}{\partial t} + \mathcal{O}(\delta^2),$$

and we know $\delta \mathbf{x} = \mathbf{u}(\mathbf{x}, t)\delta t + \mathcal{O}(\delta^2)$, so these equations simplify to

$$\frac{DF}{Dt} = \frac{\partial F}{\partial t} + \mathbf{u} \cdot \nabla F,$$

where we use new notation for the total time derivative. The additional $\mathbf{u} \cdot \nabla F$ corresponds to the movement due to the fluid. This is called the *material derivative*, as it describes the rate of change of a field, when moving through a fluid (or material).

1.3 Conservation of Mass

Consider a (rigid) tube with constant cross-section, with fluid coming in with speed $\mathbf{u} = 2$, and exiting with speed $\mathbf{u} = 1$.

Page 5 1 KINEMATICS

For a fluid such as air, this could be conceivably possible: the air could be compressed in the tube.

However, with water this would be impossible, as the density of water ρ_{water} is relatively constant. Hence a difference in velocities means that mass is being destroyed.

This suggests that there must be a relationship between $\rho(\mathbf{x}, t)$ and $\mathbf{u}(\mathbf{x}, t)$ such that mass is never created or destroyed, so we go looking for such a relationship.

Consider an arbitrary volume V, fixed in space and bounded by a surface ∂V with outwards normal \mathbf{n} . Then the mass in V, which is

$$M = \int_{V} \rho \, \mathrm{d}V,$$

can only change if mass flows in or out at the surface ∂V . The amount of mass that escapes an area A over time t is $\rho \mathbf{u} \cdot \mathbf{n} \delta A \delta t$. We can think of $\rho \mathbf{u}$ as the mass flux. Integrating over V,

$$\frac{\mathrm{d}}{\mathrm{d}t} \int_{V} \rho \, \mathrm{d}V = -\int_{S} \rho \mathbf{u} \cdot \mathrm{d}\mathbf{S},$$

$$\iff \int_{V} \frac{\partial p}{\partial t} \, \mathrm{d}V = -\int_{V} \nabla \cdot (\rho \mathbf{u}) \, \mathrm{d}V,$$

where we have used the divergence theorem. Since this holds for all volumes V, we must have

$$\frac{\partial \rho}{\partial t} + \nabla \cdot (\rho \mathbf{u}) = 0.$$

Using $\nabla \cdot (\rho \mathbf{u}) = \mathbf{u} \cdot \nabla \rho + \rho \nabla \cdot \mathbf{u}$, we can rewrite this as

$$\frac{D\rho}{Dt} + \rho \nabla \cdot \mathbf{u} = 0.$$

Physically, this means that if a fluid is flowing away from a point, the density should decrease, and vice versa.

If a fluid is *incompressible*, then the density of the fluid is constant, so $\dot{\rho} = \nabla \rho = 0$. Hence the velocity must satisfy

$$\nabla \cdot \mathbf{u} = 0$$

for incompressible flow. In this course, we make the assumption that density is constant and uniform. This assumption is good when the speed of the fluid is much less than the speed of sound, which is around $330\,\mathrm{m\,s^{-1}}$ in air, and $1500\,\mathrm{m\,s^{-1}}$ in water.

Page 6 1 KINEMATICS

1.4 Kinematic Boundary Condition

Suppose that the material boundary of a body of fluid has velocity $\mathbf{U}(\mathbf{x},t)$. Then at a point \mathbf{x} on the boundary of the fluid, the velocity relative to the moving boundary is $\mathbf{u}(\mathbf{x},t) - \mathbf{U}(\mathbf{x},t)$.

The condition that there is no mass flux across the boundary can be written as $\rho(\mathbf{u} - \mathbf{U}) \cdot \mathbf{n} \, \delta A \delta t = 0$, or

$$\mathbf{n} \cdot \mathbf{u} = \mathbf{n} \cdot \mathbf{U}$$
.

Example 1.1.

- 1. For a stationary rigid boundary, $\mathbf{U} = 0$, so we must have $\mathbf{u} \cdot \mathbf{n} = 0$.
- 2. Water waves have an air-water interface $z = \eta(x, y, t)$. We can think of the water surface as a contour of the function $F(x, y, z, t) = z \eta(x, y, t)$.

Then the normal **n** will be parallel to $\nabla F = (-\eta_x, \eta_y, 1)$. Since **U** = $(0, 0, \eta_t)$, if we take **u** = (u, v, w), the boundary flux condition implies


$$-u\eta_x - v\eta_y + w = \eta_t.$$

This is equivalent to

$$\frac{D}{Dt}(z-\eta) = 0,$$

which means that particles on the surface of the wave will stay on the surface.

Figure 3: Surface of Water



1.5 Stream Function for 2D Incompressible Flow

Recall that a fluid is incompressible if $\nabla \cdot \mathbf{u} = 0$. However, this is equivalent to $\mathbf{u} = \nabla \times \mathbf{A}$ for some potential \mathbf{A} .

For two dimensional flows $\mathbf{u} = (u(x,y), v(x,y), 0)$, we can take

$$\mathbf{A} = (0, 0, \psi(x, y)) \implies \mathbf{u} = \left(\frac{\partial \psi}{\partial y}, -\frac{\partial \psi}{\partial x}, 0\right).$$

Page 7 1 KINEMATICS

Indeed, this implies

$$\frac{\partial u}{\partial x} + \frac{\partial v}{\partial y} = 0,$$

so **u** is divergence-free, as expected. We say that $\psi(x,y)$ is the stream function.

The stream function satisfies the following properties:

- (i) The streamlines are given by $\psi = C$ (so **u** is parallel to the contours of ψ).
- (ii) $|\mathbf{u}| = |\nabla \psi|$, so the flow is faster where the streamlines are closer together.
- (iii) The volume that is crossing the line from \mathbf{x}_0 to \mathbf{x}_1 is

$$\int_{\mathbf{x}_0}^{\mathbf{x}_1} \mathbf{u} \cdot \mathbf{n} \, \mathrm{d}l = \psi(\mathbf{x}_1) - \psi(\mathbf{x}_0).$$

(iv) ψ is constant on a stationary rigid boundary.

Example 1.2.

Take $\mathbf{u} = (y, x)$. Since $\nabla \cdot \mathbf{u} = 0$, a stream function exists. Integrating the above equations,

$$\frac{\partial \phi}{\partial y} = y \implies \psi = \frac{1}{2}y^2 + f(x),$$
$$-\frac{\partial \psi}{\partial x} = x \implies f(x) = -\frac{1}{2}x^2.$$

Hence the streamlines are

$$y^2 - x^2 = C.$$

In polar coordinates, we have $\mathbf{u} = (u_r(r,\theta), u_\theta(r,\theta), 0)$. If $\mathbf{A} = (0,0,\psi(r,\theta))$, then

$$\mathbf{u} = \nabla \times \mathbf{A} = \left(\frac{1}{r} \frac{\partial \psi}{\partial \theta}, -\frac{\partial \psi}{\partial r}, 0\right).$$

We can verify that

$$\nabla \cdot \mathbf{u} = \frac{1}{r} \frac{\partial}{\partial r} (r u_r) + \frac{1}{r} \frac{\partial u_\theta}{\partial \theta} = 0.$$

Axisymmetric flow in spherical polar coordinates has

$$u_{\phi} = \frac{\partial}{\partial \phi} = 0.$$

Page 8 1 KINEMATICS

If we have $\nabla \cdot \mathbf{u} = 0$, and we take

$$\mathbf{A} = \left(0, 0, \frac{\Psi(r, \theta)}{r \sin \theta}\right),\,$$

then

$$\mathbf{u} = \left(\frac{1}{r^2 \sin \theta} \frac{\partial \Psi}{\partial \theta}, -\frac{1}{r \sin \theta} \frac{\partial \Psi}{\partial r}, 0\right)$$

is parallel to the contours of Ψ . Hence the contours of the Stokes stream $\Psi(r,\theta)$ form the stream tubes.

2 Dynamics of Inviscid Flow

2.1 Surface and Volume Forces

There are two types of force which act on a fluid:

- (i) Those proportional to the volume, like gravity.
- (ii) Those proportional to the surface area, like pressure or *viscous stress*, which is the friction between moving fluid and moving material, whether a boundary or another fluid.

We look at these individually.

(i) For volume or body forces, we denote the force on a small volume element as $\mathbf{f}(\mathbf{x},t) \, \delta V$. Often, \mathbf{f} is conservative with potential energy per unit volume χ , and hence $\mathbf{f} = -\nabla \chi$.

The most common case for us is gravity; here $\mathbf{f} \, \delta V = \rho \mathbf{g} \, \delta V$, with $\chi = \rho g z$, where $\mathbf{g} = (0, 0, q)$.

(ii) For a surface force, we consider a small element of area $\mathbf{n} \delta A$.


Denote the surface force exerted by the outside on the inside by $\tau(\mathbf{x}, t; \mathbf{n}) \delta A$, where τ is the *stress* acting on the area element. Note that the stress τ depends on the orientation \mathbf{n} .

By Newton's third law, the surface force exerted by the inside on the outside is

$$-\boldsymbol{\tau}(\mathbf{x},t;\mathbf{n}) = \boldsymbol{\tau}(\mathbf{x},t;\mathbf{n}).$$

We defer discussion of viscous stresses to chapter 3. In fact, in many phenomena the viscous stresses are negligible and the fluid behaves as if it is *inviscid* (frictionless).

Figure 4: Surface force on a small area δA



For inviscid fluids, the stress τ acting across $\mathbf{n} \delta A$ has no tangential component, and has magnitude independent of the orientation:

$$\tau(\mathbf{x}, t; \mathbf{n}) = -p(\mathbf{x}, t)\mathbf{n},$$

where p is the pressure. Note the sign: the outside pushes on the inside in the direction $-\mathbf{n}$.

2.2 The Euler Momentum Equation

Consider an arbitrary volume V, fixed in space, bounded by surface ∂V with an outward normal \mathbf{n} .

The momentum $\int_V p\mathbf{u} \, dV$ inside V can change due to:

- (i) Flow of momentum across the boundary ∂V ,
- (ii) Volume/body forces,
- (iii) Surface Forces.

Recall the volume out across δA in time δt is $\mathbf{n} \, \delta A \cdot \mathbf{u} \, \delta t$, and the momentum out is $\rho \mathbf{u}(\mathbf{u} \cdot \mathbf{n} \, \delta A \delta t)$. Hence,

$$\frac{\mathrm{d}}{\mathrm{d}t} \int_{V} \rho \mathbf{u} \, \mathrm{d}V = -\int_{\partial V} \rho \mathbf{u} (\mathbf{u} \cdot \mathbf{n}) \, \mathrm{d}A + \int_{\partial V} (-p\mathbf{n}) \, \mathrm{d}A + \int_{V} \mathbf{f} \, \mathrm{d}V.$$

Here $\rho u_i u_j$ is the momentum flux, a second order tensor. We can rewrite this in terms of components as

$$\frac{\mathrm{d}}{\mathrm{d}t} \int_{V} \rho u_{i} \, \mathrm{d}V = -\int_{\partial V} (\rho u_{i} u_{j}) n_{j} \, \mathrm{d}A - \int_{\partial V} p n_{i} \, \mathrm{d}A + \int_{V} f_{i} \, \mathrm{d}V$$

$$\iff \int_{V} \frac{\partial}{\partial t} (\rho u_{i}) \, \mathrm{d}V = -\int_{V} \frac{\partial}{\partial x_{j}} (\rho u_{i} u_{j}) \, \mathrm{d}V - \int_{V} \frac{\partial f}{\partial x_{i}} \, \mathrm{d}V + \int_{V} f_{i} \, \mathrm{d}V.$$

Since V is arbitrary, we obtain

$$\frac{\partial}{\partial t}(\rho u_i) + \frac{\partial}{\partial x_j}(\rho u_i u_h) = -\frac{\partial f}{\partial x_i} + f_i.$$

The left hand side can be expanded as

$$LHS = u_i \left(\frac{\partial \rho}{\partial t} + \frac{\partial}{\partial x_j} (\rho u_j) \right) + \rho \frac{\partial u_i}{\partial t} + \rho u_j \frac{\partial u_i}{\partial x_j}$$
$$= \rho \left(\frac{\partial}{\partial t} + \mathbf{u} \cdot \nabla \right) u_i,$$

due to mass conservation. What we are left with is the material derivative, so we get

$$\rho \frac{D\mathbf{u}}{Dt} = -\nabla p + \mathbf{f}.$$

This is the Euler momentum equation.

The Euler momentum equation also has a dynamic boundary condition, which says that the stress τ exerted on the fluid by the boundary is $-p\mathbf{n}$.

Example 2.1.

Consider a bent hose pipe with steady uniform flow U in and out, with constant cross-sectional area A. We neglect gravity (so $\mathbf{f} = 0$).

From the momentum integral equation, the momentum inside the volume is unchanging, and $\mathbf{f} = 0$, so this simplifies to

$$\int_{\text{walls}} [\rho \mathbf{u}(\mathbf{u} \cdot \mathbf{n}) + p\mathbf{n}] \, dA + \int_{\text{ends}} [\rho \mathbf{u}(\mathbf{u} \cdot \mathbf{n}) + p\mathbf{n}] \, dA = 0.$$

We know that

$$\int_{\text{walls}} [\rho \mathbf{u}(\mathbf{u} \cdot \mathbf{n}) + p\mathbf{n}] \, dA = \int_{\text{walls}} p\mathbf{n} \, dA,$$

as the walls are rigid, so $\mathbf{u} \cdot \mathbf{n} = 0$. This is simply the force by the fluid on the pipe. Moreover, on the ends

$$\int_{\text{ends}} [\rho \mathbf{u}(\mathbf{u} \cdot \mathbf{n}) + p\mathbf{n}] dA = A[p_1 \mathbf{n}_1 + \rho(-U\mathbf{n}_1)(-U) + p_2 \mathbf{n}_2 + \rho(U\mathbf{n}_2)U].$$

In fact we get $p_1 = p_2$. Hence the force on the pipe is

$$-A(p+\rho U^2)(\mathbf{n}_1+\mathbf{n}_2).$$

The ρU^2 contribution comes from the change in momentum flux: the fluid in changes direction.

2.3 Bernoulli's Equation for Steady Flow with Potential Forces

Recall the Euler equation

$$\rho \bigg(\frac{\partial \mathbf{u}}{\partial t} + (\mathbf{u} \cdot \nabla) \mathbf{u} \bigg) = - \nabla p + \mathbf{f}.$$

For steady flows, the change in time will be 0. Moreover, we can rewrite the potential forces as $\mathbf{f} = -\nabla \chi$. Using the vector identity

$$\mathbf{u} \times (\nabla \times \mathbf{u}) = \nabla \left(\frac{1}{2}u^2\right) - (\mathbf{u} \cdot \nabla)\mathbf{u},$$

where $u = |\mathbf{u}|$, we can introduce the *vorticity*

$$\mathbf{w} = \nabla \times \mathbf{u}$$

to reduce the Euler equation to

$$\rho\left(0 + \nabla\left(\frac{1}{2}u^2\right) - \mathbf{u} \times \mathbf{w}\right) = -\nabla p - \nabla \chi$$

$$\iff \nabla\left(\frac{1}{2}\rho u^2 + p + \chi\right) = \rho \mathbf{u} \times \mathbf{w}$$

$$\iff \mathbf{u} \cdot \nabla\left(\frac{1}{2}\rho u^2 + p + \chi\right) = 0.$$


Hence

$$H = \frac{1}{2}\rho u^2 + p + \chi$$

is constant along streamlines. This is Bernoulli's equation.

Since H is constant, p is low where u is high, and vice versa.

Figure 5: Water Container




At the surface of the water, we have a large area, with $u \approx 0$, $\chi = 0$ and $p = p_a$.

At the small exit tube, $\chi = -\rho g h$, $p = p_a$ (as the water is next to the air), and so by Bernoulli, $u = \sqrt{2gh}$.

At a point in the water, $u \approx 0$, $\chi = -\rho gh$ and $p = p_a + \rho gh$.


Figure 6: Pitot Tube



Using Bernoulli along the stagnation line,

$$\frac{1}{2}\rho_{\text{air}}u^2 + p_0 = 0 + p_1 \implies u = \left[\frac{2(p_1 - p_0)}{\rho_{\text{air}}}\right]^{1/2}.$$

Figure 7: Venturi Meter



Assume steady flow, so it is uniform across a cross section. This is alright for gentle variation of A. Due to mass conservation,

$$A_1u_1 = A_2u_2 = Q.$$

Due to Bernoulli,


$$\frac{1}{2}\rho u_1^2 + p_1 = \frac{1}{2}\rho u_2^2 + p_2 \implies p_1 - p_2 = \frac{1}{2}\rho u_1^2 \left(\frac{A_1^2}{A_2^2} - 1\right) > 0.$$

We can measure h to get $\rho gh = p_1 - p_2 = u_1$, so

$$Q = \sqrt{2gh} \frac{A_1 A_2}{\sqrt{A_1^2 - A_1^2}}.$$

We cannot use Bernoulli for a sudden enlargement of a pipe, as there will be complex unsteady flow with energy loss.


Figure 8: Large Change in Pipe



Assuming that $p_{\text{jet}} = p_{\text{still}}$, so there is no sideways acceleration, and $p_{\text{jet}} = p_0$, applying the momentum integral equation to the box, with $\mathbf{f} = 0$, we get

$$\frac{\mathrm{d}}{\mathrm{d}t} \left(\int \rho \mathbf{u} \, \mathrm{d}V \right) \approx 0.$$


Figure 9: Momentum Integral for Large Change



Then we can show that

$$p_1 = p_0 + \rho u_1^2 \left(\frac{A_1}{A_0} - 1\right) \left(\frac{A_1}{A_0}\right).$$

Figure 10: Oblique Wall



Now consider a water jet hitting an oblique wall. We will consider a two-dimensional case, where we neglect gravity. Assume the cross section of the incoming fluid is u, and has speed U, and the area going up is a_2 , and going down is a_1 .

At the contact point of the stream and the wall, there will be pressure $p > p_a$, implying there is a force.

Using Bernoulli on the surface streamline where $p = p_a$ is constant, then the speed is constant along the streamline. Hence far from the impact where flow is uniform and $p = p_a$, we have u = U, so by mass conservation, $aU = a_1U + a_2U$.

The momentum integral equation applied to this gives

$$\frac{\mathrm{d}}{\mathrm{d}t} \int_{V} \rho \mathbf{u} \, \mathrm{d}V = -\int_{\partial V} \rho \mathbf{u} (\mathbf{u} \cdot \mathbf{n}) + p \mathbf{n} \, \mathrm{d}A + \int_{V} \mathbf{f} \, \mathrm{d}V.$$

The time derivative is 0, as the flow is steady, and we neglect gravity. Hence we get

$$\int_{\partial V} \rho \mathbf{u}(\mathbf{u} \cdot \mathbf{n}) + p \mathbf{n} \, \mathrm{d}A.$$

Note that $p = p_a$ apart from near the impact, and $\mathbf{u} \cdot \mathbf{n} = 0$ apart from the ends. Hence, the component parallel to the plane going upwards is

$$-\rho U^2 a \cos \beta + p U^2 a_2 - p U^2 a_1,$$

which we can solve (using conservation of mass) to get

$$a_2 = a \frac{1 + \cos \beta}{2}, \qquad q_1 = a \frac{1 - \cos \beta}{2}.$$

The component perpendicular to the plane is

$$\frac{1}{2}\rho U^2 a \sin \beta = \int_{\partial V} p\mathbf{n} \, dA = \int_{\partial V} (p - p_a)\mathbf{n} \, dA,$$

which is the force on the wall.

2.4 Hydrostatic Pressure and Archimedes Principle

If $\mathbf{u} = 0$, then by Euler,

$$0 = -\nabla p + \rho \mathbf{g} = -\nabla (p + \chi),$$

$$\implies p + \chi = \text{constant} \implies p = p_0 - pgz.$$

This is the *hydrostatic pressure*.

We can also calculate the pressure force on a submerged body with $\mathbf{u} = 0$, in a fluid with density ρ_f :

$$\mathbf{F} = -\int p\mathbf{n} \, dA = -\int (p_0 - \rho gz)\mathbf{n} \, dA = -\int \nabla (p_0 - \rho gz) \, dV = \rho_f g\hat{\mathbf{z}}V.$$

Hence Archimedes principle says the upthrust or buoyancy is the weight of the fluid displaced.

For $\mathbf{u} \neq 0$ and constant ρ everywhere, we can write $p = p_0 - \rho gz + p'$, and get

$$\rho \frac{D\mathbf{u}}{Dt} = -\nabla p'.$$

Here p' is the *dynamic* or *modified* pressure. This is the variation due to the motion after subtracting the hydrostatic balance.

We can ignore gravity if there are no density variations and no free surfaces. If there is a free surface between air and water, then since $\rho_{\text{water}} \neq \rho_{\text{air}}$, gravity has an effect, leading to waves.

2.5 Vorticity

Vorticity is defined by

$$\boldsymbol{\omega} = \nabla \times \mathbf{u}$$
.

This is another way to talk about the angular momentum of the fluid.

- 1. If $\mathbf{u} = \mathbf{\Omega} \times \mathbf{x}$, this is solid-body rotation, and gives $\boldsymbol{\omega} = 2\mathbf{\Omega}$.
- 2. If $\mathbf{u} = (0, \gamma_x, 0)$, this is a simple shear, and gives $\boldsymbol{\omega} = (0, 0, \gamma)$.

3. If $\mathbf{u} = (0, \frac{\kappa}{2\pi r}, 0)$ in cylindrical polars, this is known as a line vortex with $\boldsymbol{\omega} = \mathbf{0}$ except at r = 0. Indeed, doing the line integral around the singularity gives

$$\oint_{r=a} \mathbf{u} \cdot d\mathbf{l} = \int_0^{2\pi} \frac{R}{2\pi r} r \, d\theta = R,$$

but using Stokes' theorem gives


$$\oint_{r=a} \mathbf{u} \cdot d\mathbf{l} = \int_{r < a} \mathbf{w} \cdot \hat{\mathbf{z}} \, dA,$$

hence we get $\boldsymbol{\omega} = (0, 0, \kappa \delta(r)).$

2.5.1 Interpretation of Vorticity

Consider a material line element $\delta \mathbf{l}$, moving with the fluid.

Figure 11: Line Element



Then $\delta \mathbf{l} \to \delta \mathbf{l} + (\delta \mathbf{l} \cdot \nabla) \mathbf{u} \delta t$, or

$$\frac{\mathrm{d}}{\mathrm{d}t}\delta\mathbf{l} = (\delta\mathbf{l}\cdot\nabla)\mathbf{u}.$$

Hence the tensor $\partial u_i/\partial x_j$ determines the rate of change of $\delta \mathbf{l}$. We can write

$$\frac{\partial u_i}{\partial x_j} = \frac{1}{2} \left(\frac{\partial u_i}{\partial x_j} + \frac{\partial u_j}{\partial x_i} \right) + \frac{1}{2} \left(\frac{\partial u_i}{\partial x_j} - \frac{\partial u_j}{\partial x_i} \right) = e_{ij} + \frac{1}{2} \varepsilon_{jik} \omega_k.$$

The local rotation of line elements due to the second term is

$$\frac{1}{2}\varepsilon_{jik}\omega_k\delta l_j = \frac{1}{2}(\boldsymbol{w}\times\delta\mathbf{l}).$$

The local motion due to the first term is called the *strain rate*, which gives zero angular velocity averaged over all orientation $\delta \mathbf{l}$. \mathbf{e} is symmetric and traceless when $\nabla \cdot \mathbf{u} = 0$.

Note that $\frac{1}{2}\omega$ gives the rate of rotation of blobs, not whether the blobs are going in circles.

Index

Archimedes principle, 16

Bernoulli's equation, 12

body force, 9

continuum mechanics, 2

dynamic pressure, 16

Euler momentum equation, 11

fields, 2

hydrostatic pressure, 16

incompressible, 5

inviscid, 9

mass flux, 5

material derivative, 4

pathline, 3

steady-state flows, 3

stream function, 7

streamlines, 3

stress, 9

surface force, 9

volume force, 9

vorticity, 12, 16