
Prometheus安装配置windows Exporter节点

- <u>一</u>、windows exporter的安装下载
- ■ 1. 安装包的下载
 - 2.windows exporter下载完成后,双击即可运行。
 - 3. 在注册表和服务数据库中创建windows exporter服务项
 - 4. 启动注册的windows export服务
- <u>二、Prometheus增加windows exporter配置</u>
- o <u>1. 添加 prometheus.yml 配置: (需要注意文件格式)</u>
 - 2. 检查windows exporter节点
- 三、导入exporter的grafana 监控面板
- o 1.查看grafana版本
 - 2. 搜索所需的面板
 - 3. 下载控制面板
 - 4. grafana导入选中的面板
 - 5. 导入成功后的面板

一、 windows_exporter的安装下载

1. 安装包的下载

windows exporter 官方下载地址: https://github.com/prometheuscommunity/windows exporter/releases



2.windows_exporter下载完成后,双击即可运行。

1. 默认端口是9182,在浏览器输入:localhost:9182即可打开如下页面。为方便后续管理及使用,把windows_exporter注册为服务

windows_exporter

Metrics

(version=0.20.0, branch=heads/tags/v0.20.0, revision=677a7c8d67deb99b92f4f24b8c890e0a4c152b0c)


CSDN @酒米_linyx

3. 在注册表和服务数据库中创建windows_exporter服务项


sc create windows_exporter binpath= "C:\Program Files (x86)\windwos_exporter\windows_exporter-0.20.0-amd64.exe" type= own start= auto displayname= windows_exporter
注: binpath后接的是.exe程序所在的目录及程序名称


4. 启动注册的windows_export服务

1. 打开服务属性



2. 输入启动参数: -telemetry.addr=127.0.0.1:9182





二、Prometheus增加windows_exporter配置

1. 添加 prometheus.yml 配置: (需要注意文件格式)

- targets: ["10.8.109.232:9182","10.8.109.233:9182"]

2. 检查windows_exporter节点

1. 重启prometheus,即可查看已经配置好的exporter Use local time Enable query his TSDB Status

Q Expression (press Shift+Enter for no Command-Line Flags **Execute** Rules

Comparison time

Target Add Panel CSDN @酒米_liny: ← → C ☆ ▲ 不安全 | 10.8.109.219:9090/targets?search= £ ☆ □ **△** UP 7.304s ago 14.315ms 0.996ms Get "http://10.8.109.232:914 http://10.8.109.232:9145/metrics DOWN 11.328s ago http://10.8.109.219:9145/metrics UP 12.407s ago redis (1/1 up) showless Last Scrape

10.875s ago

582.402ms 562.207ms

CSDN @酒米_linyx

三、导入exporter的grafana 监控面板

1.查看grafana版本

windwos_exporter (2/2 up)


因为某些grafana监控面板,对grafana版本有一定要求

[root@rdapp ~]# ps -axu |grep grafana root 7362 0.0 0.0 112824 984 pts/2 S+ 16:04 0:00 grep --color=auto grafana root 20852 0.4 1.0 1939228 83064 ? Ssl 11:19 1:24 /opt/rdapp/grafana/bin/grafana-server [root@rdapp ~]# cat /opt/rdapp/grafana/VERSION 9.2.3

2. 搜索所需的面板


浏览器打开 grafana监控面板地址: https://grafana.com/grafana/dashboards/?

search=windows exporter



3. 下载控制面板


选中所需面板,点击 Copy ID 或者 Download JSON



4. grafana导入选中的面板

1. 方法一:输入复制的面板 ID号,点击Load导入

2. 方法二:上传下载的Json文件,导入面板



5. 导入成功后的面板

