

# Red Hat Openshift Container Storage 3.11

# **Operations Guide**

Configuring and Managing Red Hat Openshift Container Storage.

## Red Hat Openshift Container Storage 3.11 Operations Guide

Configuring and Managing Red Hat Openshift Container Storage.

Customer Content Services Red Hat ccs@redhat.com

#### **Legal Notice**

Copyright © 2019 Red Hat, Inc.

The text of and illustrations in this document are licensed by Red Hat under a Creative Commons Attribution–Share Alike 3.0 Unported license ("CC-BY-SA"). An explanation of CC-BY-SA is available at

http://creativecommons.org/licenses/by-sa/3.0/

. In accordance with CC-BY-SA, if you distribute this document or an adaptation of it, you must provide the URL for the original version.

Red Hat, as the licensor of this document, waives the right to enforce, and agrees not to assert, Section 4d of CC-BY-SA to the fullest extent permitted by applicable law.

Red Hat, Red Hat Enterprise Linux, the Shadowman logo, the Red Hat logo, JBoss, OpenShift, Fedora, the Infinity logo, and RHCE are trademarks of Red Hat, Inc., registered in the United States and other countries.

Linux ® is the registered trademark of Linus Torvalds in the United States and other countries.

Java <sup>®</sup> is a registered trademark of Oracle and/or its affiliates.

XFS <sup>®</sup> is a trademark of Silicon Graphics International Corp. or its subsidiaries in the United States and/or other countries.

MySQL <sup>®</sup> is a registered trademark of MySQL AB in the United States, the European Union and other countries.

Node.js ® is an official trademark of Joyent. Red Hat is not formally related to or endorsed by the official Joyent Node.js open source or commercial project.

The OpenStack <sup>®</sup> Word Mark and OpenStack logo are either registered trademarks/service marks or trademarks/service marks of the OpenStack Foundation, in the United States and other countries and are used with the OpenStack Foundation's permission. We are not affiliated with, endorsed or sponsored by the OpenStack Foundation, or the OpenStack community.

All other trademarks are the property of their respective owners.

#### **Abstract**

This guide provides information about operating your Container Storage deployment.

## **Table of Contents**

PART I. MANAGE	4
CHAPTER 1. MANAGING CLUSTERS	5
1.1. INCREASING STORAGE CAPACITY	6
1.1.1. Adding New Devices	6
1.1.2. Adding New Nodes	6
1.1.3. Adding a New Cluster	9
1.1.3.1. Adding a New Cluster to an Existing Red Hat Openshift Container Storage Installation	9
1.1.3.2. Adding Another Red Hat Openshift Container Storage Cluster in a New Project	11
1.2. REDUCING STORAGE CAPACITY	15
1.2.1. Deleting Volumes	15
1.2.2. Deleting Device	15
1.2.2.1. Disabling and Enabling a Device	15
1.2.2.2. Removing and Deleting the Device	16
1.2.2.3. Replacing a Device	16
1.2.3. Deleting Node	18
1.2.3.1. Disabling and Enabling a Node	18
1.2.3.2. Removing and Deleting the Node	18
1.2.3.3. Replacing a Node	19
1.2.4. Deleting Clusters	21
CHAPTER 2. OPERATIONS ON A RED HAT GLUSTER STORAGE POD IN AN OPENSHIFT ENVIRONMENT	22
2.1. MAINTENANCE ON NODES	26
2.1.1. Necessary steps to be followed before maintenance	26
2.1.2. Necessary steps to be followed after maintenance	27
PART II. OPERATIONS	30
CHARTER 2 CREATING REDCICTENT VOLUMES	21
CHAPTER 3. CREATING PERSISTENT VOLUMES	<b>31</b> 31
3.1.1. Static Provisioning of Volumes	31
3.1.2. Dynamic Provisioning of Volumes	38
3.1.2.1. Configuring Dynamic Provisioning of Volumes	38
3.1.2.1.1. Creating Secret for Heketi Authentication	38
3.1.2.1.2. Registering a Storage Class	39
3.1.2.1.3. Creating a Persistent Volume Claim	41
3.1.2.1.4. Verifying Claim Creation	42
3.1.2.1.5. (Optional) Providing a Custom Volume Name Prefix for Persistent Volumes	43
3.1.2.1.6. Using the Claim in a Pod	44
3.1.2.1.7. Expanding Persistent Volume Claim	45
3.1.2.1.8. Deleting a Persistent Volume Claim	48
3.1.3. Volume Security	49
3.2. BLOCK STORAGE	51
3.2.1. Dynamic Provisioning of Volumes for Block Storage	51
3.2.1.1. Configuring Dynamic Provisioning of Volumes	52
3.2.1.1.1. Configuring Multipathing on all Initiators	52
3.2.1.1.2. Creating Secret for Heketi Authentication	53
3.2.1.1.3. Registering a Storage Class	53
3.2.1.1.4. Creating a Persistent Volume Claim	55
3.2.1.1.5. Verifying Claim Creation	57
3.2.1.1.6. (Optional) Providing a Custom Volume Name Prefix for Persistent Volumes	57
3.2.1.1.7. Using the Claim in a Pod	58

3.2.1.1.8. Deleting a Persistent Volume Claim 3.2.2. Replacing a Block on Block Storage	60 60
CHAPTER 4. SHUTTING DOWN GLUSTER-BLOCK CLIENT NODES	66
CHAPTER 5. S3 COMPATIBLE OBJECT STORE IN A RED HAT OPENSHIFT CONTAINER STORAGE ENVIRONMENT  5.1. SETTING UP S3 COMPATIBLE OBJECT STORE FOR RED HAT OPENSHIFT CONTAINER STORAGE 5.2. OBJECT OPERATIONS	<b>67</b> 67 70
CHAPTER 6. CLUSTER ADMINISTRATOR SETUP	. 71
CHAPTER 7. GLUSTER BLOCK STORAGE AS BACKEND FOR LOGGING AND METRICS 7.1. PREREQUISITES 7.2. ENABLING GLUSTER BLOCK STORAGE AS BACKEND FOR LOGGING 7.3. ENABLING GLUSTER BLOCK STORAGE AS BACKEND FOR METRICS 7.4. VERIFYING IF GLUSTER BLOCK IS SETUP AS BACKEND	<b>72</b> 72 72 73 74
PART III. SECURITY	75
CHAPTER 8. ENABLING ENCRYPTION  8.1. PREREQUISITES  8.2. ENABLING ENCRYPTION FOR A NEW RED HAT OPENSHIFT CONTAINER STORAGE SETUP  8.2.1. Enabling Management Encryption  8.2.2. Enabling I/O encryption for a Volume  8.3. ENABLING ENCRYPTION FOR AN EXISTING RED HAT OPENSHIFT CONTAINER STORAGE SETUP  8.3.1. Enabling I/O encryption for a Volume  8.3.2. Enabling Management Encryption  8.4. DISABLING ENCRYPTION  8.4.1. Disabling I/O Encryption for all the Volumes  8.4.2. Disabling Management Encryption	766 766 766 777 799 80 81 81 82
CHAPTER 9. UPDATING THE REGISTRY WITH RED HAT OPENSHIFT CONTAINER STORAGE AS THE STORAGE BACK-END  9.1. VALIDATING THE OPENSHIFT CONTAINER PLATFORM REGISTRY DEPLOYMENT  9.2. CONVERTING THE OPENSHIFT CONTAINER PLATFORM REGISTRY WITH RED HAT OPENSHIFT CONTAINER STORAGE	<b>85</b> 85
PART V. MONITORING	92
CHAPTER 10. ENABLING VOLUME METRICS IN OPENSHIFT 3.10 AND 3.11  10.1. AVAILABLE METRICS FOR FILE STORAGE AND BLOCK STORAGE  10.2. ENABLING HEKETI METRICS IN OPENSHIFT 3.10  10.3. ENABLING HEKETI METRICS IN OPENSHIFT 3.11  10.4. VIEWING METRICS	93 93 94 95 96
PART VI. TROUBLESHOOT	98
CHAPTER 11. TROUBLESHOOTING	99
CHAPTER 12. CLIENT CONFIGURATION USING PORT FORWARDING	101

## **PART I. MANAGE**

#### **CHAPTER 1. MANAGING CLUSTERS**

Heketi allows administrators to add and remove storage capacity by managing either a single or multiple Red Hat Gluster Storage clusters.

Heketi provides a RESTful management interface which can be used to manage the lifecycle of Red Hat Gluster Storage volumes. With Heketi, cloud services like OpenStack Manila, Kubernetes, and OpenShift can dynamically provision Red Hat Gluster Storage volumes with any of the supported durability types. Heketi will automatically determine the location for bricks across the cluster, making sure to place bricks and its replicas across different failure domains. Heketi also supports any number of Red Hat Gluster Storage clusters, allowing cloud services to provide network file storage without being limited to a single Red Hat Gluster Storage cluster.


With Heketi, the administrator no longer manages or configures bricks, disks, or trusted storage pools. Heketi service will manage all hardware for the administrator, enabling it to allocate storage on demand. Any disks registered with Heketi must be provided in raw format, which will then be managed by it using LVM on the disks provided.



#### NOTE

The replica 3 and the arbiter volumes are supported volume types that can be created using Heketi.

#### Heketi volume creation



GLUSTER\_386133\_0116

A create volume request to Heketi leads it to select bricks spread across 2 zones and 4 nodes. After the volume is created in Red hat Gluster Storage, Heketi provides the volume information to the service that initially made the request.

#### 1.1. INCREASING STORAGE CAPACITY

You can increase the storage capacity using any of the following ways:

- Adding devices
- Adding new nodes
- Adding an entirely new cluster.

#### 1.1.1. Adding New Devices

You can add more devices to existing nodes to increase storage capacity. When adding more devices, you must ensure to add devices as a set. For example, when expanding a distributed replicated volume with a replica count of replica 2, then one device should be added to at least two nodes. If using replica 3, then at least one device should be added to at least three nodes.

You can add a device by using CLI as follows:

Register the specified device. The following example command shows how to add a device \(^\)/dev/sde \(^\) to node \( d6f2c22f2757bf67b1486d868dcb7794: \)

# heketi-cli device add --name=/dev/sde --node=d6f2c22f2757bf67b1486d868dcb7794 OUTPUT:

Device added successfully

#### 1.1.2. Adding New Nodes

Another way to add storage to Heketi, is to add new nodes to the cluster. Like adding devices, you can add a new node to an existing cluster by using CLI. After you add a new node to the cluster, you must register new devices to that node.



#### **NOTE**

For adding a node to be successful, ensure the ports are opened for glusterd communication. For more information about the ports, see https://access.redhat.com/documentation/en-us/red\_hat\_gluster\_storage/3.5/html/installation\_guide/port\_information

1. Scaleup the OCP cluster to add the new node. For more information see, https://access.redhat.com/documentation/en-us/openshift\_container\_platform/3.11/html-single/configuring\_clusters/#adding-cluster-hosts\_adding-hosts-to-cluster



#### **NOTE**

- If the new node is already part of OCP cluster then skip this step and proceed with Step 2.
- The OCP cluster can be scaled up to add new nodes as either compute nodes or infra nodes. For example, for infra it is node3.example.com openshift\_node\_group\_name='node-config-infra' and for compute node it is node3.example.com openshift\_node\_group\_name='node-config-compute'.
- 2. Configure the firewall rules:



#### **NOTE**

For adding a node to be successful, ensure the ports are opened for glusterd communication. For more information about the ports, see https://access.redhat.com/documentation/en-us/red\_hat\_gluster\_storage/3.5/html/installation\_guide/port\_information

a. Add the following rules to the /etc/sysconfig/iptables file of the newly added glusterfs node:

-A OS\_FIREWALL\_ALLOW -p tcp -m state --state NEW -m tcp --dport 24007 -j ACCEPT

-A OS\_FIREWALL\_ALLOW -p tcp -m state --state NEW -m tcp --dport 24008 -j ACCEPT

-A OS FIREWALL ALLOW -p tcp -m state --state NEW -m tcp --dport 2222 -j ACCEPT

-A OS\_FIREWALL\_ALLOW -p tcp -m state --state NEW -m multiport --dports 49152:49664 -j ACCEPT

-A OS\_FIREWALL\_ALLOW -p tcp -m state --state NEW -m tcp --dport 24010 -j ACCEPT

-A OS FIREWALL ALLOW -p tcp -m state --state NEW -m tcp --dport 3260 -j ACCEPT

-A OS\_FIREWALL\_ALLOW -p tcp -m state --state NEW -m tcp --dport 111 -j ACCEPT

b. Reload/restart the iptables:

# systemctl restart iptables

- 3. Execute the following steps to add labels to the node where the RHGS Container will be deployed:
  - a. Verify that Red Hat Openshift Container Storage is deployed and working as expected in the existing project by executing the following command:

# oc get ds

For example:

# oc get ds
NAME DESIRED CURRENT READY UP-TO-DATE AVAILABLE NODE
SELECTOR AGE
glusterfs-storage 3 3 3 3 3 glusterfs=storage-host 1d

b. Add the label for each node which is newly added, where the Red Hat Gluster Storage pods are to be added for the new cluster:

# oc label node <NODE\_NAME> glusterfs=<node\_label>

where,

- NODE\_NAME: is the name of the newly created node.
- node\_label: The name that is used in the existing daemonset. This is the value you get in the previous step when you execute **oc get ds**.

For example:

```
# oc label node 192.168.90.3 glusterfs=storage-host node "192.168.90.3" labeled
```

c. Verify if the Red Hat Gluster Storage pods are running on the newly added node by executing the following command:

Observe additional Gluster Storage pods spawned on these new nodes

# oc get pods

For example:

```
# oc get pods
NAME READY STATUS RESTARTS AGE
glusterfs-356cf 1/1 Running 0 30d
glusterfs-fh4gm 1/1 Running 0 30d
glusterfs-hg4tk 1/1 Running 0 30d
glusterfs-v759z 0/1 Running 0 1m
```

You should see additional Gluster Storage pods, in this example 4 gluster pods instead of just 3 as before. It will take 1-2 minutes for them to become healthy. (i.e. glusterfs-v759z 0/1 not healthy yet).

d. Verify if the Red Hat Gluster Storage pods are running

# oc get pods -o wide -l glusterfs=storage-pod

4. Add a new node to the cluster by using Heketi CLI. Following shows an example of how to add new node in **zone 1** to `597fceb5d6c876b899e48f599b988f54 ` cluster using the CLI:

# heketi-cli node add --zone=1 --cluster=597fceb5d6c876b899e48f599b988f54 -- management-host-name=node4.example.com --storage-host-name=192.168.10.104

#### **OUTPUT:**

Node information:

ld: 095d5f26b56dc6c64564a9bc17338cbf

State: online

Cluster Id: 597fceb5d6c876b899e48f599b988f54

Zone: 1

Management Hostname node4.example.com

Storage Hostname 192.168.10.104

5. Add devices to the cluster by using Heketi CLI. For more information on adding devices, refer Section 1.1.1, "Adding New Devices".



#### NOTE

When a node is added to a gluster trusted storage pool using heketi, existing endpoints are not updated automatically.

To update the endpoints execute the following commands:

# heketi-cli volume endpoint patch <volume-id>

# oc patch ep <heketi-db-endpoint-name> -p <changes>

#### 1.1.3. Adding a New Cluster

Storage capacity can also be increased by adding new clusters of Red Hat Gluster Storage. New clusters can be added in the following two ways based on the requirement:

- Adding a new cluster to an existing Red Hat Openshift Container Storage installation
- Adding another Red Hat Openshift Container Storage cluster in a new project

In all cases, the nodes of the new clusters must be prepared as either OCP nodes (converged mode) or RHGS nodes (independent mode).

# 1.1.3.1. Adding a New Cluster to an Existing Red Hat Openshift Container Storage Installation

To add a new cluster to an existing Red Hat Openshift Container Storage installation, execute the following commands:

1. Verify that Red Hat Openshift Container Storage is deployed and working as expected in the existing project by executing the following command.:

# oc get ds

For example:

# oc get ds

NAME DESIRED CURRENT READY UP-TO-DATE AVAILABLE NODE

SELECTOR AGE
glusterfs-storage 3 3 3 3 3 glusterfs=storage-host 1d



#### NOTE

Add new hosts by performing step 1 through step 3 in Section 1.1.2, "Adding New Nodes" section. Repeat the steps for all the nodes you want to add.

2. Verify if the Red Hat Gluster Storage pods are running by executing the following command:

# oc get pods

3. Add the label for each node which is newly added, where the Red Hat Gluster Storage pods are to be added for the new cluster to start by executing the following command:

# oc label node <NODE\_NAME> glusterfs=<node\_label>

where,

- NODE\_NAME: is the name of the newly created node
- node\_label: The name that is used in the existing daemonset.

For example:

```
# oc label node 192.168.90.3 glusterfs=storage-host node "192.168.90.3" labeled
```

Observe additional Gluster Storage pods spawned on these new nodes

# oc get pods

For example:

```
# oc get pods
                      STATUS RESTARTS AGE
NAME
             READY
glusterfs-356cf 1/1
                    Running 0
                                    30d
                                    30d
glusterfs-fh4gm 1/1
                     Running 0
glusterfs-hg4tk 1/1
                    Running 0
                                    30d
glusterfs-v759z 0/1
                     Running 0
                                    1m
glusterfs-rgs3k 0/1
                    Running 0
                                    1m
glusterfs-gtq9f 0/1
                    Running 0
                                    1m
```

You should see additional Gluster Storage pods, in this example 6 gluster pods instead of just 3 as before. It will take 1-2 minutes for them to become healthy. (i.e. glusterfs-v759z, glusterfs-rgs3k, and glusterfs-gtq9f 0/1 not healthy yet).

4. Verify if the Red Hat Gluster Storage pods are running by executing the following command:

# oc get ds

For example:

```
# oc get ds
NAME DESIRED CURRENT READY UP-TO-DATE AVAILABLE NODE
SELECTOR AGE
glusterfs-storage 3 3 3 3 glusterfs=storage-host 1d
```

5. Create a new cluster in Heketi by using the following command:

# heketi-cli cluster create

6. Add nodes and devices to the newly created cluster as described in sections ] and xref:sect\_Adding\_New\_Nodes[.

#### 1.1.3.2. Adding Another Red Hat Openshift Container Storage Cluster in a New Project

To add another Red Hat Openshift Container Storage in a new project to, execute the following commands:



#### **NOTE**

As Node label is global, there can be conflicts to start Red Hat Gluster Storage DaemonSets with the same label in two different projects. Node label is anargument to cns-deploy, thereby enabling deployment of multiple trusted storage pool by using a different label in a different project.

For more information on how to add a new cluster to the existing Red Hat Openshift Container Storage in independent mode, see

https://access.redhat.com/documentation/en-us/red\_hat\_openshift\_container\_storage/3.11/html/deployment\_guide/cns\_deploy\_optional

1. Create a new project by executing the following command:

# oc new-project <new\_project\_name>

For example:

# oc new-project storage-project-2

Now using project "storage-project-2" on server "https://master.example.com:8443"

2. After the project is created, execute the following command on the master node to enable the deployment of the privileged containers as Red Hat Gluster Storage container can only run in the privileged mode.

```
# oc adm policy add-scc-to-user privileged -z storage-project-2
# oc adm policy add-scc-to-user privileged -z default
```

3. Create a new topology file for the new cluster. You must provide a topology file for the new cluster which describes the topology of the Red Hat Gluster Storage nodes and their attached storage devices. As a sample, a formatted topology file (topology-sample.json) is installed with the 'heketi-client' package in the /usr/share/heketi/ directory.

For example:

"zone": 1

```
"devices": [
     "/dev/sdb",
     "/dev/sdc",
     "/dev/sdd",
     "/dev/sde".
     "/dev/sdf".
     "/dev/sdg",
     "/dev/sdh",
     "/dev/sdi"
},
  "node": {
     "hostnames": {
        "manage": [
           "node2.example.com"
        "storage": [
           "192.168.68.2"
     "zone": 2
  "devices": [
     "/dev/sdb",
     "/dev/sdc".
     "/dev/sdd",
     "/dev/sde",
     "/dev/sdf",
     "/dev/sdg",
     "/dev/sdh",
     "/dev/sdi"
},
```

where,

- clusters: Array of clusters. Each element on the array is a map which describes the cluster as follows.
- nodes: Array of OpenShift nodes that will host the Red Hat Gluster Storage container. Each element on the array is a map which describes the node as follows
  - node: It is a map of the following elements:
    - zone: The value represents the zone number that the node belongs to; the zone number is used by heketi for choosing optimum position of bricks by having replicas of bricks in different zones. Hence zone number is similar to a failure domain.
    - hostnames: It is a map which lists the manage and storage addresses

- manage: It is the hostname/IP Address that is used by Heketi to communicate with the node
- storage: It is the IP address that is used by other OpenShift nodes to communicate with the node. Storage data traffic will use the interface attached to this IP. This must be the IP address and not the hostname because, in an OpenShift environment, Heketi considers this to be the endpoint too.
- devices: Name of each disk to be added

Edit the topology file based on the Red Hat Gluster Storage pod hostname under the **node.hostnames.manage** section and **node.hostnames.storage** section with the IP address. For simplicity, the /usr/share/heketi/topology-sample.json file only sets up 4 nodes with 8 drives each.

4. Execute the following command on the client to deploy the heketi and Red Hat Gluster Storage pods:

# cns-deploy -n <namespace> --daemonset-label <NODE\_LABEL> -g topology.json

For example:

# cns-deploy -n storage-project-2 --daemonset-label glusterfs2 -g topology.json Welcome to the deployment tool for GlusterFS on Kubernetes and OpenShift.

Before getting started, this script has some requirements of the execution environment and of the container platform that you should verify.

The client machine that will run this script must have:

- \* Administrative access to an existing Kubernetes or OpenShift cluster
- \* Access to a python interpreter 'python'
- \* Access to the heketi client 'heketi-cli'

Each of the nodes that will host GlusterFS must also have appropriate firewall rules for the required GlusterFS ports:

- \* 2222 sshd (if running GlusterFS in a pod)
- \* 24007 GlusterFS Daemon
- \* 24008 GlusterFS Management
- \* 49152 to 49251 Each brick for every volume on the host requires its own port. For every new brick, one new port will be used starting at 49152. We recommend a default range of 49152-49251 on each host, though you can adjust this to fit your needs.

In addition, for an OpenShift deployment you must:

- \* Have 'cluster admin' role on the administrative account doing the deployment
- \* Add the 'default' and 'router' Service Accounts to the 'privileged' SCC
- \* Have a router deployed that is configured to allow apps to access services running in the cluster

Do you wish to proceed with deployment?

[Y]es, [N]o? [Default: Y]: Y Using OpenShift CLI.

NAME STATUS AGE storage-project-2 Active 2m Using namespace "storage-project-2".

Checking that heketi pod is not running ... OK template "deploy-heketi" created serviceaccount "heketi-service-account" created template "heketi" created template "glusterfs" created role "edit" added: "system:serviceaccount:storage-project-2:heketi-service-account" node "192.168.35.5" labeled node "192.168.35.6" labeled node "192.168.35.7" labeled daemonset "glusterfs" created Waiting for GlusterFS pods to start ... OK service "deploy-heketi" created route "deploy-heketi" created deploymentconfig "deploy-heketi" created Waiting for deploy-heketi pod to start ... OK Creating cluster ... ID: fde139c21b0afcb6206bf272e0df1590 Creating node 192.168.35.5 ... ID: 0768a1ee35dce4cf707c7a1e9caa3d2a Adding device /dev/vdc ... OK Adding device /dev/vdd ... OK Adding device /dev/vde ... OK Adding device /dev/vdf ... OK Creating node 192.168.35.6 ... ID: 63966f6ffd48c1980c4a2d03abeedd04 Adding device /dev/vdc ... OK Adding device /dev/vdd ... OK Adding device /dev/vde ... OK Adding device /dev/vdf ... OK Creating node 192.168.35.7 ... ID: de129c099193aaff2c64dca825f33558 Adding device /dev/vdc ... OK Adding device /dev/vdd ... OK Adding device /dev/vde ... OK Adding device /dev/vdf ... OK heketi topology loaded. Saving heketi-storage.ison secret "heketi-storage-secret" created endpoints "heketi-storage-endpoints" created service "heketi-storage-endpoints" created job "heketi-storage-copy-job" created deploymentconfig "deploy-heketi" deleted route "deploy-heketi" deleted service "deploy-heketi" deleted job "heketi-storage-copy-job" deleted pod "deploy-heketi-1-d0grs" deleted secret "heketi-storage-secret" deleted service "heketi" created route "heketi" created deploymentconfig "heketi" created Waiting for heketi pod to start ... OK heketi is now running. Ready to create and provide GlusterFS volumes.



#### **NOTE**

For more information on the cns-deploy commands, see to the man page of the cns-deploy.

# cns-deploy --help

5. Verify that Red Hat Openshift Container Storage is deployed and working as expected in the new project with the new daemonSet label by executing the following command:

# oc get ds

For example:

# oc get ds

NAME DESIRED CURRENT READY NODE-SELECTOR AGE
glusterfs 3 3 3 storagenode=glusterfs2 8m

#### 1.2. REDUCING STORAGE CAPACITY

Heketi also supports the reduction of storage capacity. You can reduce storage by deleting devices, nodes, and clusters. These requests can only be performed by using the Heketi CLI or the API. For information on using command line API, see Heketi API https://github.com/heketi/heketi/wiki/API.



#### NOTE

- The IDs can be retrieved by executing the heketi-cli topology info command.
  - # heketi-cli topology info
- The **heketidbstorage** volume cannot be deleted as it contains the heketi database.

#### 1.2.1. Deleting Volumes

You can delete the volume using the following Heketi CLI command:

# heketi-cli volume delete <volume\_id>

For example:

# heketi-cli volume delete 12b2590191f571be9e896c7a483953c3 Volume 12b2590191f571be9e896c7a483953c3 deleted

#### 1.2.2. Deleting Device

Deleting the device deletes devices from heketi's topology. Devices that have bricks cannot be deleted. You must ensure they are free of bricks by disabling and removing devices.

#### 1.2.2.1. Disabling and Enabling a Device

Disabling devices stops further allocation of bricks onto the device. You can disable devices using the following Heketi CLI command:

# heketi-cli device disable <device\_id>

For example:

# heketi-cli device disable f53b13b9de1b5125691ee77db8bb47f4 Device f53b13b9de1b5125691ee77db8bb47f4 is now offline

If you want to re-enable the device, execute the following command. Enabling the device allows allocation of bricks onto the device.

# heketi-cli device enable <device\_id>

For example:

# heketi-cli device enable f53b13b9de1b5125691ee77db8bb47f4 Device f53b13b9de1b5125691ee77db8bb47f4 is now online

#### 1.2.2.2. Removing and Deleting the Device

Removing devices moves existing bricks from the device to other devices. This helps in ensuring the device is free of bricks. A device can be removed only after disabling it.

1. Remove device using the following command:

# heketi-cli device remove <device\_id>

For example:

# heketi-cli device remove e9ef1d9043ed3898227143add599e1f9 Device e9ef1d9043ed3898227143add599e1f9 is now removed

2. Delete the device using the following command:

# heketi-cli device delete <device\_id>

For example:

# heketi-cli device delete 56912a57287d07fad0651ba0003cf9aa Device 56912a57287d07fad0651ba0003cf9aa deleted

The only way to reuse a deleted device is by adding the device to heketi's topology again.

#### 1.2.2.3. Replacing a Device

Heketi does not allow one-to-one replacement of a device with another. However, in case of a failed device, follow the example below for the sequence of operations that are required to replace a failed device.

1. Locate the device that has failed using the following command:

-

#### # heketi-cli topology info

```
...
Nodes:
Node ld: 8faade64a9c8669de204b66bc083b10d
...

Id:a811261864ee190941b17c72809a5001 Name:/dev/vdc State:online
Size (GiB):499 Used (GiB):281 Free (GiB):218
Bricks:
Id:34c14120bef5621f287951bcdfa774fc Size (GiB):280 Path:
/var/lib/heketi/mounts/vg_a811261864ee190941b17c72809a5001/brick_34c14120bef5621f287951bcdfa774fc/brick
...
...
```

The example below illustrates the sequence of operations that are required to replace a failed device. The example uses device ID **a811261864ee190941b17c72809a5001** which belongs to node with id **8faade64a9c8669de204b66bc083b10das**.

2. Add a new device preferably to the same node as the device being replaced.

# heketi-cli device add --name /dev/vdd --node 8faade64a9c8669de204b66bc083b10d Device added successfully

3. Disable the failed device.

# heketi-cli device disable a811261864ee190941b17c72809a5001 Device a811261864ee190941b17c72809a5001 is now offline

4. Remove the failed device.

# heketi-cli device remove a811261864ee190941b17c72809a5001 Device a811261864ee190941b17c72809a5001 is now removed

At this stage, the bricks are migrated from the failed device. Heketi chooses a suitable device based on the brick allocation algorithm. As a result, there is a possibility that all the bricks might not be migrated to the new added device.

5. Delete the failed device.

# heketi-cli device delete a811261864ee190941b17c72809a5001 Device a811261864ee190941b17c72809a5001 deleted

6. Before repeating the above sequence of steps on another device, you must wait for the self-heal operation to complete. You can verify that the self-heal operation completed when the Number of entries value returns a 0 value.

# oc rsh <any\_gluster\_pod\_name> for each in \$(gluster volume list); do gluster vol heal \$each info | grep "Number of entries:";

done

Number of entries: 0 Number of entries: 0 Number of entries: 0

#### 1.2.3. Deleting Node

Nodes that have devices added to it cannot be deleted. To delete the node, the devices that are associated with the node have to be deleted. Disabling and removing the node ensures all the underlying devices are removed too. Once the node is removed, all the devices in it can be deleted and finally the node can be deleted.

#### 1.2.3.1. Disabling and Enabling a Node

Disabling node stops further allocation of bricks to all the devices associated to the node. You can disable nodes using the following Heketi CLI command:

# heketi-cli node disable <node\_id>

For example:

# heketi-cli node disable 5f0af88b968ed1f01bf959fe4fe804dc Node 5f0af88b968ed1f01bf959fe4fe804dc is now offline

If you want to re-enable the node, execute the following command.

# heketi-cli node enable <node\_id>

For example:

# heketi-cli node enable 5f0af88b968ed1f01bf959fe4fe804dc Node 5f0af88b968ed1f01bf959fe4fe804dc is now online

#### 1.2.3.2. Removing and Deleting the Node

Removing nodes moves existing bricks from all the devices in the node to other devices in the cluster. This helps in ensuring all the device in the node is free of bricks. A device can be removed only after disabling it.

1. To remove the node execute the following command:

# heketi-cli node remove <node\_id>

For example:

# heketi-cli node remove 5f0af88b968ed1f01bf959fe4fe804dc Node 5f0af88b968ed1f01bf959fe4fe804dc is now removed

2. Delete the devices associated with the node by executing the following command as the nodes that have devices associated with it cannot be deleted:

# heketi-cli device delete <device id>

For example:

# heketi-cli device delete 56912a57287d07fad0651ba0003cf9aa Device 56912a57287d07fad0651ba0003cf9aa deleted

Execute the command for every device on the node.

3. Delete the node using the following command:

# heketi-cli node delete <node\_id>

For example:

# heketi-cli node delete 5f0af88b968ed1f01bf959fe4fe804dc Node 5f0af88b968ed1f01bf959fe4fe804dc deleted

Deleting the node deletes the node from the heketi topology. The only way to reuse a deleted node is by adding the node to heketi's topology again



#### **NOTE**

When a node is deleted from a gluster trusted storage pool using heketi, existing endpoints are not updated automatically.

To update the endpoints execute the following commands:

# heketi-cli volume endpoint patch <volume-id>

# oc patch ep <heketi-db-endpoint-name> -p <changes>

#### 1.2.3.3. Replacing a Node

951bcdfa774fc/brick

Heketi does not allow one-to-one replacement of a node with another. However, in case of a failed node, follow the example below for the sequence of operations that are required to replace a failed node and its respective devices.

1. Locate the node that has failed using the following command:

```
# heketi-cli topology info
...
...
...
...
Nodes:
Node ld: 8faade64a9c8669de204b66bc083b10d
...
...
...
ld:a811261864ee190941b17c72809a5001 Name:/dev/vdc State:online Size
(GiB):499 Used (GiB):281 Free (GiB):218
Bricks:
ld:34c14120bef5621f287951bcdfa774fc Size (GiB):280 Path:
/var/lib/heketi/mounts/vg_a811261864ee190941b17c72809a5001/brick_34c14120bef5621f287
```

...

The example below illustrates the sequence of operations that are required to replace a failed node. The example uses node ID 8faade64a9c8669de204b66bc083b10d.

Scale up the OCP cluster to add the replacement node. For more detail how to add a node, refer to the steps in section Section 1.1.2, "Adding New Nodes".



#### NOTE

If the replacement node is already part of OCP cluster then skip this step and proceed with step 2.

2. Add a new node, preferably that has the same devices as the node being replaced.

# heketi-cli node add --zone=1 --cluster=597fceb5d6c876b899e48f599b988f54 -- management-host-name=node4.example.com --storage-host-name=192.168.10.104

# heketi-cli device add --name /dev/vdd --node 8faade64a9c8669de204b66bc083b10d

Node and device added successfully

3. Disable the failed node.

# heketi-cli node disable 8faade64a9c8669de204b66bc083b10d Node 8faade64a9c8669de204b66bc083b10d is now offline

4. Remove the failed node.

# heketi-cli node remove 8faade64a9c8669de204b66bc083b10d Node 8faade64a9c8669de204b66bc083b10d is now removed

At this stage, the bricks are migrated from the failed node. Heketi chooses a suitable device based on the brick allocation algorithm.

5. Delete the devices associated with the node by executing the following command as the nodes that have devices associated with it cannot be deleted:

# heketi-cli device delete <device\_id>

For example:

# heketi-cli device delete 56912a57287d07fad0651ba0003cf9aa Device 56912a57287d07fad0651ba0003cf9aa deleted

Execute the command for every device on the node.

6. Delete the failed node.

# heketi-cli node delete 8faade64a9c8669de204b66bc083b10d Node 8faade64a9c8669de204b66bc083b10d deleted

#### 1.2.4. Deleting Clusters

You can delete the cluster using the following Heketi CLI command:



#### NOTE

Before a cluster is deleted, ensure that all the nodes inside the cluster are deleted.

# heketi-cli cluster delete <cluster\_id>

For example:

# heketi-cli cluster delete 0e949d91c608d13fd3fc4e96f798a5b1 Cluster 0e949d91c608d13fd3fc4e96f798a5b1 deleted

# CHAPTER 2. OPERATIONS ON A RED HAT GLUSTER STORAGE POD IN AN OPENSHIFT ENVIRONMENT

This chapter lists out the various operations that can be performed on a Red Hat Gluster Storage pod (gluster pod):

• To list the pods, execute the following command:

```
# oc get pods -n <storage_project_name>
```

For example:

# oc get pods -n storage-project	
NAME	READY STATUS RESTARTS AGE
storage-project-router-1-v89qc	1/1 Running 0 1d
glusterfs-dc-node1.example.com	1/1 Running 0 1d
glusterfs-dc-node2.example.com	1/1 Running 1 1d
glusterfs-dc-node3.example.com	1/1 Running 0 1d
heketi-1-k1u14	1/1 Running 0 23m

Following are the gluster pods from the above example:

glusterfs-dc-node1.example.com glusterfs-dc-node2.example.com glusterfs-dc-node3.example.com



#### **NOTE**

The topology.json file will provide the details of the nodes in a given Trusted Storage Pool (TSP). In the above example all the 3 Red Hat Gluster Storage nodes are from the same TSP.

• To enter the gluster pod shell, execute the following command:

# oc rsh <gluster\_pod\_name> -n <storage\_project\_name>

For example:

# oc rsh glusterfs-dc-node1.example.com -n storage-project sh-4.2#

• To get the peer status, execute the following command:

# gluster peer status

For example:

# gluster peer status

Number of Peers: 2

Hostname: node2.example.com

Uuid: 9f3f84d2-ef8e-4d6e-aa2c-5e0370a99620

State: Peer in Cluster (Connected)

Other names: node1.example.com

Hostname: node3.example.com

Uuid: 38621acd-eb76-4bd8-8162-9c2374affbbd

State: Peer in Cluster (Connected)

• To list the gluster volumes on the Trusted Storage Pool, execute the following command:

# gluster volume info

#### For example:

Volume Name: heketidbstorage Type: Distributed-Replicate

Volume ID: 2fa53b28-121d-4842-9d2f-dce1b0458fda

Status: Started

Number of Bricks:  $2 \times 3 = 6$ 

Transport-type: tcp

Bricks: Brick1:

 $192.168.121.172: /var/lib/heketi/mounts/vg\_1be433737b71419dc9b395e221255fb3/brick\_c67fb$ 

97f74649d990c5743090e0c9176/brick

Brick2:

192.168.121.233:/var/lib/heketi/mounts/vg\_0013ee200cdefaeb6dfedd28e50fd261/brick\_6ebf1e e62a8e9e7a0f88e4551d4b2386/brick

Brick3:

192.168.121.168:/var/lib/heketi/mounts/vg\_e4b32535c55c88f9190da7b7efd1fcab/brick\_df5db97aa002d572a0fec6bcf2101aad/brick

/ aa00203/ 2a01

192.168.121.233:/var/lib/heketi/mounts/vg\_0013ee200cdefaeb6dfedd28e50fd261/brick\_acc82e 56236df912e9a1948f594415a7/brick

Brick5:

192.168.121.168:/var/lib/heketi/mounts/vg\_e4b32535c55c88f9190da7b7efd1fcab/brick\_65dceb1f749ec417533ddeae9535e8be/brick

Brick6:

192.168.121.172:/var/lib/heketi/mounts/vg\_7ad961dbd24e16d62cabe10fd8bf8909/brick\_f25845 0fc6f025f99952a6edea203859/brick

Options Reconfigured:

performance.readdir-ahead: on

Volume Name: vol\_9e86c0493f6b1be648c9deee1dc226a6

Type: Distributed-Replicate

Volume ID: 940177c3-d866-4e5e-9aa0-fc9be94fc0f4

Status: Started

Number of Bricks:  $2 \times 3 = 6$ 

Transport-type: tcp

Bricks: Brick1:

192.168.121.168:/var/lib/heketi/mounts/vg 3fa141bf2d09d30b899f2f260c494376/brick 9fb4a52

06bdd8ac70170d00f304f99a5/brick

Brick2:

192.168.121.172:/var/lib/heketi/mounts/vg\_7ad961dbd24e16d62cabe10fd8bf8909/brick\_dae24 22d518915241f74fd90b426a379/brick

Brick3:

192.168.121.233:/var/lib/heketi/mounts/vg\_5c6428c439eb6686c5e4cee56532bacf/brick\_b3768ba8e80863724c9ec42446ea4812/brick

Brick4:

192.168.121.172:/var/lib/heketi/mounts/vg\_7ad961dbd24e16d62cabe10fd8bf8909/brick\_0a139 58525c6343c4a7951acec199da0/brick

Brick5:

192.168.121.168:/var/lib/heketi/mounts/vg\_17fbc98d84df86756e7826326fb33aa4/brick\_af42af87ab4f01e8ca153abbbee9/brick

Brick6:

192.168.121.233:/var/lib/heketi/mounts/vg\_5c6428c439eb6686c5e4cee56532bacf/brick\_ef41e0 4ca648efaf04178e64d25dbdcb/brick

Options Reconfigured:

performance.readdir-ahead: on

To get the volume status, execute the following command:

# gluster volume status <volname>

#### For example:

# gluster volume status vol_9e86c	0493f6b1b	e648c9d	leee1	dc226a6			
Status of volume: vol_9e86c0493f					l		
Brick 192.168.121.168:/var/lib/hek	eti/mounts/	V					
g_3fa141bf2d09d30b899f2f260c4	94376/brick	_9f					
b4a5206bdd8ac70170d00f304f99a	a5/brick	49154	0	Υ	3462		
Brick 192.168.121.172:/var/lib/hek	eti/mounts/	V					
g_7ad961dbd24e16d62cabe10fd8		k_da					
e2422d518915241f74fd90b426a3		49154	0	Υ	115939		
Brick 192.168.121.233:/var/lib/hek							
g_5c6428c439eb6686c5e4cee565		_					
768ba8e80863724c9ec42446ea48		49154	4 0	Υ	116134		
Brick 192.168.121.172:/var/lib/hek							
g_7ad961dbd24e16d62cabe10fd8		_			4.45050		
13958525c6343c4a7951acec199c		49155	5 0	Υ	115958		
Brick 192.168.121.168:/var/lib/hek							
g_17fbc98d84df86756e7826326fb		_	0	\ <u>/</u>	0.404		
42af87ad87ab4f01e8ca153abbbee		49155	0	Y	3481		
Brick 192.168.121.233:/var/lib/hek							
g_5c6428c439eb6686c5e4cee565 41e04ca648efaf04178e64d25dbdd		_	0	V	116153		
NFS Server on localhost			0 Y	Y 116173	110133		
Self-heal Daemon on localhost		-	Υ		01		
NFS Server on node1.example.co		IN/A	ĭ	2049	0 Y	3501	
Self-heal Daemon on node1.exam				2049 N/A	N/A	Y 3509	
NFS Server on 192.168.121.172	•	049 (	)		5978	1 3309	
Self-heal Daemon on 192.168.121		N/A	N/A	Υ	115986		
3011 110di Dacilioti 011 132.100.121		1 1/ / 1	1 1/ / 1		110000		

Task Status of Volume vol\_9e86c0493f6b1be648c9deee1dc226a6

-----

There are no active volume tasks

 To use the snapshot feature, load the snapshot module using the following command on one of the nodes:

# modprobe dm\_snapshot



#### **IMPORTANT**

#### **Restrictions for using Snapshot**

- After a snapshot is created, it must be accessed throughthe user-serviceable snapshots feature only. This can be used tocopy the old versions of files into the required location.
  - Reverting the volume to a snapshot state is not supported and should never be done as it might damage the consistency of the data.
- On a volume with snapshots, volume changing operations, such as volume expansion, must not be performed.
- To take the snapshot of the gluster volume, execute the following command:
  - # gluster snapshot create <snapname> <volname>

For example:

# gluster snapshot create snap1 vol\_9e86c0493f6b1be648c9deee1dc226a6 snapshot create: success: Snap snap1 GMT-2016.07.29-13.05.46 created successfully

- To list the snapshots, execute the following command:
  - # gluster snapshot list

For example:

# gluster snapshot list

snap1\_GMT-2016.07.29-13.05.46 snap2\_GMT-2016.07.29-13.06.13 snap3\_GMT-2016.07.29-13.06.18 snap4\_GMT-2016.07.29-13.06.22 snap5\_GMT-2016.07.29-13.06.26

- To delete a snapshot, execute the following command:
  - # gluster snap delete <snapname>

For example:

# gluster snap delete snap1\_GMT-2016.07.29-13.05.46

Deleting snap will erase all the information about the snap. Do you still want to continue? (y/n) y

snapshot delete: snap1\_GMT-2016.07.29-13.05.46: snap removed successfully

For more information about managing snapshots, see https://access.redhat.com/documentation/en-us/red\_hat\_gluster\_storage/3.5/html-single/administration\_guide/index#chap-Managing\_Snapshots.

 You can set up Red Hat Openshift Container Storage volumes for geo-replication to a non-Red Hat Openshift Container Storage remote site. Geo-replication uses a master-slave model. Here, the Red Hat Openshift Container Storage volume acts as the master volume. To set up geo-replication, you must run the geo-replication commands on gluster pods. To enter the gluster pod shell, execute the following command:

# oc rsh <gluster\_pod\_name> -n <storage\_project\_name>

For more information about setting up geo-replication, see https://access.redhat.com/documentation/en-us/red\_hat\_gluster\_storage/3.5/html/administration\_guide/chap-managing\_geo-replication.

Brick multiplexing is a feature that allows including multiple bricks into one process. This reduces
resource consumption, allowing you to run more bricks than earlier with the same memory
consumption.

Brick multiplexing is enabled by default from Container-Native Storage 3.6. If you want to turn it off, execute the following command:

# gluster volume set all cluster.brick-multiplex off

• The **auto\_unmount** option in glusterfs libfuse, when enabled, ensures that the file system is unmounted at FUSE server termination by running a separate monitor process that performs the unmount.

The GlusterFS plugin in Openshift enables the auto unmount option for gluster mounts.

#### 2.1. MAINTENANCE ON NODES

#### 2.1.1. Necessary steps to be followed before maintenance

- Remove the label glusterfs or equivalent one which is the selector for the glusterfs daemonset. Wait for the pod to terminate.
  - Run the following command to get the **node selector**.

```
# oc get ds
```

For example:

```
# oc get ds
NAME DESIRED CURRENT READY UP-TO-DATE AVAILABLE
glusterfs-storage 3 3 3 3 3
NODE SELECTOR AGE
glusterfs=storage-host 12d
```

• Remove the glusterfs label using the following command.

# oc label node <storge\_node1> glusterfs-

For example:

# oc label node <storge\_node1> glusterfsnode/<storage\_node1> labeled

• Wait for glusterfs pod to be terminated. Verify using the below command.

# oc get pods -l glusterfs

For example:

```
# oc get pods -l glusterfs
NAME
                      READY
                               STATUS
                                         RESTARTS AGE
glusterblock-storage-provisioner 1/1
                                   Running 0
                                                   7m
glusterfs-storage-4tc9c
                         1/1 Terminating 0
                                                 5m
glusterfs-storage-htrfg
                         1/1
                               Running 0
                                               1d
glusterfs-storage-z75bc
                         1/1
                                 Running 0
                                                1d
heketi-storage-1-shgrr
                         1/1
                                Running 0
                                                1d
```

Make the node unschedulable using the below command.

# oc adm manage-node --schedulable=false <storage\_node1>

For example:

```
# oc adm manage-node --schedulable=false <storage_node1>
NAME STATUS ROLES AGE VERSION
storage_node1 Ready,SchedulingDisabled compute 12d v1.11.0+d4cacc0
```

• Drain the node using the below command.

# oc adm drain --ignore-daemonsets <storage\_node1>



#### **NOTE**

Perform the maintenance and reboot if required

#### 2.1.2. Necessary steps to be followed after maintenance

Make the node schedulable using the below command.

# oc adm manage-node --schedulable=true <storage\_node1>

For example:

# oc adm manage-node --schedulable=true <storage\_node1> NAME STATUS ROLES AGE VERSION node1 Ready compute 12d v1.11.0+d4cacc0

- Add the label **glusterfs** or equivalent which is the selector for the **glusterfs daemonset**. Wait for the pod to be ready.
  - Run the following command to get the **node selector**.

```
# oc get ds
```

For example:

```
# oc get ds

NAME DESIRED CURRENT READY UP-TO-DATE AVAILABLE glusterfs-storage 3 3 3 3 3 

NODE SELECTOR AGE glusterfs=storage-host 12d
```

• Label the glusterfs node using the above node selector and the below command.

```
# oc label node <storage_node1> glusterfs=storage-host
```

For example:

```
# oc label node <storage_node1> glusterfs=storage-host
node/<storage_node1> labeled
```

• Wait for the pod to come up to Ready State.

```
# oc get pods
```

For example:

```
# oc get pods
NAME
                       READY
                                 STATUS RESTARTS AGE
glusterblock-storage-provisioner 1/1
                                     Running 0
                                                     3m
glusterfs-storage-4tc9c
                                  Running 0
                                                  50s
                           0/1
glusterfs-storage-htrfg
                          1/1
                                 Running 0
                                                 1d
glusterfs-storage-z75bc
                           1/1
                                  Running 0
                                                  1d
heketi-storage-1-shgrr
                                  Running 0
                           1/1
                                                  1d
```

• Wait for the pod to be in 1/1 Ready State. For example:

```
# oc get pods
NAME
                        READY
                                 STATUS RESTARTS AGE
glusterblock-storage-provisioner
                              1/1
                                     Running 0
                                                     3m
glusterfs-storage-4tc9c
                           1/1
                                  Running 0
                                                  58s
glusterfs-storage-htrfg
                           1/1
                                                 1d
                                 Running 0
glusterfs-storage-z75bc
                           1/1
                                   Running 0
                                                  1d
heketi-storage-1-shgrr
                           1/1
                                  Running 0
                                                  1d
```

• Wait for heal to complete, use oc rsh to obtain shell of glusterfs pod and monitor heal using the below command, and wait for **Number of entries** to be zero(0).

# for each\_volume in gluster volume list; do gluster volume heal \$each\_volume info; done

#### For example:

# for each\_volume in gluster volume list; do gluster volume heal \$each\_volume info ; done Brick

10.70.46.210:/var/lib/heketi/mounts/vg\_64e90b4b94174f19802a8026f652f6d7/brick\_564f7725c ef192f0fd2ba1422ecbf590/brick

Status: Connected Number of entries: 0

#### Brick

10.70.46.243:/var/lib/heketi/mounts/vg\_4fadbf84bbc67873543472655e9660ec/brick\_9c9c8c64c48d24c91948bc810219c945/brick

Status: Connected Number of entries: 0

#### Brick

10.70.46.224:/var/lib/heketi/mounts/vg\_9fbaf0c06495e66f5087a51ad64e54c3/brick\_75e40df81 383a03b1778399dc342e794/brick

Status: Connected Number of entries: 0

#### **Brick**

10.70.46.224:/var/lib/heketi/mounts/vg\_9fbaf0c06495e66f5087a51ad64e54c3/brick\_e0058f65155769142cec81798962b9a7/brick

Status: Connected Number of entries: 0

#### Brick

10.70.46.210:/var/lib/heketi/mounts/vg\_64e90b4b94174f19802a8026f652f6d7/brick\_3cf035275 dc93e0437fdfaea509a3a44/brick

Status: Connected Number of entries: 0

#### Brick

10.70.46.243:/var/lib/heketi/mounts/vg\_4fadbf84bbc67873543472655e9660ec/brick\_2cfd11ce587e622fe800dfaec101e463/brick

Status: Connected Number of entries: 0

## **PART II. OPERATIONS**

#### **CHAPTER 3. CREATING PERSISTENT VOLUMES**

OpenShift Container Platform clusters can be provisioned with persistent storage using GlusterFS.

Persistent volumes (PVs) and persistent volume claims (PVCs) can share volumes across a single project. While the GlusterFS-specific information contained in a PV definition could also be defined directly in a pod definition, doing so does not create the volume as a distinct cluster resource, making the volume more susceptible to conflicts.

#### Binding PVs by Labels and Selectors

Labels are an OpenShift Container Platform feature that support user-defined tags (key-value pairs) as part of an object's specification. Their primary purpose is to enable the arbitrary grouping of objects by defining identical labels among them. These labels can then be targeted by selectors to match all objects with specified label values. It is this functionality we will take advantage of to enable our PVC to bind to our PV.

You can use labels to identify common attributes or characteristics shared among volumes. For example, you can define the gluster volume to have a custom attribute (key) named storage-tier\_with a value of \_gold \_assigned. A claim will be able to select a PV with \_storage-tier=gold to match this PV.

More details for provisioning volumes in file-based storage is provided in ]. Similarly, further details for provisioning volumes in block-based storage is provided in xref:Block\_Storage[.

#### 3.1. FILE STORAGE

File storage, also called file-level or file-based storage, stores data in a hierarchical structure. The data is saved in files and folders, and presented to both the system storing it and the system retrieving it in the same format. You can provision volumes either statically or dynamically for file-based storage.

#### 3.1.1. Static Provisioning of Volumes

To enable persistent volume support in OpenShift and Kubernetes, few endpoints and a service must be created.



#### NOTE

The following steps are not required if OpenShift Container Storage was deployed using the (default) Ansible installer

The sample glusterfs endpoint file (sample-gluster-endpoints.yaml) and the sample glusterfs service file (sample-gluster-service.yaml) are available at\* /usr/share/heketi/templates/ \*directory.

The sample endpoints and services file will not be available for ansible deployments since /usr/share/heketi/templates/ directory will not be created for such deployments.



#### **NOTE**

Ensure to copy the sample glusterfs endpoint file / glusterfs service file to a location of your choice and then edit the copied file. For example:

# cp /usr/share/heketi/templates/sample-gluster-endpoints.yaml /<\_path\_>/gluster-endpoints.yaml

1. To specify the endpoints you want to create, update the copied **sample-gluster-endpoints.yaml** file with the endpoints to be created based on the environment. Each Red Hat Gluster Storage trusted storage pool requires its own endpoint with the IP of the nodes in the trusted storage pool.

```
# cat sample-gluster-endpoints.yaml
apiVersion: v1
kind: Endpoints
metadata:
 name: glusterfs-cluster
subsets:
 - addresses:
   - ip: 192.168.10.100
  ports:
   - port: 1
 - addresses:
   - ip: 192.168.10.101
  ports:
   - port: 1
 - addresses:
   - ip: 192.168.10.102
  ports:
- port: 1
```

#### name

The name of the endpoint.

ip

The ip address of the Red Hat Gluster Storage nodes.

2. Execute the following command to create the endpoints:

```
# oc create -f <name_of_endpoint_file>
```

For example:

```
# oc create -f sample-gluster-endpoints.yaml endpoints "glusterfs-cluster" created
```

3. To verify that the endpoints are created, execute the following command:

# oc get endpoints

For example:

```
# oc get endpoints
NAME ENDPOINTS AGE
storage-project-router 192.168.121.233:80,192.168.121.233:443,192.168.121.233:1936
2d
glusterfs-cluster 192.168.121.168:1,192.168.121.172:1,192.168.121.233:1 3s
heketi 10.1.1.3:8080 2m
heketi-storage-endpoints 192.168.121.168:1,192.168.121.172:1,192.168.121.233:1 3m
```

4. Execute the following command to create a gluster service:

# oc create -f <name\_of\_service\_file>

For example:

```
# cat sample-gluster-service.yaml
apiVersion: v1
kind: Service
metadata:
name: glusterfs-cluster
spec:
ports:
- port: 1
```

# oc create -f sample-gluster-service.yaml service "glusterfs-cluster" created

5. To verify that the service is created, execute the following command:

# oc get service

For example:

```
# oc get service
NAME
                  CLUSTER-IP
                                EXTERNAL-IP PORT(S)
                                                                 AGE
                                              80/TCP,443/TCP,1936/TCP 2d
storage-project-router 172.30.94.109 <none>
glusterfs-cluster
                   172.30.212.6 <none>
                                           1/TCP
                                                            5s
heketi
                172.30.175.7 <none>
                                        8080/TCP
                                                           2m
heketi-storage-endpoints 172.30.18.24 <none>
                                               1/TCP
                                                                3<sub>m</sub>
```



## **NOTE**

The endpoints and the services must be created for each project that requires a persistent storage.

6. Create a 100G persistent volume with Replica 3 from GlusterFS and output a persistent volume specification describing this volume to the file pv001.json:

\$ heketi-cli volume create --size=100 --persistent-volume-file=pv001.json

```
cat pv001.json
{
  "kind": "PersistentVolume",
  "apiVersion": "v1",
  "metadata": {
     "name": "glusterfs-f8c612ee",
     "creationTimestamp": null
  },
  "spec": {
     "capacity": {
        "storage": "100Gi"
     },
     "glusterfs": {
```

```
"endpoints": "TYPE ENDPOINT HERE",
   "path": "vol_f8c612eea57556197511f6b8c54b6070"
},
   "accessModes": [
    "ReadWriteMany"
],
   "persistentVolumeReclaimPolicy": "Retain"
},
   "status": {}
```



#### **IMPORTANT**

You must manually add the Labels information to the .json file.

Following is the example YAML file for reference:

```
apiVersion: v1
kind: PersistentVolume
metadata:
name: pv-storage-project-glusterfs1
labels:
storage-tier: gold
spec:
capacity:
storage: 12Gi
accessModes:
- ReadWriteMany
persistentVolumeReclaimPolicy: Retain
glusterfs:
endpoints: TYPE END POINTS NAME HERE,
path: vol_e6b77204ff54c779c042f570a71b1407
```

## name

The name of the volume.

## storage

The amount of storage allocated to this volume

## glusterfs

The volume type being used, in this case the glusterfs plug-in

## endpoints

The endpoints name that defines the trusted storage pool created

#### path

The Red Hat Gluster Storage volume that will be accessed from the Trusted Storage Pool.

#### accessModes

accessModes are used as labels to match a PV and a PVC. They currently do not define any form of access control.

## labels

Use labels to identify common attributes or characteristics shared among volumes. In this case, we have defined the gluster volume to have a custom attribute (key) named *storage-tier* with a value of *gold* assigned. A claim will be able to select a PV with *storage-tier=gold* to match this PV.



#### **NOTE**

- heketi-cli also accepts the endpoint name on the command line (-persistent-volume-endpoint="TYPE ENDPOINT HERE"). This can then be
  piped to oc create -f to create the persistent volume immediately.
- If there are multiple Red Hat Gluster Storage trusted storage pools in your environment, you can check on which trusted storage pool the volume is created using the **heketi-cli volume list** command. This command lists the cluster name. You can then update the endpoint information in the **pv001.json** file accordingly.
- When creating a Heketi volume with only two nodes with the replica count set to the default value of three (replica 3), an error "No space" is displayed by Heketi as there is no space to create a replica set of three disks on three different nodes.
- If all the heketi-cli write operations (ex: volume create, cluster create..etc) fails and the read operations (ex: topology info, volume info ..etc) are successful, then the possibility is that the gluster volume is operating in read-only mode.
- 7. Edit the pv001.json file and enter the name of the endpoint in the endpoint's section:

```
cat pv001.json
 "kind": "PersistentVolume",
 "apiVersion": "v1",
 "metadata": {
  "name": "glusterfs-f8c612ee",
  "creationTimestamp": null,
  "labels": {
   "storage-tier": "gold"
 "spec": {
  "capacity": {
   "storage": "12Gi"
  "glusterfs": {
   "endpoints": "glusterfs-cluster",
   "path": "vol_f8c612eea57556197511f6b8c54b6070"
  "accessModes": [
   "ReadWriteMany"
  "persistentVolumeReclaimPolicy": "Retain"
 "status": {}
```

8. Create a persistent volume by executing the following command:

# oc create -f pv001.json

For example:

```
# oc create -f pv001.json
persistentvolume "glusterfs-4fc22ff9" created
```

9. To verify that the persistent volume is created, execute the following command:

```
# oc get pv
```

For example:

```
# oc get pv
```

NAME CAPACITY ACCESSMODES STATUS CLAIM REASON AGE glusterfs-4fc22ff9 100Gi RWX Available 4s

10. Create a persistent volume claim file. For example:

```
# cat pvc.yaml
apiVersion: v1
kind: PersistentVolumeClaim
metadata:
   name: glusterfs-claim
spec:
   accessModes:
   - ReadWriteMany
resources:
   requests:
    storage: 100Gi
   selector:
   matchLabels:
storage-tier: gold
```

11. Bind the persistent volume to the persistent volume claim by executing the following command:

```
# oc create -f pvc.yaml
```

For example:

```
# oc create -f pvc.yaml
persistentvolumeclaim"glusterfs-claim" created
```

12. To verify that the persistent volume and the persistent volume claim is bound, execute the following commands:

```
# oc get pv
# oc get pvc
```

For example:

```
# oc get pv
```

NAME CAPACITY ACCESSMODES STATUS CLAIM REASON

**AGE** 

glusterfs-4fc22ff9 100Gi RWX Bound storage-project/glusterfs-claim 1m

# oc get pvc

NAME STATUS VOLUME CAPACITY ACCESSMODES AGE glusterfs-claim Bound glusterfs-4fc22ff9 100Gi RWX 11s

13. The claim can now be used in the application. For example:

```
# cat app.yaml
```

apiVersion: v1 kind: Pod metadata: name: busybox

spec:

containers:

- image: busybox command:
  - sleep
  - "3600"

name: busybox volumeMounts:

- mountPath: /usr/share/busybox
  - name: mypvc

volumes:

- name: mypvc
- persistentVolumeClaim: claimName: glusterfs-claim

# oc create -f app.yaml pod "busybox" created

For more information about using the glusterfs claim in the application see, https://access.redhat.com/documentation/en-us/openshift\_container\_platform/3.11/html-single/configuring\_clusters/#install-config-storage-examples-gluster-example.

14. To verify that the pod is created, execute the following command:

# oc get pods -n <storage\_project\_name>

For example:

# oc get pods -n storage-project

NAME	READ'	Y STATI	JS	RESTAF	RTS	AGE
block-test-router-1-deploy	y 0	/1 Run	ning	0	4h	
busybox	1/1	Running	0	43s		
glusterblock-provisioner-	1-bjpz4	1/1 R	unniı	ng 0	4h	
glusterfs-7l5xf	1/1	Running	0	4h		
glusterfs-hhxtk	1/1	Running	3	4h		
glusterfs-m4rbc	1/1	Running	g 0	4h		
heketi-1-3h9nb	1/1	Running	g 0	4h		

15. To verify that the persistent volume is mounted inside the container, execute the following command:

## # oc rsh busybox

```
/ $ df -h
Filesystem
                         Used Available Use% Mounted on
                  Size
/dev/mapper/docker-253:0-1310998-
81732b5fd87c197f627a24bcd2777f12eec4ee937cc2660656908b2fa6359129
            100.0G 34.1M 99.9G 0%/
                             1.5G 0% /dev
tmpfs
                1.5G
                         0
tmpfs
                1.5G
                             1.5G 0% /sys/fs/cgroup
                         0
192.168.121.168:vol 4fc22ff934e531dec3830cfbcad1eeae
            99.9G 66.1M
                            99.9G 0% /usr/share/busybox
                1.5G
                            1.5G 0% /run/secrets
/dev/mapper/vg vagrant-lv root
            37.7G
                     3.8G 32.0G 11% /dev/termination-log
tmpfs
                1.5G 12.0K
                               1.5G 0% /var/run/secretgit
s/kubernetes.io/serviceaccount
```



#### **NOTE**

If you encounter a permission denied error on the mount point, then refer to section Gluster Volume Security at: https://access.redhat.com/documentation/en-us/openshift\_container\_platform/3.11/html-single/configuring\_clusters/#install-configstorage-examples-gluster-example.

# 3.1.2. Dynamic Provisioning of Volumes

Dynamic provisioning enables you to provision a Red Hat Gluster Storage volume to a running application container without pre-creating the volume. The volume will be created dynamically as the claim request comes in, and a volume of exactly the same size will be provisioned to the application containers.



#### **NOTE**

The steps outlined below are not necessary when OpenShift Container Storage was deployed using the (default) Ansible installer and the default storage class (glusterfsstorage) created during the installation will be used.

### 3.1.2.1. Configuring Dynamic Provisioning of Volumes

To configure dynamic provisioning of volumes, the administrator must define StorageClass objects that describe named "classes" of storage offered in a cluster. After creating a Storage Class, a secret for heketi authentication must be created before proceeding with the creation of persistent volume claim.

#### 3.1.2.1.1. Creating Secret for Heketi Authentication

To create a secret for Heketi authentication, execute the following commands:



#### **NOTE**

If the **admin-key** value (secret to access heketi to get the volume details) was not set during the deployment of Red Hat Openshift Container Storage, then the following steps can be omitted.

1. Create an encoded value for the password by executing the following command:

```
# echo -n "<key>" | base64
```

where "key" is the value for "admin-key" that was created while deploying Red Hat Openshift Container Storage

For example:

```
# echo -n "mypassword" | base64
bXlwYXNzd29yZA==
```

2. Create a secret file. A sample secret file is provided below:

# cat glusterfs-secret.yaml

apiVersion: v1 kind: Secret metadata:

name: heketi-secret namespace: default

data:

# base64 encoded password. E.g.: echo -n "mypassword" | base64

key: bXlwYXNzd29yZA==
type: kubernetes.io/glusterfs

3. Register the secret on Openshift by executing the following command:

```
# oc create -f glusterfs-secret.yaml
secret "heketi-secret" created
```

## 3.1.2.1.2. Registering a Storage Class

When configuring a StorageClass object for persistent volume provisioning, the administrator must describe the type of provisioner to use and the parameters that will be used by the provisioner when it provisions a PersistentVolume belonging to the class.

1. To create a storage class execute the following command:

# cat > glusterfs-storageclass.yaml

apiVersion: storage.k8s.io/v1

kind: StorageClass

metadata:

name: gluster-container

provisioner: kubernetes.io/glusterfs

reclaimPolicy: Retain

parameters:

resturl: "http://heketi-storage-project.cloudapps.mystorage.com"

restuser: "admin"

volumetype: "replicate:3"

clusterid: "630372ccdc720a92c681fb928f27b53f,796e6db1981f369ea0340913eeea4c9a"

secretNamespace: "default" secretName: "heketi-secret"

volumeoptions: "client.ssl on, server.ssl on"

volumenameprefix: "test-vol" allowVolumeExpansion: true

where,

#### resturl

Gluster REST service/Heketi service url which provision gluster volumes on demand. The general format must be IPaddress:Port and this is a mandatory parameter for GlusterFS dynamic provisioner. If Heketi service is exposed as a routable service in openshift/kubernetes setup, this can have a format similar to http://heketi-storage-project.cloudapps.mystorage.com where the fqdn is a resolvable heketi service url.

#### restuser

Gluster REST service/Heketi user who has access to create volumes in the trusted storage pool

#### volumetype

It specifies the volume type that is being used.



#### NOTE

Distributed-Three-way replication is the only supported volume type.

#### clusterid

It is the ID of the cluster which will be used by Heketi when provisioning the volume. It can also be a list of comma-separated cluster IDs. This is an optional parameter.



## NOTE

To get the cluster ID, execute the following command:



# heketi-cli cluster list

## secretNamespace + secretName

Identification of Secret instance that contains the user password that is used when communicating with the Gluster REST service. These parameters are optional. Empty password will be used when both secretNamespace and secretName are omitted.



#### **NOTE**

When the persistent volumes are dynamically provisioned, the Gluster plugin automatically creates an endpoint and a headless service in the name gluster-dynamic-<claimname>. This dynamic endpoint and service will be deleted automatically when the persistent volume claim is deleted.

#### volumeoptions

This is an optional parameter. It allows you to create glusterfs volumes with encryption enabled by setting the parameter to "client.ssl on, server.ssl on". For more information on enabling encryption, see Chapter 8, *Enabling Encryption*.



#### **NOTE**

Do not add this parameter in the storageclass if encryption is not enabled.

## volumenameprefix

This is an optional parameter. It depicts the name of the volume created by heketi. For more information see Section 3.1.2.1.5, "(Optional) Providing a Custom Volume Name Prefix for Persistent Volumes"



#### NOTE

The value for this parameter cannot contain \_ in the storageclass.

## allowVolumeExpansion

To increase the PV claim value, ensure to set the **allowVolumeExpansion** parameter in the storageclass file to **true**. For more information, see Section 3.1.2.1.7, "Expanding Persistent Volume Claim".

2. To register the storage class to Openshift, execute the following command:

# oc create -f glusterfs-storageclass.yaml storageclass "gluster-container" created

3. To get the details of the storage class, execute the following command:

# oc describe storageclass gluster-container

Name: gluster-container IsDefaultClass: No Annotations: <none>

Provisioner: kubernetes.io/glusterfs Parameters: resturl=http://heketi-storage-

project.cloudapps.mystorage.com,restuser=admin,secretName=heketi-

secret,secretNamespace=default

No events.

## 3.1.2.1.3. Creating a Persistent Volume Claim

To create a persistent volume claim execute the following commands:

1. Create a Persistent Volume Claim file. A sample persistent volume claim is provided below:

# cat glusterfs-pvc-claim1.yaml kind: PersistentVolumeClaim apiVersion: v1 metadata: name: claim1 annotations:

volume.beta.kubernetes.io/storage-class: gluster-container

spec:

persistentVolumeReclaimPolicy: Retain

accessModes:

- ReadWriteOnce

resources:

requests: storage: 5Gi

## persistentVolumeReclaimPolicy

This is an optional parameter. When this parameter is set to "Retain" the underlying persistent volume is retained even after the corresponding persistent volume claim is deleted.



#### NOTE

When PVC is deleted, the underlying heketi and gluster volumes are not deleted if "persistentVolumeReclaimPolicy:" is set to "Retain". To delete the volume, you must use heketi cli and then delete the PV.

2. Register the claim by executing the following command:

# oc create -f glusterfs-pvc-claim1.yaml persistentvolumeclaim "claim1" created

3. To get the details of the claim, execute the following command:

# oc describe pvc <\_claim\_name\_>

For example:

# oc describe pvc claim1

Name: claim1

Namespace: default

StorageClass: gluster-container

Status: Bound

Volume: pvc-54b88668-9da6-11e6-965e-54ee7551fd0c

Labels: <none>
Capacity: 4Gi

Access Modes: RWO

No events.

## 3.1.2.1.4. Verifying Claim Creation

To verify if the claim is created, execute the following commands:

1. To get the details of the persistent volume claim and persistent volume, execute the following command:

# oc get pv,pvc

NAME CAPACITY ACCESSMODES RECLAIMPOLICY

STATUS CLAIM REASON AGE

pv/pvc-962aa6d1-bddb-11e6-be23-5254009fc65b 4Gi RWO Delete Bound storage-project/claim1 3m

NAME STATUS VOLUME CAPACITY ACCESSMODES AGE pvc/claim1 Bound pvc-962aa6d1-bddb-11e6-be23-5254009fc65b 4Gi RWO 4m

2. To validate if the endpoint and the services are created as part of claim creation, execute the following command:

# oc get endpoints, service

NAME ENDPOINTS AGE

ep/storage-project-router 192.168.68.3:443,192.168.68.3:1936,192.168.68.3:80 28d

ep/gluster-dynamic-claim1 192.168.68.2:1,192.168.68.3:1,192.168.68.4:1 5m

ep/heketi 10.130.0.21:8080 21d

ep/heketi-storage-endpoints 192.168.68.2:1,192.168.68.3:1,192.168.68.4:1 25d

**CLUSTER-IP** EXTERNAL-IP PORT(S) **AGE** svc/storage-project-router 172.30.166.64 <none> 80/TCP,443/TCP,1936/TCP 28d svc/gluster-dynamic-claim1 172.30.52.17 1/TCP 5m svc/heketi 8080/TCP 172.30.129.113 <none> 21d svc/heketi-storage-endpoints 172.30.133.212 <none> 25d 1/TCP

## 3.1.2.1.5. (Optional) Providing a Custom Volume Name Prefix for Persistent Volumes

You can provide a custom volume name prefix to the persistent volume that is created. By providing a custom volume name prefix, users can now easily search/filter the volumes based on:

- Any string that was provided as the field value of "volnameprefix" in the storageclass file.
- Persistent volume claim name.
- Project / Namespace name.

To set the name, ensure that you have added the parameter **volumenameprefix** to the storage class file. For more information, see Section 3.1.2.1.2, "Registering a Storage Class"



#### **NOTE**

The value for this parameter cannot contain \_ in the storageclass.

To verify if the custom volume name prefix is set, execute the following command:

# oc describe pv <pv\_name>

For example:

# oc describe pv pvc-f92e3065-25e8-11e8-8f17-005056a55501 Name: pvc-f92e3065-25e8-11e8-8f17-005056a55501

Labels: <none>

```
Description=Gluster-Internal: Dynamically provisioned PV
Annotations:
          gluster.kubernetes.io/heketi-volume-id=027c76b24b1a3ce3f94d162f843529c8
          gluster.org/type=file
          kubernetes.io/createdby=heketi-dynamic-provisioner
          pv.beta.kubernetes.io/gid=2000
          pv.kubernetes.io/bound-by-controller=yes
          pv.kubernetes.io/provisioned-by=kubernetes.io/glusterfs
          volume.beta.kubernetes.io/mount-options=auto unmount
StorageClass: gluster-container-prefix
Status:
            Bound
Claim:
            glusterfs/claim1
Reclaim Policy: Delete
Access Modes: RWO
Capacity:
             1Gi
Message:
Source:
  Type:
            Glusterfs (a Glusterfs mount on the host that shares a pod's lifetime)
  EndpointsName: glusterfs-dynamic-claim1
  Path:
             test-vol_glusterfs_claim1_f9352e4c-25e8-11e8-b460-005056a55501
  ReadOnly:
                false
Events:
              <none>
```

The value for **Path** will have the custom volume name prefix attached to the namespace and the claim name, which is "test-vol" in this case.

#### 3.1.2.1.6. Using the Claim in a Pod

Execute the following steps to use the claim in a pod.

1. To use the claim in the application, for example

```
# cat app.yaml
apiVersion: v1
kind: Pod
metadata:
 name: busybox
spec:
 containers:
  - image: busybox
   command:
    - sleep
    - "3600"
   name: busybox
   volumeMounts:
    - mountPath: /usr/share/busybox
     name: mypvc
 volumes:
  - name: mypvc
   persistentVolumeClaim:
claimName: claim1
# oc create -f app.yaml
```

pod "busybox" created

For more information about using the glusterfs claim in the application see, https://access.redhat.com/documentation/en-us/openshift\_container\_platform/3.11/html-single/configuring\_clusters/#install-config-storage-examples-gluster-example.

2. To verify that the pod is created, execute the following command:

# oc get pods -n storage-project

NAME STATUS RESTARTS AGE READY storage-project-router-1-at7tf 1/1 Running 0 13d busybox 1/1 Running 0 8s glusterfs-dc-192.168.68.2-1-hu28h 1/1 7d Running 0 glusterfs-dc-192.168.68.3-1-ytnlg 1/1 0 7d Running glusterfs-dc-192.168.68.4-1-juqcq 1/1 13d Running 0 heketi-1-9r47c 1/1 Running 13d

3. To verify that the persistent volume is mounted inside the container, execute the following command:

# oc rsh busybox

```
/ $ df -h
Filesystem
                  Size
                         Used Available Use% Mounted on
/dev/mapper/docker-253:0-666733-
38050a1d2cdb41dc00d60f25a7a295f6e89d4c529302fb2b93d8faa5a3205fb9
             10.0G
                     33.8M
                              9.9G 0%/
tmpfs
                             23.5G 0% /dev
               23.5G
                          0
tmpfs
               23.5G
                          0 23.5G 0%/sys/fs/cgroup
/dev/mapper/rhgs-root
             17.5G
                      3.6G
                            13.8G 21% /run/secrets
/dev/mapper/rhgs-root
             17.5G
                      3.6G 13.8G 21% /dev/termination-log
/dev/mapper/rhgs-root
             17.5G
                            13.8G 21% /etc/resolv.conf
                      3.6G
/dev/mapper/rhgs-root
             17.5G
                      3.6G 13.8G 21% /etc/hostname
/dev/mapper/rhgs-root
             17.5G
                      3.6G 13.8G 21% /etc/hosts
shm
               64.0M
                          0 64.0M 0% /dev/shm
192.168.68.2:vol_5b05cf2e5404afe614f8afa698792bae
              4.0G
                     32.6M
                             4.0G 1% /usr/share/busybox
tmpfs
               23.5G
                       16.0K
                               23.5G 0%
/var/run/secrets/kubernetes.io/serviceaccount
tmpfs
               23.5G
                          0
                             23.5G 0% /proc/kcore
tmpfs
               23.5G
                             23.5G 0% /proc/timer stats
```

#### 3.1.2.1.7. Expanding Persistent Volume Claim

To increase the PV claim value, ensure to set the **allowVolumeExpansion** parameter in the storageclass file to **true**. For more information refer, Section 3.1.2.1.2, "Registering a Storage Class"



### **NOTE**

You can also resize a PV via the OpenShift Container Platform 3.11 Web Console.

To expand the persistent volume claim value, execute the following commands:

 If the feature gates ExpandPersistentVolumes, and the admissionconfig PersistentVolumeClaimResize are not enabled, then edit the master.conf file located at /etc/origin/master/master-config.yaml on the master to enable them. For example: To enable feature gates ExpandPersistentVolumes

```
apiServerArguments:
    runtime-config:
    - apis/settings.k8s.io/v1alpha1=true
    storage-backend:
    - etcd3
    storage-media-type:
    - application/vnd.kubernetes.protobuf
    feature-gates:
    - ExpandPersistentVolumes=true
    controllerArguments:
        feature-gates:
        - ExpandPersistentVolumes=true
```

To enable admissionconfig **PersistentVolumeClaimResize** add the following under admission config in the master-config file.

```
admissionConfig:
pluginConfig:
PersistentVolumeClaimResize:
configuration:
apiVersion: v1
disable: false
kind: DefaultAdmissionConfig
```

a. Restart the OpenShift master by running the following commands:

```
# /usr/local/bin/master-restart api
# /usr/local/bin/master-restart controllers
```

2. To check the existing persistent volume size, execute the following command on the app pod:

```
# oc rsh busybox
# df -h
```

For example:

```
# oc rsh busybox
/ # df -h
Filesystem
                 Size
                        Used Available Use% Mounted on
/dev/mapper/docker-253:0-100702042-
0fa327369e7708b67f0c632d83721cd9a5b39fd3a7b3218f3ff3c83ef4320ce7
            10.0G 34.2M 9.9G 0%/
                        0 15.6G 0%/dev
tmpfs
               15.6G
tmpfs
               15.6G
                         0 15.6G 0%/sys/fs/cgroup
/dev/mapper/rhel_dhcp47--150-root
             50.0G
                     7.4G 42.6G 15% /dev/termination-log
```

```
/dev/mapper/rhel_dhcp47--150-root
              50.0G
                     7.4G 42.6G 15% /run/secrets
/dev/mapper/rhel_dhcp47--150-root
              50.0G 7.4G 42.6G 15% /etc/resolv.conf
/dev/mapper/rhel dhcp47--150-root
              50.0G 7.4G 42.6G 15% /etc/hostname
/dev/mapper/rhel dhcp47--150-root
              50.0G 7.4G 42.6G 15% /etc/hosts
                           0 64.0M 0%/dev/shm
                64.0M
10.70.46.177:test-vol glusterfs claim10 d3e15a8b-26b3-11e8-acdf-005056a55501
                      32.6M
                               2.0G 2% /usr/share/busybox
              2.0G
                        16.0K 15.6G 0%
tmpfs
                15.6G
/var/run/secrets/kubernetes.io/serviceaccount
                        0 15.6G 0%/proc/kcore
tmpfs
                15.6G
                15.6G
                           0 15.6G 0% /proc/timer_list
tmpfs
                15.6G 0 15.6G 0% /proc/timer_stats
15.6G 0 15.6G 0% /proc/sched_debug
15.6G 0 15.6G 0% /proc/scsi
tmpfs
tmpfs
tmpfs
tmpfs
                15.6G
                         0 15.6G 0%/sys/firmware
```

In this example the persistent volume size is 2Gi.

3. To edit the persistent volume claim value, execute the following command and edit the following storage parameter:

```
resources:
    requests:
    storage: <storage_value>

# oc edit pvc <claim_name>
```

For example, to expand the storage value to 20Gi:

```
# oc edit pvc claim3
apiVersion: v1
kind: PersistentVolumeClaim
metadata:
 annotations:
  pv.kubernetes.io/bind-completed: "yes"
  pv.kubernetes.io/bound-by-controller: "yes"
  volume.beta.kubernetes.io/storage-class: gluster-container2
  volume.beta.kubernetes.io/storage-provisioner: kubernetes.io/glusterfs
 creationTimestamp: 2018-02-14T07:42:00Z
 name: claim3
 namespace: storage-project
 resourceVersion: "283924"
 selfLink: /api/v1/namespaces/storage-project/persistentvolumeclaims/claim3
 uid: 8a9bb0df-115a-11e8-8cb3-005056a5a340
 accessModes:
 - ReadWriteOnce
 resources:
  requests:
   storage: 20Gi
 volumeName: pvc-8a9bb0df-115a-11e8-8cb3-005056a5a340
```

status:

accessModes:

- ReadWriteOnce

capacity: storage: 2Gi phase: Bound

4. To verify, execute the following command on the app pod:

# oc rsh busybox

/ # df -h

For example:

```
# oc rsh busybox
# df -h
Filesystem
                        Used Available Use% Mounted on
                 Size
/dev/mapper/docker-253:0-100702042-
0fa327369e7708b67f0c632d83721cd9a5b39fd3a7b3218f3ff3c83ef4320ce7
             10.0G 34.2M
                             9.9G 0%/
                         0 15.6G 0%/dev
tmpfs
               15.6G
tmpfs
               15.6G
                         0 15.6G 0%/sys/fs/cgroup
/dev/mapper/rhel_dhcp47--150-root
             50.0G
                     7.4G 42.6G 15% /dev/termination-log
/dev/mapper/rhel dhcp47--150-root
             50.0G
                     7.4G 42.6G 15% /run/secrets
/dev/mapper/rhel dhcp47--150-root
             50.0G
                     7.4G 42.6G 15% /etc/resolv.conf
/dev/mapper/rhel dhcp47--150-root
             50.0G
                     7.4G 42.6G 15% /etc/hostname
/dev/mapper/rhel_dhcp47--150-root
             50.0G
                     7.4G 42.6G 15% /etc/hosts
               64.0M
                         0 64.0M 0% /dev/shm
10.70.46.177:test-vol glusterfs claim10 d3e15a8b-26b3-11e8-acdf-005056a55501
             20.0G 65.3M 19.9G 1% /usr/share/busybox
tmpfs
               15.6G
                       16.0K
                              15.6G 0%
/var/run/secrets/kubernetes.io/serviceaccount
tmpfs
               15.6G
                         0 15.6G 0% /proc/kcore
tmpfs
                         0 15.6G 0% /proc/timer list
               15.6G
tmpfs
                         0 15.6G 0% /proc/timer stats
               15.6G
tmpfs
               15.6G
                         0 15.6G 0% /proc/sched_debug
tmpfs
               15.6G
                         0 15.6G 0% /proc/scsi
                         0 15.6G 0%/sys/firmware
tmpfs
               15.6G
```

It is observed that the size is changed from 2Gi (earlier) to 20Gi.

#### 3.1.2.1.8. Deleting a Persistent Volume Claim



#### NOTE

If the "persistentVolumeReclaimPolicy" parameter was set to "Retain" when registering the storageclass, the underlying PV and the corresponding volume remains even when a PVC is deleted.

1. To delete a claim, execute the following command:

# oc delete pvc <claim-name>

For example:

# oc delete pvc claim1
persistentvolumeclaim "claim1" deleted

2. To verify if the claim is deleted, execute the following command:

# oc get pvc <claim-name>

For example:

# oc get pvc claim1 No resources found.

When the user deletes a persistent volume claim that is bound to a persistent volume created by dynamic provisioning, apart from deleting the persistent volume claim, Kubernetes will also delete the persistent volume, endpoints, service, and the actual volume. Execute the following commands if this has to be verified:

• To verify if the persistent volume is deleted, execute the following command:

# oc get pv <pv-name>

For example:

# oc get pv pvc-962aa6d1-bddb-11e6-be23-5254009fc65b No resources found.

• To verify if the endpoints are deleted, execute the following command:

# oc get endpoints <endpointname>

For example:

# oc get endpoints gluster-dynamic-claim1 No resources found.

• To verify if the service is deleted, execute the following command:

# oc get service <servicename>

For example:

# oc get service gluster-dynamic-claim1 No resources found.

## 3.1.3. Volume Security

Volumes come with a UID/GID of 0 (root). For an application pod to write to the volume, it should also have a UID/GID of 0 (root). With the volume security feature the administrator can now create a volume with a unique GID and the application pod can write to the volume using this unique GID

## Volume security for statically provisioned volumes

To create a statically provisioned volume with a GID, execute the following command:

\$ heketi-cli volume create --size=100 --persistent-volume-file=pv001.json --gid=590

In the above command, a 100G persistent volume with a GID of 590 is created and the output of the persistent volume specification describing this volume is added to the **pv001.json** file.

For more information about accessing the volume using this GID, see https://access.redhat.com/documentation/en-us/openshift\_container\_platform/3.11/html/configuring\_clusters/persistent-storage-examples#install-config-storage-examples-gluster-example.

## Volume security for dynamically provisioned volumes

Two new parameters, **gidMin** and **gidMax**, are introduced with the dynamic provisioner. These values allow the administrator to configure the GID range for the volume in the storage class. To set up the GID values and provide volume security for dynamically provisioned volumes, execute the following commands:

1. Create a storage class file with the GID values. For example:

# cat glusterfs-storageclass.yaml

apiVersion: storage.k8s.io/v1

kind: StorageClass

metadata:

name: gluster-container

provisioner: kubernetes.io/glusterfs

parameters:

resturl: "http://heketi-storage-project.cloudapps.mystorage.com"

restuser: "admin"

secretNamespace: "default" secretName: "heketi-secret"

gidMin: "2000" gidMax: "4000"



## **NOTE**

If the **gidMin** and **gidMax** values are not provided, then the dynamic provisioned volumes will have the GID between 2000 and 2147483647.

- 2. Create a persistent volume claim. For more information see, Section 3.1.2.1.3, "Creating a Persistent Volume Claim"
- 3. Use the claim in the pod. Ensure that this pod is non-privileged. For more information see, Section 3.1.2.1.6, "Using the Claim in a Pod"
- 4. To verify if the GID is within the range specified, execute the following command:

# oc rsh busybox

\$ id

For example:

\$ id uid=1000060000 gid=0(root) groups=0(root),2001

where, 2001 in the above output is the allocated GID for the persistent volume, which is within the range specified in the storage class. You can write to this volume with the allocated GID.



#### **NOTE**

When the persistent volume claim is deleted, the GID of the persistent volume is released from the pool.

## 3.2. BLOCK STORAGE

Block storage allows the creation of high performance individual storage units. Unlike the traditional file storage capability that glusterfs supports, each storage volume/block device can be treated as an independent disk drive, so that each storage volume/block device can support an individual file system.

gluster-block is a distributed management framework for block devices. It aims to make Gluster-backed block storage creation and maintenance as simple as possible. gluster-block can provision block devices and export them as iSCSI LUN's across multiple nodes, and uses iSCSI protocol for data transfer as SCSI block/commands.



#### **NOTE**

- Block volume expansion is not supported in OpenShift Container Storage 3.11.
- Static provisioning of volumes is not supported for Block storage. Dynamic provisioning of volumes is the only method supported.
- The recommended Red Hat Enterprise Linux (RHEL) version for block storage is RHEL-7.5.4. Please ensure that your kernel version matches with 3.10.0-862.14.4.el7.x86 64. To verify execute:

# uname -r

Reboot the node for the latest kernel update to take effect.

## 3.2.1. Dynamic Provisioning of Volumes for Block Storage

Dynamic provisioning enables you to provision a Red Hat Gluster Storage volume to a running application container without pre-creating the volume. The volume will be created dynamically as the claim request comes in, and a volume of exactly the same size will be provisioned to the application containers.



#### **NOTE**

The steps outlined below are not necessary when OpenShift Container Storage was deployed using the (default) Ansible installer and the default storage class (glusterfs-storage-block) created during the installation will be used.

## 3.2.1.1. Configuring Dynamic Provisioning of Volumes

To configure dynamic provisioning of volumes, the administrator must define StorageClass objects that describe named "classes" of storage offered in a cluster. After creating a Storage Class, a secret for heketi authentication must be created before proceeding with the creation of persistent volume claim.

## 3.2.1.1.1. Configuring Multipathing on all Initiators

To ensure the iSCSI initiator can communicate with the iSCSI targets and achieve HA using multipathing, execute the following steps on all the OpenShift nodes (iSCSI initiator) where the app pods are hosted:

- 1. To install initiator related packages on all the nodes where initiator has to be configured, execute the following command:
  - # yum install iscsi-initiator-utils device-mapper-multipath
- 2. To enable multipath, execute the following command:
  - # mpathconf --enable
- 3. Create and add the following content to the multipath.conf file:



#### **NOTE**

In case of upgrades, make sure that the changes to multipath.conf and reloading of multipathd are done only after all the server nodes are upgraded.

4. Execute the following commands to start multipath daemon and [re]load the multipath configuration:

# systemctl start multipathd

# systemctl reload multipathd

## 3.2.1.1.2. Creating Secret for Heketi Authentication

To create a secret for Heketi authentication, execute the following commands:



#### NOTE

If the **admin-key** value (secret to access heketi to get the volume details) was not set during the deployment of Red Hat Openshift Container Storage, then the following steps can be omitted.

1. Create an encoded value for the password by executing the following command:

```
# echo -n "<key>" | base64
```

where key is the value for admin-key that was created while deploying CNS

For example:

```
# echo -n "mypassword" | base64
bXlwYXNzd29yZA==
```

2. Create a secret file. A sample secret file is provided below:

```
# cat glusterfs-secret.yaml
```

apiVersion: v1 kind: Secret metadata:

name: heketi-secret namespace: default

data:

# base64 encoded password. E.g.: echo -n "mypassword" | base64

key: bXlwYXNzd29yZA==
type: gluster.org/glusterblock

3. Register the secret on Openshift by executing the following command:

# oc create -f glusterfs-secret.yaml secret "heketi-secret" created

## 3.2.1.1.3. Registering a Storage Class

When configuring a StorageClass object for persistent volume provisioning, the administrator must describe the type of provisioner to use and the parameters that will be used by the provisioner when it provisions a PersistentVolume belonging to the class.

1. Create a storage class. A sample storage class file is presented below:

# cat > glusterfs-block-storageclass.yaml

apiVersion: storage.k8s.io/v1

kind: StorageClass

metadata:

name: gluster-block

provisioner: gluster.org/glusterblock-infra-storage

reclaimPolicy: Retain

parameters:

resturl: "http://heketi-storage-project.cloudapps.mystorage.com"

restuser: "admin"

restsecretnamespace: "default" restsecretname: "heketi-secret"

hacount: "3"

clusterids: "630372ccdc720a92c681fb928f27b53f,796e6db1981f369ea0340913eeea4c9a"

chapauthenabled: "true" volumenameprefix: "test-vol"

where,

## provisioner

The provisioner name should match the provisioner name with which the **glusterblock provisioner** pod was deployed. To get the **provisioner name** use the following command:

# oc describe pod <glusterblock\_provisioner\_pod\_name> |grep PROVISIONER\_NAME

For example:

# oc describe pod glusterblock-registry-provisioner-dc-1-5j8l9 |grep PROVISIONER\_NAME

PROVISIONER\_NAME: gluster.org/glusterblock-infra-storage

#### resturl

Gluster REST service/Heketi service url which provision gluster volumes on demand. The general format must be IPaddress:Port and this is a mandatory parameter for GlusterFS dynamic provisioner. If Heketi service is exposed as a routable service in openshift/kubernetes setup, this can have a format similar to http://heketi-storage-project.cloudapps.mystorage.com where the fqdn is a resolvable heketi service url.

#### restuser

Gluster REST service/Heketi user who has access to create volumes in the trusted storage pool

#### restsecretnamespace + restsecretname

Identification of Secret instance that contains user password to use when talking to Gluster REST service. These parameters are optional. Empty password will be used when both **restsecretnamespace** and **restsecretname** are omitted.

#### hacount

It is the count of the number of paths to the block target server. **hacount** provides high availability via multipathing capability of iSCSI. If there is a path failure, the I/Os will not be interrupted and will be served via another available paths.

## clusterids

It is the ID of the cluster which will be used by Heketi when provisioning the volume. It can also be a list of comma-separated cluster IDs. This is an optional parameter.



#### NOTE

To get the cluster ID, execute the following command:



## chapauthenabled

If you want to provision block volume with CHAP authentication enabled, this value has to be set to true. This is an optional parameter.

## volumenameprefix

This is an optional parameter. It depicts the name of the volume created by heketi. For more information see, Section 3.2.1.1.6, "(Optional) Providing a Custom Volume Name Prefix for Persistent Volumes"



#### **NOTE**

The value for this parameter cannot contain \_ in the storage lass.

2. To register the storage class to Openshift, execute the following command:

# oc create -f glusterfs-block-storageclass.yaml storageclass "gluster-block" created

3. To get the details of the storage class, execute the following command:

# oc describe storageclass gluster-block

Name: gluster-block

IsDefaultClass: No Annotations: <none>

Provisioner: gluster.org/glusterblock-infra-storage

Parameters: chapauthenabled=true,hacount=3,opmode=heketi,restsecretname=heketi-

secret,restsecretnamespace=default,resturl=http://heketi-storage-

project.cloudapps.mystorage.com,restuser=admin

Events: <none>

#### 3.2.1.1.4. Creating a Persistent Volume Claim

To create a persistent volume claim execute the following commands:

1. Create a Persistent Volume Claim file. A sample persistent volume claim is provided below:

# cat glusterfs-block-pvc-claim.yaml kind: PersistentVolumeClaim

apiVersion: v1 metadata: name: claim1 annotations:

volume.beta.kubernetes.io/storage-class: gluster-block

spec:

persistentVolumeReclaimPolicy: Retain

accessModes:

- ReadWriteOnce

resources: requests: storage: 5Gi

#### persistentVolumeReclaimPolicy

This is an optional parameter. When this parameter is set to "Retain" the underlying persistent volume is retained even after the corresponding persistent volume claim is deleted.



#### NOTE

When PVC is deleted, the underlying heketi and gluster volumes are not deleted if "persistentVolumeReclaimPolicy:" is set to "Retain". To delete the volume, you must use heketi cli and then delete the PV.

2. Register the claim by executing the following command:

# oc create -f glusterfs-block-pvc-claim.yaml persistentvolumeclaim "claim1" created

3. To get the details of the claim, execute the following command:

# oc describe pvc <\_claim\_name\_>

For example:

# oc describe pvc claim1

Name: claim1

Namespace: block-test StorageClass: gluster-block

Status: Bound

Volume: pvc-ee30ff43-7ddc-11e7-89da-5254002ec671

Labels: <none>

Annotations: control-plane.alpha.kubernetes.io/leader={"holderIdentity":"8d7fecb4-7dba-

11e7-a347-0a580a830002","leaseDurationSeconds":15,"acquireTime":"2017-08-

10T15:02:30Z","renewTime":"2017-08-10T15:02:58Z","lea...

pv.kubernetes.io/bind-completed=yes

pv.kubernetes.io/bound-by-controller=yes

volume.beta.kubernetes.io/storage-class=gluster-block

volume.beta.kubernetes.io/storage-provisioner=gluster.org/glusterblock

Capacity: 5Gi

Access Modes: RWO

Events:

FirstSeen LastSeen Count From SubObjectPath Type Reason

Message

...... ...... ..... .... .... ....

1m 1m 1 gluster.org/glusterblock 8d7fecb4-7dba-11e7-a347-0a580a830002 Normal Provisioning External provisioner is provisioning volume for claim "blocktest/claim1"

1m 1m 18 persistentvolume-controller Normal ExternalProvisioning cannot find provisioner "gluster.org/glusterblock", expecting that a volume for the claim is provisioned either manually or via external software

1m 1m 1 gluster.org/glusterblock 8d7fecb4-7dba-11e7-a347-0a580a830002

Normal ProvisioningSucceeded Successfully provisioned volume pvc-ee30ff43-7ddc-11e7-89da-5254002ec671

## 3.2.1.1.5. Verifying Claim Creation

To verify if the claim is created, execute the following commands:

1. To get the details of the persistent volume claim and persistent volume, execute the following command:

# oc get pv,pvc

NAME CAPACITY ACCESSMODES RECLAIMPOLICY
STATUS CLAIM STORAGECLASS REASON AGE
pv/pvc-ee30ff43-7ddc-11e7-89da-5254002ec671 5Gi RWO Delete Bound
block-test/claim1 gluster-block 3m

NAME STATUS VOLUME CAPACITY ACCESSMODES STORAGECLASS AGE pvc/claim1 Bound pvc-ee30ff43-7ddc-11e7-89da-5254002ec671 5Gi RWO gluster-block 4m

## 3.2.1.1.6. (Optional) Providing a Custom Volume Name Prefix for Persistent Volumes

You can provide a custom volume name prefix to the persistent volume that is created. By providing a custom volume name prefix, users can now easily search/filter the volumes based on:

- Any string that was provided as the field value of "volnameprefix" in the storageclass file.
- Persistent volume claim name.
- Project / Namespace name.

To set the name, ensure that you have added the parameter **volumenameprefix** to the storage class file. For more information, refer Section 3.2.1.1.3, "Registering a Storage Class"



#### **NOTE**

The value for this parameter cannot contain \_ in the storage class.

To verify if the custom volume name prefix is set, execute the following command:

# oc describe pv <pv\_name>

For example:

# oc describe pv pvc-4e97bd84-25f4-11e8-8f17-005056a55501 Name: pvc-4e97bd84-25f4-11e8-8f17-005056a55501

Labels: <none>

```
Annotations:
                 AccessKey=glusterblk-67d422eb-7b78-4059-9c21-a58e0eabe049-secret
            AccessKeyNs=glusterfs
            Blockstring=url:http://172.31.251.137:8080,user:admin,secret:heketi-
secret,secretnamespace:glusterfs
            Description=Gluster-external: Dynamically provisioned PV
            gluster.org/type=block
            gluster.org/volume-id=cd37c089372040eba20904fb60b8c33e
            glusterBlkProvIdentity=gluster.org/glusterblock
            glusterBlockShare=test-vol glusterfs bclaim1 4eab5a22-25f4-11e8-954d-
0a580a830003
            kubernetes.io/createdby=heketi
            pv.kubernetes.io/provisioned-by=gluster.org/glusterblock
            v2.0.0=v2.0.0
  StorageClass: gluster-block-prefix
  Status:
              Bound
  Claim:
              glusterfs/bclaim1
  Reclaim Policy: Delete
  Access Modes: RWO
  Capacity:
               5Gi
  Message:
  Source:
                  ISCSI (an ISCSI Disk resource that is attached to a kubelet's host machine and
    Type:
then exposed to the pod)
    TargetPortal:
                     10.70.46.177
    IQN:
                  iqn.2016-12.org.gluster-block:67d422eb-7b78-4059-9c21-a58e0eabe049
    Lun:
    ISCSIInterface
                     default
    FSType:
                    xfs
    ReadOnly:
                    false
    Portals:
                  [10.70.46.142 10.70.46.4]
    DiscoveryCHAPAuth: false
    SessionCHAPAuth: true
    SecretRef:
                    {glusterblk-67d422eb-7b78-4059-9c21-a58e0eabe049-secret }
    InitiatorName:
                     <none>
Events:
                 <none>
```

The value for **glusterBlockShare** will have the custom volume name prefix attached to the namespace and the claim name, which is "test-vol" in this case.

#### 3.2.1.1.7. Using the Claim in a Pod

Execute the following steps to use the claim in a pod.

1. To use the claim in the application, for example

```
# cat app.yaml

apiVersion: v1
kind: Pod
metadata:
name: busybox
spec:
containers:
- image: busybox
command:
- sleep
```

- "3600" name: busybox volumeMounts:

- mountPath: /usr/share/busybox

name: mypvc

volumes:

- name: mypvc

persistentVolumeClaim:

claimName: claim1

# oc create -f app.yaml pod "busybox" created

For more information about using the glusterfs claim in the application see, https://access.redhat.com/documentation/en-us/openshift\_container\_platform/3.11/html-single/configuring\_clusters/#install-config-storage-examples-gluster-example.

2. To verify that the pod is created, execute the following command:

# oc get pods -n storage-project

NIANAE	DEAD		DECTAR	TO 405
NAME	READ'	Y STATUS	RESTAF	RIS AGE
block-test-router-1-deplo	y 0.	/1 Running	0	4h
busybox	1/1	Running 0	43s	
glusterblock-provisioner-	1-bjpz4	1/1 Runni	ng 0	4h
glusterfs-7l5xf	1/1	Running 0	4h	
glusterfs-hhxtk	1/1	Running 3	4h	
glusterfs-m4rbc	1/1	Running 0	4h	
heketi-1-3h9nb	1/1	Running 0	4h	

3. To verify that the persistent volume is mounted inside the container, execute the following command:

# oc rsh busybox

```
/ # df -h
Filesystem
                 Size Used Available Use% Mounted on
/dev/mapper/docker-253:1-11438-
39febd9d64f3a3594fc11da83d6cbaf5caf32e758eb9e2d7bdd798752130de7e
            10.0G 33.9M
                            9.9G 0%/
tmpfs
               3.8G 0
                            3.8G 0% /dev
tmpfs
               3.8G
                      0 3.8G 0%/sys/fs/cgroup
/dev/mapper/VolGroup00-LogVol00
             7.7G 2.8G 4.5G 39% /dev/termination-log
/dev/mapper/VolGroup00-LogVol00
             7.7G
                   2.8G 4.5G 39% /run/secrets
/dev/mapper/VolGroup00-LogVol00
             7.7G
                    2.8G 4.5G 39% /etc/resolv.conf
/dev/mapper/VolGroup00-LogVol00
             7.7G
                    2.8G
                           4.5G 39% /etc/hostname
/dev/mapper/VolGroup00-LogVol00
            7.7G 2.8G
                           4.5G 39% /etc/hosts
              64.0M
                        0 64.0M 0% /dev/shm
shm
/dev/mpatha
                   5.0G 32.2M 5.0G 1% /usr/share/busybox
tmpfs
               3.8G 16.0K 3.8G 0% /var/run/secrets/kubernetes.io/serviceaccount
```

tmpfs	3.8G	0	3.8G	0% /proc/kcore
tmpfs	3.8G	0	3.8G	0% /proc/timer_list
tmpfs	3.8G	0	3.8G	0% /proc/timer_stats
tmpfs	3.8G	0	3.8G	0% /proc/sched_debug

## 3.2.1.1.8. Deleting a Persistent Volume Claim



#### NOTE

If the "persistentVolumeReclaimPolicy" parameter was set to "Retain" when registering the storageclass, the underlying PV and the corresponding volume remains even when a PVC is deleted.

1. To delete a claim, execute the following command:

# oc delete pvc <claim-name>

For example:

# oc delete pvc claim1
persistentvolumeclaim "claim1" deleted

2. To verify if the claim is deleted, execute the following command:

# oc get pvc <claim-name>

For example:

# oc get pvc claim1 No resources found.

When the user deletes a persistent volume claim that is bound to a persistent volume created by dynamic provisioning, apart from deleting the persistent volume claim, Kubernetes will also delete the persistent volume, endpoints, service, and the actual volume. Execute the following commands if this has to be verified:

To verify if the persistent volume is deleted, execute the following command:

# oc get pv <pv-name>

For example:

# oc get pv pvc-962aa6d1-bddb-11e6-be23-5254009fc65b No resources found.

Next step: If you are installing Red Hat Openshift Container Storage 3.11, and you want to use block storage as the backend storage for logging and metrics, proceed to Chapter 7, *Gluster Block Storage as Backend for Logging and Metrics*.

## 3.2.2. Replacing a Block on Block Storage

If you want to replace a block from a node that is out of resource or is faulty, it can be replaced to a new node.

Execute the following commands:

1. Execute the following command to fetch the zone and cluster info from heketi

# heketi-cli topology info --user=<user> --secret=<user key>

--user

heketi user

--secret

Secret key for a specified user

2. After obtaining the cluster id and zone id add a new node to heketi by executing the following command:



#### NOTE

Before adding the node, ensure the node is labeled as a glusterfs storage host by adding the label "glusterfs=storage-host", using the following command;

# oc label node <NODENAME> glusterfs=storage-host

# heketi-cli node add --zone=<zoneid> --cluster=<clusterid> --management-host-name= <new hostname> --storage-host-name=<new node ip> --user=<user> --secret=<user key>

#### --cluster

The cluster in which the node should reside

--management-host-name

Management hostname. This is the new node that has to be added.

--storage-host-name

Storage hostname.

--zone

The zone in which the node should reside

--user

heketi user.

--secret

Secret key for a specified user

For example:

heketi-cli node add --zone=1 --cluster=607204cb27346a221f39887a97cf3f90 --management-host-name=dhcp43-241.lab.eng.blr.redhat.com --storage-host-name=10.70.43.241 -- user=admin --secret=adminkey

Node information:

ld: 2639c473a2805f6e19d45997bb18cb9c

State: online

Cluster Id: 607204cb27346a221f39887a97cf3f90

Zone: 1

Management Hostname dhcp43-241.lab.eng.blr.redhat.com

Storage Hostname 10.70.43.241

3. Execute the following command to add the device

# heketi-cli device add --name=<device name> --node=<node id> --user=<user> --secret= <user key>

#### --name

Name of device to add

#### --node

Newly added node id

#### For example:

# heketi-cli device add --name=/dev/vdc --node=2639c473a2805f6e19d45997bb18cb9c --user=admin --secret=adminkey

Device added successfully

4. After the new node and its associated devices are added to heketi, the faulty or unwanted node can be removed from heketi

To remove any node from heketi, follow this workflow:

- node disable (Disallow usage of a node by placing it offline)
- node replace (Removes a node and all its associated devices from Heketi)
- device delete (Deletes a device from Heketi node)
- node delete (Deletes a node from Heketi management)
- 5. Execute the following command to fetch the node list from heketi

#heketi-cli node list --user=<user> --secret=<user key>

#### For example:

6. Execute the following command to fetch the node info of the node, that has to be deleted from heketi:

# heketi-cli node info <nodeid> --user=<user> --secret=<user key>

For example:

# heketi-cli node info c513da1f9bda528a9fd6da7cb546a1ee --user=admin --

secret=adminkey

Node ld: c513da1f9bda528a9fd6da7cb546a1ee

State: online

Cluster Id: 607204cb27346a221f39887a97cf3f90

Zone: 1

Management Hostname: dhcp43-171.lab.eng.blr.redhat.com

Storage Hostname: 10.70.43.171

Devices:

ld:3a1e0717e6352a8830ab43978347a103 Name:/dev/vdc

State:online Size

(GiB):499 Used (GiB):100 Free (GiB):399 Bricks:1

ld:89a57ace1c3184826e1317fef785e6b7 Name:/dev/vdd (GiB):499 Used (GiB):10 Free (GiB):489 Bricks:5 State:online Size

7. Execute the following command to disable the node from heketi. This makes the node go offline:

# heketi-cli node disable <node-id> --user=<user> --secret=<user key>

For example:

# heketi-cli node disable ab37fc5aabbd714eb8b09c9a868163df --user=admin -- secret=adminkey

Node ab37fc5aabbd714eb8b09c9a868163df is now offline

8. Execute the following command to remove a node and all its associated devices from Heketi:

#heketi-cli node remove <node-id> --user=<user> --secret=<user key>

For example:

# heketi-cli node remove ab37fc5aabbd714eb8b09c9a868163df --user=admin --secret=adminkey

Node ab37fc5aabbd714eb8b09c9a868163df is now removed

9. Execute the following command to delete the devices from heketi node:

# heketi-cli device delete <device-id> --user=<user> --secret=<user key>

For example:

# heketi-cli device delete 0fca78c3a94faabfbe5a5a9eef01b99c --user=admin -- secret=adminkey

Device 0fca78c3a94faabfbe5a5a9eef01b99c deleted

10. Execute the following command to delete a node from Heketi management:

#heketi-cli node delete <nodeid> --user=<user> --secret=<user key>

For example:

# heketi-cli node delete ab37fc5aabbd714eb8b09c9a868163df --user=admin -- secret=adminkey

Node ab37fc5aabbd714eb8b09c9a868163df deleted

- 11. Execute the following commands on any one of the gluster pods to replace the faulty node with the new node:
  - a. Execute the following command to get list of blockvolumes hosted under block-hosting-volume
    - # gluster-block list <block-hosting-volume> --json-pretty
  - b. Execute the following command to find out which all blockvolumes are hosted on the old node, with the help of info command
    - # gluster-block info <block-hosting-volume>/<block-volume> --json-pretty
  - c. Execute the following command to replace the faulty node with the new node:
    - # gluster-block replace <volname/blockname> <old-node> <new-node> [force]

For example:

```
{
  "NAME":"block",
  "CREATE SUCCESS":"192.168.124.73",
  "DELETE SUCCESS":"192.168.124.63",
  "REPLACE PORTAL SUCCESS ON":[
  "192.168.124.79"
  ],
  "RESULT":"SUCCESS"
}

Note: If the old node is down and does not come up again then you can force replace: gluster-block replace sample/block 192.168.124.63 192.168.124.73 force --json-pretty

{
  "NAME":"block",
  "CREATE SUCCESS":"192.168.124.73",
  "DELETE FAILED (ignored)":"192.168.124.63",
  "REPLACE PORTAL SUCCESS ON":[
  "192.168.124.79"
  ],
  "RESULT":"SUCCESS"
}
```



#### **NOTE**

The next steps henceforth are to be executed only if the block that is to be replaced is still in use.

12. Logout of the old portal by executing the following command on the initiator:

# iscsiadm -m node -T <targetname> -p <old node> -u

For example:

# iscsiadm -m node -T iqn.2016-12.org.gluster-block:d6d18f43-8a74-4b2c-a5b7-df1fa3f5bc9a -p 192.168.124.63 -u

Logging out of session [sid: 8, target: iqn.2016-12.org.gluster-block:d6d18f43-8a74-4b2c-a5b7-df1fa3f5bc9a, portal: 192.168.124.63,3260]

Logout of [sid: 8, target: iqn.2016-12.org.gluster-block:d6d18f43-8a74-4b2c-a5b7-

df1fa3f5bc9a, portal: 192.168.124.63,3260] successful.

13. To re-discover the new node execute the following command:

# iscsiadm -m discovery -t st -p <new node>

For example:

# iscsiadm -m discovery -t st -p 192.168.124.73 192.168.124.79:3260,1 iqn.2016-12.org.gluster-block:d6d18f43-8a74-4b2c-a5b7-df1fa3f5bc9a 192.168.124.73:3260,2 iqn.2016-12.org.gluster-block:d6d18f43-8a74-4b2c-a5b7-df1fa3f5bc9a

14. Login to the new portal by executing the following command:

# iscsiadm -m node -T <targetname> -p <new node ip> -l

For example:

# iscsiadm -m node -T iqn.2016-12.org.gluster-block:d6d18f43-8a74-4b2c-a5b7-df1fa3f5bc9a -p 192.168.124.73 -l

15. To verify if the enabled hosting volume is replaced and running successfully, execute the following command on the initiator:

# II /dev/disk/by-path/ip-\* | grep <targetname> | grep <"new node ip">

# CHAPTER 4. SHUTTING DOWN GLUSTER-BLOCK CLIENT NODES

Follow this procedure to shutdown gluster-block client nodes:

- 1. Evacuate the pods. For more information, refer https://access.redhat.com/documentation/en-us/openshift\_container\_platform/3.11/html-single/cluster\_administration/#evacuating-pods-on-nodes
- 2. Ensure that no gluster block mounts exist in the system.
- 3. Reboot the nodes. For more information, refer https://access.redhat.com/documentation/enus/openshift\_container\_platform/3.11/html-single/cluster\_administration/#rebooting-nodes

# CHAPTER 5. S3 COMPATIBLE OBJECT STORE IN A RED HAT OPENSHIFT CONTAINER STORAGE ENVIRONMENT



#### **IMPORTANT**

Support for S3 compatible Object Store in Container-Native Storage is under technology preview. Technology Preview features are not fully supported under Red Hat service-level agreements (SLAs), may not be functionally complete, and are not intended for production use.

Tech Preview features provide early access to upcoming product innovations, enabling customers to test functionality and provide feedback during the development process.

As Red Hat considers making future iterations of Technology Preview features generally available, we will provide commercially reasonable efforts to resolve any reported issues that customers experience when using these features.

Object Store provides a system for data storage that enables users to access the same data, both as an object and as a file, thus simplifying management and controlling storage costs. The S3 API is the de facto standard for HTTP based access to object storage services.

# 5.1. SETTING UP S3 COMPATIBLE OBJECT STORE FOR RED HAT OPENSHIFT CONTAINER STORAGE



#### **NOTE**

Ensure that cns-deploy package has been installed before setting up S3 Compatible Object Store. For more information on how to install cns-deploy package, see https://access.redhat.com/documentation/en-us/red\_hat\_openshift\_container\_storage/3.11/html-single/deployment\_guide/#part-Appendix

Execute the following steps from the /usr/share/heketi/templates/ directory to set up S3 compatible object store for Red Hat Openshift Container Storage:

1. (Optional): If you want to create a secret for heketi, then execute the following command:

# oc create secret generic heketi-\${NAMESPACE}-admin-secret --from-literal=key=\${ADMIN\_KEY} --type=kubernetes.io/glusterfs

For example:

# oc create secret generic heketi-storage-project-admin-secret --from-literal=key=abcd --type=kubernetes.io/glusterfs

a. Execute the following command to label the secret:

# oc label --overwrite secret heketi-\${NAMESPACE}-admin-secret glusterfs=s3-heketi-\${NAMESPACE}-admin-secret gluster-s3=heketi-\${NAMESPACE}-admin-secret

For example:

# oc label --overwrite secret heketi-storage-project-admin-secret glusterfs=s3-heketi-storage-project-admin-secret gluster-s3=heketi-storage-project-admin-secret

2. Create a GlusterFS StorageClass file. Use the **HEKETI\_URL** and **NAMESPACE** from the current setup and set a **STORAGE\_CLASS** name.

# sed -e 's/\${HEKETI\_URL}/<HEKETI\_URL>/g' -e 's/\${STORAGE\_CLASS}/<STORAGE\_CLASSNAME>/g' -e 's/\${NAMESPACE}/<NAMESPACE\_NAME>/g' /usr/share/heketi/templates/gluster-s3-storageclass.yaml | oc create -f -

For example:

# sed -e 's/\${HEKETI\_URL}/heketi-storage-project.cloudapps.mystorage.com/g' -e 's/\${STORAGE\_CLASS}/gluster-s3-store/g' -e 's/\${NAMESPACE}/storage-project/g' /usr/share/heketi/templates/gluster-s3-storageclass.yaml | oc create -f -storageclass "gluster-s3-store" created



You can run the following command to obtain the HEKETI\_URL:

# oc get routes --all-namespaces | grep heketi

A sample output of the command is as follows:

glusterfs heketi-storage heketi-storage-glusterfs.router.default.svc.cluster.local heketi-storage <all> None

If there are multiple lines in the output then you can choose the most relevant one.

You can run the following command to obtain the NAMESPACE:

oc get project

A sample output of the command is as follows:

# oc project
Using project "glusterfs" on server "master.example.com:8443"

where, glusterfs is the NAMESPACE.

3. Create the Persistent Volume Claims using the storage class.

# sed -e 's/\${VOLUME\_CAPACITY}/<NEW SIZE in Gi>/g' -e 's/\${STORAGE\_CLASS}/<STORAGE\_CLASSNAME>/g' /usr/share/heketi/templates/gluster-s3-pvcs.yaml | oc create -f -

For example:

# sed -e 's/\${VOLUME\_CAPACITY}/2Gi/g' -e 's/\${STORAGE\_CLASS}/gluster-s3-store/g' /usr/share/heketi/templates/gluster-s3-pvcs.yaml | oc create -f - persistentvolumeclaim "gluster-s3-claim" created persistentvolumeclaim "gluster-s3-meta-claim" created

Use the **STORAGE\_CLASS** created from the previous step. Modify the **VOLUME\_CAPACITY** as per the environment requirements. Wait till the PVC is bound. Verify the same using the following command:

# oc get pvc
NAME STATUS VOLUME CAPACITY
ACCESSMODES AGE
gluster-s3-claim Bound pvc-0b7f75ef-9920-11e7-9309-00151e000016 2Gi RWX
2m
gluster-s3-meta-claim Bound pvc-0b87a698-9920-11e7-9309-00151e000016 1Gi
RWX 2m

 Start the glusters3 object storage service using the template. Set the S3\_ACCOUNT name, S3\_USER name, and S3\_PASSWORD. PVC and META\_PVC are obtained from the previous step.

# oc new-app /usr/share/heketi/templates/gluster-s3-template.yaml \

- --param=S3\_ACCOUNT=testvolume --param=S3\_USER=adminuser \
- --param=S3\_PASSWORD=itsmine --param=PVC=gluster-s3-claim \
- --param=META\_PVC=gluster-s3-meta-claim
- --> Deploying template "storage-project/gluster-s3" for "/usr/share/heketi/templates/gluster-s3-template.yaml" to project storage-project

gluster-s3

Gluster s3 service template

- \* With parameters:
  - \* S3 Account Name=testvolume
  - \* S3 User=adminuser
  - \* S3 User Password=itsmine
  - \* Primary GlusterFS-backed PVC=gluster-s3-claim
  - \* Metadata GlusterFS-backed PVC=gluster-s3-meta-claim
- --> Creating resources ...
  service "gluster-s3-service" created
  route "gluster-s3-route" created
  deploymentconfig "gluster-s3-dc" created
  --> Success
  Run 'oc status' to view your app.
- 5. Execute the following command to verify if the S3 pod is up:

# oc get pods -o wide
NAME READY STATUS RESTARTS AGE IP NODE
gluster-s3-azkys 1/1 Running 0 4m 10.130.0.29 node3
...

#### 5.2. OBJECT OPERATIONS

This section lists some of the object operation that can be performed:

• Get the URL of the route which provides S3 OS

# s3\_storage\_url=\$(oc get routes | grep "gluster.\*s3" | awk '{print \$2}')



#### **NOTE**

Ensure to download the s3curl tool from https://aws.amazon.com/code/128. This tool will be used for verifying the object operations.

 s3curl.pl requires Digest::HMAC\_SHA1 and Digest::MD5. Install the perl-Digest-HMAC package to get this. You can install the perl-Digest-HMAC package by running this command:

# yum install perl-Digest-HMAC

• Update the s3curl.pl perl script with glusters3object url which was retrieved: For example:

my @endpoints = ( 'glusters3object-storageproject.cloudapps.mystorage.com');

• To perform **PUT** operation of the bucket:

s3curl.pl --debug --id "testvolume:adminuser" --key "itsmine" --put /dev/null -- -k -v http://\$s3\_storage\_url/bucket1

• To perform **PUT** operation of the object inside the bucket:

s3curl.pl --debug --id "testvolume:adminuser" --key "itsmine" --put my\_object.jpg -- -k -v -s http://\$s3\_storage\_url/bucket1/my\_object.jpg

• To verify listing of objects in the bucket:

s3curl.pl --debug --id "testvolume:adminuser" --key "itsmine" -- -k -v -s http://\$s3\_storage\_url/bucket1/

#### **CHAPTER 6. CLUSTER ADMINISTRATOR SETUP**

#### Authentication

Set up the authentication using AllowAll Authentication method.

#### AllowAll Authentication

Set up an authentication model which allows all passwords. Edit /etc/origin/master/master-config.yaml on the OpenShift master and change the value of DenyAllPasswordIdentityProvider to AllowAllPasswordIdentityProvider. Then restart the OpenShift master.

- 1. Now that the authentication model has been setup, login as a user, for example admin/admin:
  - # oc login openshift master e.g. https://1.1.1.1:8443 --username=admin --password=admin
- 2. Grant the admin user account the cluster-admin role.

# oc login -u system:admin -n default Logged into "https:// <<openshift\_master\_fqdn>>:8443" as "system:admin" using existing credentials.

\*default
glusterfs
infra-storage
kube-public
kube-system
management-infra
openshift
openshift-infra
openshift-logging
openshift-node
openshift-sdn
openshift-web-console

Using project "default".

# oc adm policy add-cluster-role-to-user cluster-admin admin cluster role "cluster-admin" added: "admin"

For more information on authentication methods, see https://access.redhat.com/documentation/en-us/openshift\_container\_platform/3.11/html-single/configuring\_clusters/#identity-providers-configuring.

# CHAPTER 7. GLUSTER BLOCK STORAGE AS BACKEND FOR LOGGING AND METRICS

Following section guides to configure Gluster Block Storage as the backend storage for logging and metrics



#### NOTE

Block volume expansion is not supported in OCS 3.11. Administrators are required to do proper capacity planning while using Gluster Block as backend storage when using dynamic provisioning.

#### 7.1. PREREQUISITES

Before setting gluster block storage as the backend for logging or metrics, check if the following prerequisites are met:

• In the storage class file, check if the default storage class is set to the storage class of gluster block. For example:

# oc get storageclass
NAME TYPE
gluster-block gluster.org/glusterblock

• If the default is not set to **gluster-block** (or any other name that you have provided) then execute the following command. For example:

# oc patch storageclass gluster-block -p '{"metadata": {"annotations": {"storageclass.kubernetes.io/is-default-class":"true"}}}'

• Execute the following command to verify:

oc get storageclass
NAME TYPE
gluster-block (default) gluster.org/glusterblock

## 7.2. ENABLING GLUSTER BLOCK STORAGE AS BACKEND FOR LOGGING

Follow the tasks mentioned below to enable Gluster Block Storage as backend for logging:

- 1. To enable logging in Openshift Container platform, see https://access.redhat.com/documentation/en-us/openshift\_container\_platform/3.11/html-single/configuring\_clusters/#install-config-aggregate-logging
- 2. The **openshift\_logging\_es\_pvc\_dynamic** ansible variable has to be set to true.

[OSEv3:vars] openshift\_logging\_es\_pvc\_dynamic=true

For example, a sample set of variables for openshift\_logging\_ are listed below.

openshift\_logging\_install\_logging=true

```
openshift_logging_es_pvc_dynamic=true openshift_logging_kibana_nodeselector={"node-role.kubernetes.io/infra": "true"} openshift_logging_curator_nodeselector={"node-role.kubernetes.io/infra": "true"} openshift_logging_es_nodeselector={"node-role.kubernetes.io/infra": "true"} openshift_logging_es_pvc_size=10Gi openshift_logging_es_pvc_storage_class_name="glusterfs-registry-block"
```

- 3. Run the Ansible playbook. For more information, see .https://access.redhat.com/documentation/en-us/openshift\_container\_platform/3.11/html-single/configuring\_clusters/#install-config-aggregate-logging
- 4. To verify, execute the following command:

# oc get pods -n openshift-logging



#### NOTE

For more information regarding logging storage considerations, see https://access.redhat.com/documentation/en-us/openshift\_container\_platform/3.11/html-single/configuring\_clusters/#install-configaggregate-logging-sizing-guidelines-storage.

### 7.3. ENABLING GLUSTER BLOCK STORAGE AS BACKEND FOR METRICS

Follow the tasks mentioned below to enable Gluster Block Storage as backend for metrics



#### **NOTE**

By default, since Container Native Storage performs three-way replication, data will be available to the restarted node from anywhere in the cluster. As a result, it is recommended that Cassandra-level replication is turned off to avoid capacity overhead

- 1. To enable metrics in Openshift Container platform, see https://access.redhat.com/documentation/en-us/openshift\_container\_platform/3.11/html-single/configuring\_clusters/#install-config-cluster-metrics
- 2. The **openshift\_metrics\_cassandra\_storage\_type** ansible variable should be set to **dynamic**:

[OSEv3:vars]openshift\_metrics\_cassandra\_storage\_type=dynamic

For example, a sample set of variables for openshift\_metrics\_ are listed below.

openshift\_metrics\_install\_metrics=true openshift\_metrics\_storage\_kind=dynamic openshift\_metrics\_hawkular\_nodeselector={"node-role.kubernetes.io/infra": "true"} openshift\_metrics\_cassandra\_nodeselector={"node-role.kubernetes.io/infra": "true"} openshift\_metrics\_heapster\_nodeselector={"node-role.kubernetes.io/infra": "true"} openshift\_metrics\_storage\_volume\_size=10Gi openshift\_metrics\_cassandra\_pvc\_storage\_class\_name="glusterfs-registry-block"

- 3. Run the Ansible playbook. For more information, see https://access.redhat.com/documentation/en-us/openshift\_container\_platform/3.11/html-single/configuring\_clusters/#install-config-cluster-metrics.
- 4. To verify, execute the following command:

# oc get pods --namespace openshift-infra

It should list the following pods running:

heapster-cassandra heapster-metrics hawkular-&\*9



#### **NOTE**

For more information regarding metrics storage considerations, see https://access.redhat.com/documentation/en-us/openshift\_container\_platform/3.11/html-single/configuring\_clusters/#metrics-data-storage.

#### 7.4. VERIFYING IF GLUSTER BLOCK IS SETUP AS BACKEND

Execute the following commands to verify if gluster block is setup as the backend for logging and metrics:

- 1. To get an overview of the infrastructure, execute the following command:
- 2. To get the details of all the persistent volume claims, execute the following command:
  - # oc get pvc
- 3. To get the details of the pvc, execute the following command:
  - # oc describe pvc <claim\_name>

Verify the volume is mountable and that permissions allow read/write. Also, PVC claim name should match the dynamically provisioned gluster block storage class.

For more information, see https://access.redhat.com/documentation/en-us/openshift\_container\_platform/3.11/html-single/configuring\_clusters/#install-configaggregate-logging-sizing.

### PART III. SECURITY

#### CHAPTER 8. ENABLING ENCRYPTION

Red Hat Gluster Storage supports network encryption using TLS/SSL. Red Hat Gluster Storage uses TLS/SSL for authentication and authorization, in place of the home grown authentication framework used for normal connections. Red Hat Gluster Storage supports the following encryption types:

- I/O encryption encryption of the I/O connections between the Red Hat Gluster Storage clients and servers.
- Management encryption encryption of the management (glusterd) connections within a trusted storage pool.

#### 8.1. PREREQUISITES

To enable encryption it is necessary to have 3 certificates per node (glusterfs.key, gluserfs.pem and glusterfs.ca). For more information about the steps to be performed as prerequisites, see https://access.redhat.com/documentation/en-us/red\_hat\_gluster\_storage/3.5/html-single/administration\_guide/index#chap-Network\_Encryption-Preparing\_Certificates.

Ensure to enable encryption while registering the storageclass file using the volumeoptions parameter. For more information on registering a storageclass file for File storage, see https://access.redhat.com/documentation/en-us/red\_hat\_openshift\_container\_storage/3.11/html-single/operations\_guide/index#chap-Documentation-Red\_Hat\_Gluster\_Storage\_Container\_Native\_with\_OpenShift\_Platform-OpenShift\_Creating\_Persistent\_Volumes-Dynamic\_Prov.



#### **NOTE**

- Ensure to perform the steps on all the OpenShift nodes except master.
- All the Red Hat Gluster Storage volumes are mounted on the OpenShift nodes and then bind mounted to the application pods. Hence, it is not required to perform any encryption related operations specifically on the application pods.

### 8.2. ENABLING ENCRYPTION FOR A NEW RED HAT OPENSHIFT CONTAINER STORAGE SETUP

You can configure network encryption for a new Red Hat Openshift Container Storage setup for both I/O encryption and management encryption.

#### 8.2.1. Enabling Management Encryption

Though Red Hat Gluster Storage can be configured only for I/O encryption without using management encryption, it is recommended to have management encryption. If you want to enable SSL only on the I/O path, skip this section and proceed with Section 8.2.2, "Enabling I/O encryption for a Volume".

#### On the server

Perform the following on all the server, ie, the OpenShift nodes on which Red Hat Gluster Storage pods are running.


1. Create the /var/lib/glusterd/secure-access file.

# touch /var/lib/glusterd/secure-access

#### On the clients

Perform the following on the clients, that is, on all the remaining OpenShift nodes on which Red Hat Gluster Storage is not running.

1. Create the /var/lib/glusterd/secure-access file.





#### **NOTE**

All the Red Hat Gluster Storage volumes are mounted on the OpenShift nodes and then bind mounted to the application pods. Hence, it is not required to perform any encryption related operations specifically on the application pods.

After running the commands on the server and clients, deploy Red Hat Openshift Container Storage. For more information, see https://access.redhat.com/documentation/en-us/red\_hat\_openshift\_container\_storage/3.11/html-single/deployment\_guide/#chap-Documentation-Red\_Hat\_Gluster\_Storage\_Container\_Native\_with\_OpenShift\_Platform-Setting\_the\_environment-Deploy\_CNS.

#### 8.2.2. Enabling I/O encryption for a Volume

Enable the I/O encryption between the servers and clients:



#### NOTE

The servers are the OpenShift nodes on which Red Hat Gluster Storage pods are running.

The clients are the remaining OpenShift nodes on which Red Hat Gluster Storage is not running.

- Ensure Red Hat Openshift Container Storage is deployed before proceeding with further steps.
   For more information see, https://access.redhat.com/documentation/en us/red\_hat\_openshift\_container\_storage/3.11/html-single/deployment\_guide/#chap Documentation-Red\_Hat\_Gluster\_Storage\_Container\_Native\_with\_OpenShift\_Platform Setting\_the\_environment-Deploy\_CNS
- 2. You can either create a statically provisioned volume or a dynamically provisioned volume. For more information about static provisioning of volumes, see https://access.redhat.com/documentation/en-us/red\_hat\_openshift\_container\_storage/3.11/html-single/operations\_guide/#chap-Documentation-Red\_Hat\_Gluster\_Storage\_Container\_Native\_with\_OpenShift\_Platform-OpenShift\_Creating\_Persistent\_Volumes-Static\_Prov. For more information about dynamic provisioning of volumes, see https://access.redhat.com/documentation/en-us/red\_hat\_openshift\_container\_storage/3.11/html-single/operations\_guide/#chap-Documentation-Red\_Hat\_Gluster\_Storage\_Container\_Native\_with\_OpenShift\_Platform-OpenShift\_Creating\_Persistent\_Volumes-Dynamic\_Prov



To enable encryption during the creation of statically provisioned volume, execute the following command:

# heketi-cli volume create --size=100 --gluster-volume-options="client.ssl on", "server.ssl on"

3. Stop the volume by executing the following command:

# oc rsh <gluster\_pod\_name> gluster volume stop VOLNAME

The *gluster pod name* is the name of one of the Red Hat Gluster Storage pods of the trusted storage pool to which the volume belongs.



#### NOTE

To get the VOLNAME, execute the following command:

# oc describe pv <pv\_name>

For example:

# oc describe pv pvc-01569c5c-1ec9-11e7-a794-005056b38171 Name: pvc-01569c5c-1ec9-11e7-a794-005056b38171

Labels: <none>
StorageClass: fast
Status: Bound

Claim: storage-project/storage-claim68

Reclaim Policy: Delete Access Modes: RWO Capacity: 1Gi

Message: Source:

Type: Glusterfs (a Glusterfs mount on the host that shares a pod's

lifetime)

EndpointsName: glusterfs-dynamic-storage-claim68
Path: vol\_0e81e5d6e46dcbf02c11ffd9721fca28

ReadOnly: false

No events.

The VOLNAME is the value of "path" in the above output.

4. Set the list of common names of all the servers to access the volume. Ensure to include the common names of clients which will be allowed to access the volume.

# oc rsh <gluster\_pod\_name> gluster volume set VOLNAME auth.ssl-allow 'server1,server2,server3,client1,client2,client3'



If you set auth.ssl-allow option with \* as value, any TLS authenticated clients can mount and access the volume from the application side. Hence, you set the option's value to \* or provide common names of clients as well as the nodes in the trusted storage pool.

5. Enable the client.ssl and server.ssl options on the volume.

# oc rsh <gluster\_pod\_name> gluster volume set VOLNAME client.ssl on # oc rsh <gluster\_pod\_name> gluster volume set VOLNAME server.ssl on

6. Start the volume.

# oc rsh <gluster\_pod\_name> gluster volume start VOLNAME

### 8.3. ENABLING ENCRYPTION FOR AN EXISTING RED HAT OPENSHIFT CONTAINER STORAGE SETUP

You can configure network encryption for an existing Red Hat Openshift Container Storage Storage setup for both I/O encryption and management encryption.

#### 8.3.1. Enabling I/O encryption for a Volume

Enable the I/O encryption between the servers and clients for a volume:



#### **NOTE**

The servers are the OpenShift nodes on which Red Hat Gluster Storage pods are running.

The clients are the remaining OpenShift nodes on which Red Hat Gluster Storage is not running.

- 1. Stop all the application pods that have the Red Hat Gluster Storage volumes.
- 2. Stop the volume.

# oc rsh <gluster\_pod\_name> gluster volume stop VOLNAME

The *gluster pod name* is the name of one of the Red Hat Gluster Storage pods of the trusted storage pool to which the volume belongs.

3. Set the list of common names for clients allowed to access the volume. Be sure to include the common names of all the servers.

# oc rsh <gluster\_pod\_name> gluster volume set VOLNAME auth.ssl-allow 'server1,server2,server3,client1,client2,client3'



If you set auth.ssl-allow option with \* as value, any TLS authenticated clients can mount and access the volume from the application side. Hence, you set the option's value to \* or provide common names of clients as well as the nodes in the trusted storage pool.

4. Enable client.ssl and server.ssl on the volume by using the following command:

# oc rsh <gluster\_pod\_name> gluster volume set VOLNAME client.ssl on # oc rsh <gluster\_pod\_name> gluster volume set VOLNAME server.ssl on

5. Start the volume.

# oc rsh <gluster\_pod\_name> gluster volume start VOLNAME

6. Start the application pods to use the I/O encrypted Red Hat Gluster Storage volumes.

#### 8.3.2. Enabling Management Encryption

Management encryption is recommended, even though, Red Hat Gluster Storage can be configured only for I/O encryption without using management encryption. On an existing installation, with running servers and clients, schedule a downtime of volumes, applications, clients, and other end-users to enable management encryption.

You cannot currently change between unencrypted and encrypted connections dynamically. Bricks and other local services on the servers and clients do not receive notifications from glusterd if they are running when the switch to management encryption is made.

- 1. Stop all the application pods that have the Red Hat Gluster Storage volumes.
- 2. Stop all the volumes.

# oc rsh <gluster\_pod\_name> gluster volume stop VOLNAME

3. Stop the Red Hat Gluster Storage pods.

# oc delete daemonset glusterfs-storage

- 4. On deletion of daemon set the pods go down. To verify if the pods are down, execute the following command:
  - # oc get pods
- 5. Create the /var/lib/glusterd/secure-access file on all OpenShift nodes.
  - # touch /var/lib/glusterd/secure-access
- 6. Create the Red Hat Gluster Storage daemonset by executing the following command:



For Ansible deployments, the image name and the version has to be specified in the template, before executing the command.

# oc process glusterfs | oc create -f -

- 7. On creation of daemon set the pods are started. To verify if the pods are started, execute the following command:
  - # oc get pods
- 8. Start all the volumes.
  - # oc rsh <gluster\_pod\_name> gluster volume start VOLNAME
- 9. Start the application pods to use the management encrypted Red Hat Gluster Storage.

#### 8.4. DISABLING ENCRYPTION

You can disable encryption for on Red Hat Openshift Container Storage setup in the following two scenarios:

- Disabling I/O Encryption for a Volume
- Disabling Management Encryption

#### 8.4.1. Disabling I/O Encryption for all the Volumes

Execute the following commands to disable the I/O encryption between the servers and clients for a volume:



#### NOTE

The servers are the OpenShift nodes on which Red Hat Gluster Storage pods are running.

The clients are the remaining OpenShift nodes on which Red Hat Gluster Storage is not running.

- 1. Stop all the application pods that have the Red Hat Gluster Storage volumes.
- 2. Stop all the volumes.
  - # oc rsh <gluster\_pod\_name> gluster volume stop VOLNAME
- 3. Reset all the encryption options for a volume:

```
# oc rsh <gluster_pod_name> gluster volume reset VOLNAME auth.ssl-allow
# oc rsh <gluster_pod_name> gluster volume reset VOLNAME client.ssl
# oc rsh <gluster_pod_name> gluster volume reset VOLNAME server.ssl
```

4. Delete the files that were used for network encryption using the following command on all the OpenShift nodes:

# rm /etc/ssl/glusterfs.pem /etc/ssl/glusterfs.key /etc/ssl/glusterfs.ca



#### **NOTE**

Deleting these files in a setup where management encryption is enabled will result in glusterd failing on all gluster pods and hence should be avoided.

- 5. Stop the Red Hat Gluster Storage pods.
  - # oc delete daemonset glusterfs
- 6. On deletion of daemon set the pods go down. To verify if the pods are down, execute the following command:
  - # oc get pods
- 7. Create the Red Hat Gluster Storage daemonset by executing the following command:



#### **NOTE**

For Ansible deployments, the image name and the version has to be specified in the template, before executing the command.

- # oc process glusterfs | oc create -f -
- 8. On creation of daemon set the pods are started. To verify if the pods are started, execute the following command:
  - # oc get pods
- 9. Start the volume.
  - # oc rsh <gluster\_pod\_name> gluster volume start VOLNAME
- 10. Start the application pods to use the I/O encrypted Red Hat Gluster Storage volumes.

#### 8.4.2. Disabling Management Encryption

You cannot currently change between unencrypted and encrypted connections dynamically. Bricks and other local services on the servers and clients do not receive notifications from glusterd if they are running when the switch to management encryption is made.

Execute the following commands to disable the management encryption

- 1. Stop all the application pods that have the Red Hat Gluster Storage volumes.
- 2. Stop all the volumes.
  - # oc rsh <gluster pod name> gluster volume stop VOLNAME

- 3. Stop the Red Hat Gluster Storage pods.
  - # oc delete daemonset glusterfs
- 4. On deletion of daemon set the pods go down. To verify if the pods are down, execute the following command:
  - # oc get pods
- 5. Delete the /var/lib/glusterd/secure-access file on all OpenShift nodes to disable management encryption.
  - # rm /var/lib/glusterd/secure-access
- 6. Delete the files that were used for network encryption using the following command on all the OpenShift nodes:
  - # rm /etc/ssl/glusterfs.pem /etc/ssl/glusterfs.key /etc/ssl/glusterfs.ca
- 7. Create the Red Hat Gluster Storage daemonset by executing the following command:



For Ansible deployments, the image name and the version has to be specified in the template, before executing the command.

- # oc process glusterfs | oc create -f -
- 8. On creation of daemon set the pods are started. To verify if the pods are started, execute the following command:
  - # oc get pods
- 9. Start all the volumes.
  - # oc rsh <gluster\_pod\_name> gluster volume start VOLNAME
- 10. Start the application pods to use the management encrypted Red Hat Gluster Storage.

### **PART IV. MIGRATION**

# CHAPTER 9. UPDATING THE REGISTRY WITH RED HAT OPENSHIFT CONTAINER STORAGE AS THE STORAGE BACK-END

OpenShift Container Platform provides an integrated registry with storage using an NFS-backed persistent volume that is automatically setup. Red Hat Openshift Container Storage allows you to replace this with a Gluster persistent volume for registry storage. This provides increased reliability, scalability and failover.

For additional information about OpenShift Container Platform and the docker-registry, see https://access.redhat.com/documentation/en-us/openshift\_container\_platform/3.11/html/configuring\_clusters/setting-up-the-registry.

## 9.1. VALIDATING THE OPENSHIFT CONTAINER PLATFORM REGISTRY DEPLOYMENT

To verify that the registry is properly deployed, execute the following commands:

1. On the master or client, execute the following command to login as the cluster admin user:

# oc login

For example:

# oc login

Authentication required for https://master.example.com:8443 (openshift)

Username: <cluster-admin-user>

Password: <password>

Login successful.

\* default management-infra openshift openshift-infra

Using project "default".

If you are not automatically logged into project default, then switch to it by executing the following command:

# oc project default

2. To verify that the pod is created, execute the following command:

# oc get pods

For example:

# oc get pods

NAME READY STATUS RESTARTS AGE
docker-registry-2-mbu0u 1/1 Running 4 6d
docker-registry-2-spw0o 1/1 Running 3 6d
registry-console-1-rblwo 1/1 Running 3 6d

3. To verify that the endpoints are created, execute the following command:

# oc get endpoints

For example:

4. To verify that the persistent volume is created, execute the following command:

# oc get pv
NAME CAPACITY ACCESSMODES RECLAIMPOLICY STATUS CLAIM REASON
AGE
registry-volume 5Gi RWX Retain Bound default/registry-claim
7d

5. To obtain the details of the persistent volume that was created for the NFS registry, execute the following command:

# oc describe pv registry-volume
Name: registry-volume
Labels: <none>
StorageClass:
Status: Bound
Claim: default/registry-claim
Reclaim Policy: Retain

Capacity: 5Gi Message:

Access Modes: RWX

Source:

Type: NFS (an NFS mount that lasts the lifetime of a pod)

Server: cns30.rh73 Path: /exports/registry ReadOnly: false

No events.

## 9.2. CONVERTING THE OPENSHIFT CONTAINER PLATFORM REGISTRY WITH RED HAT OPENSHIFT CONTAINER STORAGE

This section provides the steps to create a Red Hat Gluster Storage volume and use it to provide storage for the integrated registry.

#### Setting up a Red Hat Gluster Storage Persistent Volume

Execute the following commands to create a Red Hat Gluster Storage volume to store the registry data and create a persistent volume.



#### NOTE

The commands must be executed in the **default** project.

1. Login to the **default** project:

# oc project default

For example:

# oc project default Now using project "default" on server "https://cns30.rh73:8443"

2. Execute the following command to create the **gluster-registry-endpoints.yaml** file:

oc get endpoints <heketi-db-storage-endpoint-name> -o yaml --namespace=project-name>
> gluster-registry-endpoints.yaml



#### **NOTE**

You must create an endpoint for each project from which you want to utilize the Red Hat Gluster Storage registry. Hence, you will have a service and an endpoint in both the **default** project and the new project (**storage-project**) created in earlier steps.

3. Edit the **gluster-registry-endpoints.yaml** file. Change the name to gluster-registry-endpoints and remove all the other metadata, leaving everything else the same.

```
# cat gluster-registry-endpoints.yaml apiVersion: v1 kind: Endpoints metadata: name: gluster-registry-endpoints subsets: - addresses: - ip: 192.168.124.114 - ip: 192.168.124.52 - ip: 192.168.124.83 ports: - port: 1 protocol: TCP
```

4. Execute the following command to create the endpoint:

# oc create -f gluster-registry-endpoints.yaml endpoints "gluster-registry-endpoints" created

5. To verify the creation of the endpoint, execute the following command:

# oc get endpoints NAME **ENDPOINTS** AGE docker-registry 10.129.0.8:5000,10.130.0.5:5000 28d gluster-registry-endpoints 192.168.124.114:1,192.168.124.52:1,192.168.124.83:1 10s kubernetes 192.168.124.250:8443,192.168.124.250:8053,192.168.124.250:8053 28d registry-console 10.131.0.6:9090 28d router 192.168.124.114:443,192.168.124.83:443,192.168.124.114:1936 + 3 more... 28d

6. Execute the following command to create the **gluster-registry-service.yaml** file:

oc get services <heketi-storage-endpoint-name> -o yaml --namespace=<project-name> > gluster-registry-service.yaml

7. Edit the **gluster-registry-service.yaml** file. Change the name to gluster-registry-service and remove all the other metadata. Also, remove the specific cluster IP addresses:

# cat gluster-registry-service.yaml apiVersion: v1 kind: Service metadata: name: gluster-registry-service spec: ports: - port: 1 protocol: TCP targetPort: 1 sessionAffinity: None type: ClusterIP status: loadBalancer: {}

8. Execute the following command to create the service:

# oc create -f gluster-registry-service.yaml services "gluster-registry-service" created

9. Execute the following command to verify if the service are running:

10. Execute the following command to obtain the fsGroup GID of the existing docker-registry pods:

```
\label{lem:condition} \begin{tabular}{ll} $\#$ export $GID=\$(oc\ get\ po\ --selector="docker-registry=default"\ -o\ go-template\ --template='\{\{printf\ "\%.0f"\ ((index\ .items\ 0).spec.securityContext.fsGroup)\}\}') \end{tabular}
```

11. Execute the following command to create a volume

# heketi-cli volume create --size=5 --name=gluster-registry-volume --gid=\${GID}

12. Create the persistent volume file for the Red Hat Gluster Storage volume:

```
# cat gluster-registry-volume.yaml
kind: PersistentVolume
apiVersion: v1
metadata:
 name: gluster-registry-volume
 labels:
  glusterfs: registry-volume
spec:
 capacity:
  storage: 5Gi
 glusterfs:
  endpoints: gluster-registry-endpoints
  path: gluster-registry-volume
 accessModes:
  - ReadWriteMany
persistentVolumeReclaimPolicy: Retain
```

13. Execute the following command to create the persistent volume:

# oc create -f gluster-registry-volume.yaml

14. Execute the following command to verify and get the details of the created persistent volume:

```
# oc get pv/gluster-registry-volume

NAME CAPACITY ACCESSMODES RECLAIMPOLICY STATUS CLAIM

REASON AGE
gluster-registry-volume 5Gi RWX Retain Available 21m
```

15. Create a new persistent volume claim. Following is a sample Persistent Volume Claim that will be used to replace the existing registry-storage volume claim.

```
# cat gluster-registry-claim.yaml apiVersion: v1 kind: PersistentVolumeClaim metadata: name: gluster-registry-claim spec: accessModes: - ReadWriteMany resources: requests: storage: 5Gi
```

selector: matchLabels: glusterfs: registry-volume

16. Create the persistent volume claim by executing the following command:

# oc create -f gluster-registry-claim.yaml

For example:

# oc create -f gluster-registry-claim.yaml persistentvolumeclaim "gluster-registry-claim" created

17. Execute the following command to verify if the claim is bound:

# oc get pvc/gluster-registry-claim

For example:

# oc get pvc/gluster-registry-claim

NAME STATUS VOLUME CAPACITY ACCESSMODES AGE gluster-registry-claim Bound gluster-registry-volume 5Gi RWX 22s

18. Make the registry read-only by executing the following command:

# oc set env -n default dc/docker-registry
'REGISTRY\_STORAGE\_MAINTENANCE\_READONLY={"enabled":true}'

To confirm the value is set to readonly, execute the following command:

# oc set env -n default dc/docker-registry --list

19. If you want to migrate the data from the old registry to the Red Hat Gluster Storage registry, then execute the following commands:



#### NOTE

These steps are optional.

a. Add the Red Hat Gluster Storage registry to the old registry deployment configuration (dc) by executing the following command:

# oc set volume dc/docker-registry --add --name=gluster-registry-storage -m /gluster-registry -t pvc --claim-name=gluster-registry-claim

b. Save the Registry pod name by executing the following command:

# export REGISTRY\_POD=\$(oc get po --selector="docker-registry=default" -o gotemplate --template='{{printf "%s" ((index .items 0).metadata.name)}}')

c. Copy the data from the old registry directory to the Red Hat Gluster Storage registry directory by executing the following command:

# oc rsh \$REGISTRY\_POD cp -a /registry/ /gluster-registry/

- d. Remove the Red Hat Gluster Storage registry from the old dc registry by executing the following command:
  - # oc volume dc/docker-registry --remove --name=gluster-registry-storage
- 20. Replace the existing registry-storage volume with the new gluster-registry-claim PVC:

# oc set volume dc/docker-registry --add --name=registry-storage -t pvc --claim-name=gluster-registry-claim --overwrite

- 21. Make the registry read write by executing the following command:
  - # oc set env dc/docker-registry REGISTRY\_STORAGE\_MAINTENANCE\_READONLY-

To validate if the setting is set to read write, execute the following command:

# oc set env -n default dc/docker-registry --list

For more information about accessing the registry, see https://access.redhat.com/documentation/en-us/openshift\_container\_platform/3.11/html/configuring\_clusters/setting-up-the-registry#install-config-registry-accessing.

### PART V. MONITORING

# CHAPTER 10. ENABLING VOLUME METRICS IN OPENSHIFT 3.10 AND 3.11

Prometheus is a stand-alone, open source systems monitoring and alerting toolkit and shipped with OpenShift. You can use Prometheus to visualize metrics and alerts for OpenShift Container Platform system resources as PVs and services like heketi.

Heketi provides a RESTful management interface which can be used to manage the life cycle of GlusterFS volumes, as well as a metrics endpoint which can be scraped by Prometheus.

The way Prometheus is integrated into OpenShift differs slightly between OCP 3.10 and 3.11.

For more information on how to setup Prometheus in OCP 3.10, see Prometheus on OpenShift Container Platform.

For more information on how to setup Prometheus in OCP 3.11, see Prometheus Cluster Monitoring.

#### 10.1. AVAILABLE METRICS FOR FILE STORAGE AND BLOCK STORAGE

The following list provides different metrics of the PVs that can be viewed on Prometheus:

#### kubelet\_volume\_stats\_available\_bytes

Number of available bytes in the volume.

#### kubelet\_volume\_stats\_capacity\_bytes

Capacity in bytes of the volume.

#### kubelet\_volume\_stats\_inodes

Maximum number of inodes in the volume.

#### kubelet volume stats inodes free

Number of free inodes in the volume.

#### kubelet\_volume\_stats\_inodes\_used

Number of used inodes in the volume.

#### kubelet\_volume\_stats\_used\_bytes

Number of used bytes in the volume.

The Heketi service provides the following metrics:

#### heketi\_cluster\_count

Number of clusters.

#### heketi\_device\_brick\_count

Number of bricks on device.

#### heketi\_device\_count

Number of devices on host.

#### heketi device free bytes

Amount of free space available on the device.

#### heketi\_device\_size\_bytes

Total size of the device.

heketi\_device\_used\_bytes

Amount of space used on the device.

#### heketi\_nodes\_count

Number of nodes on the cluster.

#### heketi\_up

Verifies if heketi is running.

#### heketi\_volumes\_count

Number of volumes on cluster.

#### heketi\_block\_volumes\_count

Number of block volumes on cluster.

#### 10.2. ENABLING HEKETI METRICS IN OPENSHIFT 3.10

To view Heketi metrics on Prometheus in OCP 3.10, execute the following commands:

 Add annotations to the **heketi-storage** service (normally running in the app-storage namespace).

# oc project app-storage # oc annotate svc heketi-storage prometheus.io/scheme=http # oc annotate svc heketi-storage prometheus.io/scrape=true

# oc describe svc heketi-storage Name: heketi-storage Namespace: app-storage

Labels: glusterfs=heketi-storage-service

heketi=storage-service

Annotations: description=Exposes Heketi service

prometheus.io/scheme=http prometheus.io/scrape=true

Selector: glusterfs=heketi-storage-pod

Type: ClusterIP
IP: 172.30.90.87
Port: heketi 8080/TCP
TargetPort: 8080/TCP

Endpoints: 172.18.14.2:8080

Session Affinity: None

2. Add the app-storage namespace for the heketi service in the Prometheus configmap.

```
# oc get cm prometheus -o yaml -n openshift-metrics
....
- job_name: 'kubernetes-service-endpoints'

tls_config:
    ca_file: /var/run/secrets/kubernetes.io/serviceaccount/ca.crt
    # TODO: this should be per target
    insecure_skip_verify: true

kubernetes_sd_configs:
    - role: endpoints

relabel_configs:
```

```
# only scrape infrastructure components
- source_labels: [__meta_kubernetes_namespace]
action: keep
```

regex: 'default|logging|metrics|kube-.+|openshift|openshift-.+|app-storage'

Do the above for all other storage namespaces (for example: infra-storage).

3. Restart the **prometheus-0** pod to query the Heketi metrics in Prometheus.

#### 10.3. ENABLING HEKETI METRICS IN OPENSHIFT 3.11

In OCP 3.11, Prometheus uses servicemonitors, which are new resources introduced by the Prometheus Operator. The servicemonitors need to be created for every storage namespace and they describe the set of targets to be monitored.

To view Heketi metrics on Prometheus in OCP 3.11, execute the following commands:

1. Add annotations to the **heketi-storage** service.

```
# oc project app-storage
# oc annotate svc heketi-storage prometheus.io/scheme=http
# oc annotate svc heketi-storage prometheus.io/scrape=true
```

2. Create a **heketi-app** servicemonitor in the openshift-monitoring namespace using the below template:

```
# cat heketi-app-sm.yml
apiVersion: monitoring.coreos.com/v1
kind: ServiceMonitor
metadata:
 name: heketi-app
 labels:
  k8s-app: heketi-app
 namespace: openshift-monitoring
spec:
 endpoints:
 - bearerTokenFile: /var/run/secrets/kubernetes.io/serviceaccount/token
  interval: 30s
  port: heketi
  scheme: http
  targetPort: 0
 namespaceSelector:
  matchNames:
  - app-storage
 selector:
  matchLabels:
   heketi: storage-service
```

Where, the namespaceSelector and label need to match the values in the heketi-storage service:

```
# oc describe svc heketi-storage -n app-storage
Name: heketi-storage
Namespace: app-storage
```

Labels: glusterfs=heketi-storage-service

heketi=storage-service

Annotations: description=Exposes Heketi service

prometheus.io/scheme=http prometheus.io/scrape=true

Selector: glusterfs=heketi-storage-pod

Type: ClusterIP
IP: 172.30.3.92
Port: heketi 8080/TCP
TargetPort: 8080/TCP

Endpoints: 10.128.4.12:8080

Session Affinity: None Events: <none>

With the correct selectors set, create the servicemonitor in the openshift-monitoring namespace with the correct selectors set.

# oc create -f heketi-app-sm.yml -n openshift-monitoring servicemonitor.monitoring.coreos.com "heketi-app" created

# oc get servicemonitor -n openshift-monitoring

NAME AGE
alertmanager 20d
cluster-monitoring-operator 20d
heketi-app 1m

kube-apiserver 20d
kube-controllers 20d
kube-state-metrics 20d
kubelet 20d
node-exporter 20d
prometheus 20d
prometheus-operator 20d

- 3. In case you have multiple OCS clusters, one servicemonitor needs to be created per OCS cluster using the steps above.
- 4. Execute the following command to add cluster-reader rights to prometheus:

# oc adm policy add-cluster-role-to-user cluster-reader \
system:serviceaccount:openshift-monitoring:prometheus-k8s -n \
openshift-monitoring
cluster role "cluster-reader" added: "system:serviceaccount:openshiftmonitoring:prometheus-k8s"


5. After some minutes, Prometheus loads the new servicemonitors.

#### 10.4. VIEWING METRICS

To view any metrics:

- 1. Add the metrics name in **Prometheus**, and click **Execute**.
- In the Graph tab, the value for the metrics for the volume is displayed as a graph.
   For example, in the following image, to check the available bytes,
   kubelet\_volume\_stats\_available\_bytes metric is added to the search bar on Prometheus. On

clicking **Execute**, the available bytes value is depicted as a graph. You can hover the mouse on the line to get more details. (To view the image in detail, right-click and select View Image.)



### PART VI. TROUBLESHOOT

#### **CHAPTER 11. TROUBLESHOOTING**

This chapter describes the most common troubleshooting scenarios related to Red Hat Openshift Container Storage.

#### What to do if a Red Hat Openshift Container Storage node Fails

If a Red Hat Openshift Container Storage node fails, and you want to delete it, then, disable the node before deleting it. For more information, see Section 1.2.3, "Deleting Node".

If a Red Hat Openshift Container Storage node fails and you want to replace it, see Section 1.2.3.3, "Replacing a Node".

#### What to do if a Red Hat Openshift Container Storage device fails

If a Red Hat Openshift Container Storage device fails, and you want to delete it, then, disable the device before deleting it. For more information, see Section 1.2.2, "Deleting Device".

If a Red Hat Openshift Container Storage device fails, and you want to replace it, see Section 1.2.2.3, "Replacing a Device".

#### What to do if Red Hat Openshift Container Storage volumes require more capacity

You can increase the storage capacity by either adding devices, increasing the cluster size, or adding an entirely new cluster. For more information, see Section 1.1, "Increasing Storage Capacity".

#### How to upgrade Openshift when Red Hat Openshift Container Storage is installed

To upgrade Openshift Container Platform, see https://access.redhat.com/documentation/en-us/openshift\_container\_platform/3.11/html/upgrading\_clusters/install-config-upgrading-automated-upgrades#upgrading-to-ocp-3-10.

#### Viewing Log Files

#### Viewing Red Hat Gluster Storage Container Logs

Debugging information related to Red Hat Gluster Storage containers is stored on the host where the containers are started. Specifically, the logs and configuration files can be found at the following locations on the openshift nodes where the Red Hat Gluster Storage server containers run:

- /etc/glusterfs
- /var/lib/glusterd
- /var/log/glusterfs

#### Viewing Heketi Logs

Debugging information related to Heketi is stored locally in the container or in the persisted volume that is provided to Heketi container.

You can obtain logs for Heketi by running the **docker logs <container-id>** command on the openshift node where the container is being run.

#### Heketi command returns with no error or empty error

Sometimes, running heketi-cli command returns with no error or empty error like \_ Error\_.It is mostly due to heketi server not properly configured. You must first ping to validate that the Heketi server is available and later verify with a \_ curl\_ command and \_/hello endpoint\_.

# curl http://deploy-heketi-storage-project.cloudapps.mystorage.com/hello

#### Heketi reports an error while loading the topology file

Running heketi-cli reports: Error "Unable to open topology file" error while loading the topology file. This could be due to the use of old syntax of single hyphen (-) as a prefix for JSON option. You must use the new syntax of double hyphens and reload the topology file.

#### cURL command to heketi server fails or does not respond

If the router or heketi is not configured properly, error messages from the heketi may not be clear. To troubleshoot, ping the heketi service using the endpoint and also using the IP address. If ping by the IP address succeeds and ping by the endpoint fails, it indicates a router configuration error. After the router is setup properly, run a simple curl command like the following:

# curl http://deploy-heketi-storage-project.cloudapps.mystorage.com/hello

If heketi is configured correctly, a welcome message from heketi is displayed. If not, check the heketi configuration.

#### Heketi fails to start when Red Hat Gluster Storage volume is used to store heketi.db file

Sometimes Heketi fails to start when Red Hat Gluster Storage volume is used to store heketi.db and reports the following error:

[heketi] INFO 2016/06/23 08:33:47 Loaded kubernetes executor [heketi] ERROR 2016/06/23 08:33:47 /src/github.com/heketi/heketi/apps/glusterfs/app.go:149: write /var/lib/heketi/heketi.db: read-only file system ERROR: Unable to start application

The read-only file system error as shown above could be seen while using a Red Hat Gluster Storage volume as backend. This could be when the quorum is lost for the Red Hat Gluster Storage volume. In a replica-3 volume, this would be seen if 2 of the 3 bricks are down. You must ensure the quorum is met for heketi gluster volume and it is able to write to heketi.db file again.

Even if you see a different error, it is a recommended practice to check if the Red Hat Gluster Storage volume serving heketi.db file is available or not. Access deny to heketi.db file is the most common reason for it to not start.

# CHAPTER 12. CLIENT CONFIGURATION USING PORT FORWARDING

If a router is not available, you may be able to set up port forwarding so that heketi-cli can communicate with the Heketi service. Execute the following commands for port forwarding:

- 1. Obtain the Heketi service pod name by running the following command:
  - # oc get pods
- 2. To forward the port on your local system to the pod, execute the following command on another terminal of your local system:
  - # oc port-forward <heketi pod name> 8080:8080
- 3. On the original terminal execute the following command to test the communication with the server:
  - # curl http://localhost:8080/hello

This will forward the local port 8080 to the pod port 8080.

- 4. Setup the Heketi server environment variable by running the following command:
  - # export HEKETI\_CLI\_SERVER=http://localhost:8080
- 5. Get information from Heketi by running the following command:
  - # heketi-cli topology info