RCSDIFF(1) RCSDIFF(1)

NAME

rcsdiff - compare RCS revisions

SYNOPSIS

DESCRIPTION

rcsdiff runs **diff**(1) to compare two revisions of each RCS file given.

Filenames matching an RCS suffix denote RCS files; all others denote working files. Names are paired as explained in $\mathbf{ci}(1)$.

The option $-\mathbf{q}$ suppresses diagnostic output. Zero, one, or two revisions may be specified with $-\mathbf{r}$. The option $-\mathbf{k}subst$ affects keyword substitution when extracting revisions, as described in $\mathbf{co}(1)$; for example, $-\mathbf{kk} - \mathbf{r} \cdot \mathbf{1} \cdot \mathbf{1} - \mathbf{r} \cdot \mathbf{1} \cdot \mathbf{2}$ ignores differences in keyword values when comparing revisions $\mathbf{1.1}$ and $\mathbf{1.2}$. To avoid excess output from locker name substitution, $-\mathbf{kkvl}$ is assumed if (1) at most one revision option is given, (2) no $-\mathbf{k}$ option is given, (3) $-\mathbf{kkv}$ is the default keyword substitution, and (4) the working file's mode would be produced by $\mathbf{co} - \mathbf{l}$. See $\mathbf{co}(1)$ for details about $-\mathbf{T}$, $-\mathbf{V}$, $-\mathbf{x}$ and $-\mathbf{z}$. Otherwise, all options of $\mathbf{diff}(1)$ that apply to regular files are accepted, with the same meaning as for \mathbf{diff} .

If both *rev1* and *rev2* are omitted, **rcsdiff** compares the latest revision on the default branch (by default the trunk) with the contents of the corresponding working file. This is useful for determining what you changed since the last checkin.

If *rev1* is given, but *rev2* is omitted, **rcsdiff** compares revision *rev1* of the RCS file with the contents of the corresponding working file.

If both rev1 and rev2 are given, resdiff compares revisions rev1 and rev2 of the RCS file.

Both rev1 and rev2 may be given numerically or symbolically.

EXAMPLE

The command

resdiff f.c

compares the latest revision on the default branch of the RCS file to the contents of the working file f.c.

ENVIRONMENT

RCSINIT

Options prepended to the argument list, separated by spaces. A backslash escapes spaces within an option. The **RCSINIT** options are prepended to the argument lists of most RCS commands. Useful **RCSINIT** options include $-\mathbf{q}$, $-\mathbf{V}$, $-\mathbf{x}$, and $-\mathbf{z}$.

RCS_MEM_LIMIT

An integer *lim*, measured in kilobytes, specifying the threshold under which commands will try to use memory-based operations for processing the RCS file. (For RCS files of size *lim* kilobytes or greater, RCS will use the slower standard input/output routines.) Default value is 256.

TMPDIR

Name of the temporary directory. If not set, the environment variables **TMP** and **TEMP** are inspected instead and the first value found is taken; if none of them are set, a host-dependent default is used, typically /tmp.

DIAGNOSTICS

Exit status is 0 for no differences during any comparison, 1 for some differences, 2 for trouble.

IDENTIFICATION

Author: Walter F. Tichy.

Manual Page Revision: 5.8; Release Date: 2011-08-30.

Copyright © 2010, 2011 Thien-Thi Nguyen.

Copyright © 1990, 1991, 1992, 1993 Paul Eggert.

Copyright © 1982, 1988, 1989 Walter F. Tichy.

RCSDIFF(1) RCSDIFF(1)

SEE ALSO

 $\boldsymbol{ci}(1), \boldsymbol{co}(1), \boldsymbol{diff}(1), \boldsymbol{ident}(1), \boldsymbol{rcs}(1), \boldsymbol{rcsintro}(1), \boldsymbol{rcsmerge}(1), \boldsymbol{rlog}(1).$

Walter F. Tichy, RCS—A System for Version Control, *Software—Practice & Experience* **15**, 7 (July 1985), 637-654.

GNU RCS 5.8 2011-08-30 2