#### **NAME**

postqueue - Postfix queue control

# **SYNOPSIS**

```
postqueue [-v] [-c config_dir] -f
postqueue [-v] [-c config_dir] -i queue_id
postqueue [-v] [-c config_dir] -p
postqueue [-v] [-c config_dir] -s site
```

#### DESCRIPTION

The **postqueue**(1) command implements the Postfix user interface for queue management. It implements operations that are traditionally available via the **sendmail**(1) command. See the **postsuper**(1) command for queue operations that require super—user privileges such as deleting a message from the queue or changing the status of a message.

The following options are recognized:

**-c** *config\_dir* 

The **main.cf** configuration file is in the named directory instead of the default configuration directory. See also the MAIL\_CONFIG environment setting below.

-**f** Flush the queue: attempt to deliver all queued mail.

This option implements the traditional "**sendmail**  $-\mathbf{q}$ " command, by contacting the Postfix  $\mathbf{qmgr}(8)$  daemon.

Warning: flushing undeliverable mail frequently will result in poor delivery performance of all other mail.

-i queue\_id

Schedule immediate delivery of deferred mail with the specified queue ID.

This option implements the traditional **sendmail** -qI command, by contacting the **flush**(8) server.

This feature is available with Postfix version 2.4 and later.

**-p** Produce a traditional sendmail–style queue listing. This option implements the traditional **mailq** command, by contacting the Postfix **showq**(8) daemon.

Each queue entry shows the queue file ID, message size, arrival time, sender, and the recipients that still need to be delivered. If mail could not be delivered upon the last attempt, the reason for failure is shown. The queue ID string is followed by an optional status character:

- \* The message is in the **active** queue, i.e. the message is selected for delivery.
- ! The message is in the **hold** queue, i.e. no further delivery attempt will be made until the mail is taken off hold.
- -s site Schedule immediate delivery of all mail that is queued for the named site. A numerical site must be specified as a valid RFC 5321 address literal enclosed in [], just like in email addresses. The site must be eligible for the "fast flush" service. See **flush**(8) for more information about the "fast flush" service.

This option implements the traditional "**sendmail**  $-q\mathbf{R}$  site" command, by contacting the Postfix  $\mathbf{flush}(8)$  daemon.

-v Enable verbose logging for debugging purposes. Multiple -v options make the software increasingly verbose. As of Postfix 2.3, this option is available for the super–user only.

#### **SECURITY**

This program is designed to run with set-group ID privileges, so that it can connect to Postfi x daemon processes

#### **DIAGNOSTICS**

Problems are logged to **syslogd**(8) and to the standard error stream.

#### **ENVIRONMENT**

#### MAIL\_CONFIG

Directory with the **main.cf** file. In order to avoid exploitation of set-group ID privileges, a non-standard directory is allowed only if:

- The name is listed in the standard **main.cf** fi le with the **alternate\_config\_directories** confi guration parameter.
- The command is invoked by the super–user.

#### **CONFIGURATION PARAMETERS**

The following **main.cf** parameters are especially relevant to this program. The text below provides only a parameter summary. See **postconf**(5) for more details including examples.

#### alternate\_config\_directories (empty)

A list of non-default Postfi x confi guration directories that may be specified with "-c confi g\_directory" on the command line, or via the MAIL CONFIG environment parameter.

## config\_directory (see 'postconf -d' output)

The default location of the Postfi x main.cf and master.cf confi guration fi les.

### command\_directory (see 'postconf -d' output)

The location of all postfi x administrative commands.

## fast\_flush\_domains (\$relay\_domains)

Optional list of destinations that are eligible for per-destination logfi les with mail that is queued to those destinations.

#### import\_environment (see 'postconf -d' output)

The list of environment parameters that a Postfi x process will import from a non-Postfi x parent process.

### queue\_directory (see 'postconf -d' output)

The location of the Postfi x top-level queue directory.

# syslog\_facility (mail)

The syslog facility of Postfi x logging.

#### syslog\_name (see 'postconf -d' output)

The mail system name that is prepended to the process name in syslog records, so that "smtpd" becomes, for example, "postfi x/smtpd".

# trigger\_timeout (10s)

The time limit for sending a trigger to a Postfi x daemon (for example, the **pickup**(8) or **qmgr**(8) daemon).

Available in Postfi x version 2.2 and later:

#### authorized flush users (static:anyone)

List of users who are authorized to flush the queue.

#### authorized\_mailq\_users (static:anyone)

List of users who are authorized to view the queue.

#### **FILES**

/var/spool/postfi x, mail queue

# **SEE ALSO**

qmgr(8), queue manager showq(8), list mail queue flush(8), fast flush service sendmail(1), Sendmail—compatible user interface postsuper(1), privileged queue operations

## **README FILES**

Use "**postconf readme\_directory**" or "**postconf html\_directory**" to locate this information. ETRN\_README, Postfi x ETRN howto

# **LICENSE**

The Secure Mailer license must be distributed with this software.

# **HISTORY**

The postqueue command was introduced with Postfi x version 1.1.

## **AUTHOR(S)**

Wietse Venema IBM T.J. Watson Research P.O. Box 704 Yorktown Heights, NY 10598, USA