NAME

postcat - show Postfix queue file contents

SYNOPSIS

postcat [-bdehnoqv] [-c config_dir] [files...]

DESCRIPTION

The **postcat**(1) command prints the contents of the named *files* in human–readable form. The files are expected to be in Postfix queue file format. If no *files* are specified on the command line, the program reads from standard input.

By default, **postcat**(1) shows the envelope and message content, as if the options **-beh** were specified. To view message content only, specify **-bh** (Postfix 2.7 and later).

Options:

-b Show body content. The **-b** option starts producing output at the first non−header line, and stops when the end of the message is reached.

This feature is available in Postfix 2.7 and later.

-c config dir

The **main.cf** configuration file is in the named directory instead of the default configuration directory.

- **−d** Print the decimal type of each record.
- **−e** Show message envelope content.

This feature is available in Postfix 2.7 and later.

-h Show message header content. The **-h** option produces output from the beginning of the message up to, but not including, the first non-header line.

This feature is available in Postfix 2.7 and later.

- **−o** Print the queue file offset of each record.
- -q Search the Postfix queue for the named *files* instead of taking the names literally.

This feature is available in Postfix 2.0 and later.

−v Enable verbose logging for debugging purposes. Multiple **−v** options make the software increasingly verbose.

DIAGNOSTICS

Problems are reported to the standard error stream.

ENVIRONMENT

MAIL_CONFIG

Directory with Postfix configuration files.

CONFIGURATION PARAMETERS

The following **main.cf** parameters are especially relevant to this program.

The text below provides only a parameter summary. See **postconf**(5) for more details including examples.

config_directory (see 'postconf -d' output)

The default location of the Postfix main.cf and master.cf configuration files.

queue_directory (see 'postconf -d' output)

The location of the Postfix top-level queue directory.

FILES

/var/spool/postfi x, Postfi x queue directory

SEE ALSO

postconf(5), Postfi x confi guration

LICENSE

The Secure Mailer license must be distributed with this software.

AUTHOR(S)

Wietse Venema IBM T.J. Watson Research P.O. Box 704 Yorktown Heights, NY 10598, USA