Bym model for spatial effects

Parametrization

This model is simply the sum of a besag model and a iid model.

The benefite is that this allows to get the posterior marginals of the sum of the spatial and iid model; otherwise it offers no advantages.

Hyperparameters

The hyperparameters are the precision τ_1 of the iid model and the precision τ_2 of the besag model. The precision parameters are represented as

$$\theta = (\theta_1, \theta_2) = (\log \tau_1, \log \tau_2)$$

and the prior is defined on θ.

Specification

The bym model is specified inside the `f()` function as

```
f(<whatever>,model="bym",graph=<graph>,
  hyper=<hyper>, adjust.for.con.comp = TRUE)
```

The neighbourhood structure of **x** is passed to the program through the `graph` argument.

The option `adjust.for.con.comp` adjust the model if the graph has more than one connected compoment, and this adjustment can be disabled setting this option to `FALSE`. This means that `constr=TRUE` is interpreted as a sum-to-zero constraint on *each* connected component and the `rankdef` parameter is set accordingly.

Hyperparameter spesification and default values

hyper

theta1

name log unstructured precision
short.name prec.unstruct
prior loggamma
param 1 5e-04
initial 4
fixed FALSE
to.theta `function(x) log(x)`
from.theta `function(x) exp(x)`

theta2

name log spatial precision
short.name prec.spatial
prior loggamma
param 1 5e-04
initial 4
fixed FALSE
to.theta `function(x) log(x)`

from.theta `function(x) exp(x)`

constr TRUE

nrow.ncol FALSE

augmented TRUE

aug.factor 2

aug.constr 2

n.div.by

n.required TRUE

set.default.values TRUE

pdf bym

Example

For examples of application of this model see the `Bym` example in Volume I.

Notes

None