

This is a copy of a conversation between ChatGPT & Anonymous.

Report conversation

Dynamic Values in ViteJS

PR Link: <https://github.com/Snapchain/zkevm-bridge-ui/pull/1>

Conversation Link: <https://chat.openai.com/share/5b5fd8b5-d766-41c4-8312-4c887e29ec6e>

using vitejs, how to make index.html to have dynamic values from .env file

To make `index.html` have dynamic values from an `.env` file in a ViteJS project, you can use Vite's environment variables and the `define` plugin feature to inject these values into your `index.html`. Here's a step-by-step guide on how to achieve this:

1. Create and Configure Your `.env` File

First, create an `.env` file at the root of your project if you haven't already. Inside this file, you can define your environment variables. Vite automatically supports `.env` files and can load variables prefixed with `VITE\_`. For example:

Code

```
VITE_APP_TITLE=My Vite App
```

2. Use Vite's `define` Option

In your `vite.config.js` or `vite.config.ts` file, use the `define` option to make your environment variables available for injection into `index.html`. You can access environment variables in Vite using `process.env.VITE\_YOUR\_VARIABLE\_NAME`.

Here's how you can modify your Vite configuration:

Code

```
import { defineConfig } from 'vite';

export default defineConfig({
  define: {
    __APP_TITLE__: JSON.stringify(process.env.VITE_APP_TITLE),
  },
});
```

```
});
```

By using `JSON.stringify()`, you ensure that the variable is correctly interpreted as a string within your JavaScript code.

3. Inject Variables into `index.html`

Now, you can inject the defined variables into your `index.html` by using the variables you defined in the Vite configuration. For example:

Code

```
<!DOCTYPE html>
<html lang="en">
<head>
  <meta charset="UTF-8">
  <meta name="viewport" content="width=device-width, initial-scale=1.0">
  <title>__APP_TITLE__</title>
</head>
<body>
  <div id="app"></div>
  <script type="module" src="/src/main.js"></script>
  <script>
    document.title = __APP_TITLE__;
  </script>
</body>
</html>
```

In this example, `__APP_TITLE__` will be replaced with the value of `VITE_APP_TITLE` from your `.env` file when Vite serves or builds your project.

4. Serve or Build Your Project

After configuring everything, when you serve or build your project, Vite will replace `__APP_TITLE__` with the actual value from your `.env` file, thus dynamically injecting the value into your `index.html`.

Note

Remember that Vite's environment variables and the `define` option only inject compile-time constants into your code. They do not provide a way to read `.env` variables at runtime directly in the browser. If you need to access environment variables at runtime in the browser, you would need to inject them into the global scope or use another method to make them available to your client-side JavaScript.