Trinity Wand Picture Tutorial

By Jon Horrocks (Dor2or on the forums.cloud-busters.com site)

This 9-part tutorial is based on how I make the Al Gray (Dragon) model Trinity Wand.

List of Tools

1 Drill
1 Pipe cutter
1 Wire cutter
1 Tape measure
1 Pencil
1 Razor blade – (Not shown in picture below)
1 Water Wand – A sealed pipe containing pure Sally Water
1 Marker – Used to mark the pipes for cutting
1 Hammer
1 Funnel
1 Plastic container and stir stick – For mixing the resin
1 Dropper – I got mine free from the local pharmacy. Ask for a baby's medicine dropper.

List of Materials

1 Container of FastSteel or QuickSteel – FastSteel is found in the paint dept. at Home Depot, Quick Steel is found in the auto dept. of Walmart
1 Package of latex gloves - I get mine from the dollar store
3 1 1/4-inch by 12-inch copper pipes
6 1 1/4-inch end caps
1 Spool of 30-gauge (0.25-mm) Insulated Wrapping Wire - Available at most Radio Shacks, comes in red, white, and blue colors.
1 18-inch by 2ft sheet of aluminum foil
1 Roll of aluminum tape - Available at Home Depot in the air conditioning section. Not necessary - packing tape will work, too, but this is better
1 Roll of 24-gauge (0.5-mm) copper wire - I get mine from Ace Hardware
1 Bottle of Sally Water - Available from Sally at steller2@cloud-busters.com
1 Gallon size plastic bottle of Arrowhead drinking water – I pour this out and put in distilled water, but any water will work. Its easier to stir with a rounded container
1 Container of resin + catalyst
1 Quarter cup of metal shavings (not shown in picture below)
1 Small quartz crystals, rose quartz pieces
3 Nickles – Yeah, the money
1 Coil of ¼-inch copper tubing – Found in the plumbing section of Home Depot

Part 1 – Preparing the Pipes

I get my copper pipe from Home Depot. They are found standing up in 10-foot lengths. You could ask a sales associate nicely to cut them in half for easier transport. Sometimes they get moody about that so nowadays I bring my own pipe cutter and take care of it in the parking lot. I then use a hani-wipe to clean the pipes before putting them in my car. They can be a little dirty off the shelf. I buy enough pipe at one time to make 10 Trinity Wands. The picture shows six 5-foot (15-dm) lengths of 1 ¼-inch (3-cm) copper pipe.



Mark the pipes in 1-foot intervals. Home Depot doesn't cut their pipes exactly to the inch so there may be an extra inch or so at the end. I just leave it.

Set the pipe cutter.



If you are fortunate enough to have a vice, then use it to hold the pipe while you work the cutter. This saves my hands a lot of stress (10 TWs = 24 pipe cuts). Notice the CD player in the background. Jumping music is essential for putting me in the right mood to create these devices. ☺



3 1-foot (30-cm) x 1 ¼-inch (3-cm) pipes and 6 end caps. Remove all of the barcode stickers as they radionically give off negative energy.

Part 2 – Securing the End Caps

Now its time to put on one set of end caps and secure them with the bonding agent. If the end cap doesn't slide on easily, put it on a little bit and then bang it on the ground until it gives

The directions on the FastSteel say to avoid contact with your skin, so I put on a latex glove. I'm right handed so that's where it goes. FastSteel is labled a "Steel-Reinforced Epoxy Putty Stick." When it fully hardens, which takes about an hour, it forms a seriously solid bond. The amount I tore off is all that is needed to cover the seam on one end cap.

FastSteel is made up of two substances. One is black and it is rolled into the other one which is grey. I use my thumb and index finger to squish the two together until there is only one single dark grey color. The catalytic reaction begins immediately and you only have a few minutes before the stuff is too hard to shape. Quickly roll-pinch the blob into a worm-like shape.



Drape the worm over the end cap seam.

Press the worm of FastSteel into place, making sure the coverage is complete over the end cap seam. Repeat this procedure to finish off the other two pipes.

There. 3 pipes with one end sporting a watertight seal.

Part 3 – Adding in the Orgonite

Stand pipes up on some newspaper on a hard, flat surface. Put a nickel, shavings and crystals into each pipe. Mix up enough Sally Water enhanced resin to cover the shavings. The orgonite will only take up about an inch of space on the bottom of each pipe – just enough to keep a charge on the water we'll be adding later.

The copper rod is to make sure the shavings and resin are fully mixed together. I let the orgonite harden overnight.

Part 4 – Making the Coils

Cut three 26.5-inch (68-cm) lengths of 24-gauge copper wire.



Wrap each wire around a pencil into about a 5-inch (13-cm) long spiral coil.

Three finished coils.



Place one coil into each pipe. They should now be resting on top of the orgonite.

Part 5 – Making the Sally Water Inserts
(THIS PART IS OPTIONAL)

This is a coil of ¼-inch (0.6-cm) by 20-foot copper tubing.



Use your wire cutters to clip off three 3-inch (8-cm) sections of the tubing.

Take the hammer and flatten about ½-inch on one end of the tubing.



Use the pliers to bend the flattened end over. Again hammer that part flat.



Use the pliers to squeeze open the other end, as it was pinched close from the wire cutters.

Use a dropper to add some pure Sally Water to the tube.

Use a piece of your 24-gauge copper wire to work the air bubbles from the tube.

Pound the other end flat, being careful not to let too much water escape. Like before, fold over and pound flat again. Here are the 3 finished Sally Water Inserts.

Drop the Inserts into the pipes so that they end up resting next to the coils on the orgonite.

Part 6 – Filling the Pipes

I poured the water out of this gallon sized Arrowhead water bottle and replaced it with distilled water. Then I took my Sally Water Wand and stirred the distilled water for a few minutes, then just let it sit in the water for awhile, charging it up. This makes what is called "2nd Generation" Sally Water, as opposed to the pure 1st Generation stuff.

Pour the 2nd generation Sally Water into the pipes using the funnel to keep things neat. The waterline should be about ½-inch (1.5-cm) below the rim of the pipe.

I like to add ¼-teaspoon (1.5-ml) of pure Sally Water to each pipe.

Use the hammer to gently tap the top end caps into place.

Apply the FastSteel to the seams of the top end caps just as you did on the bottom ones. Try to keep the pipes upright this time so that the water doesn't dribble out.



Here's a closeup of the bond. Does it look solid? Originally I tried using other types of bonding agents including silicone sealant, but they all leaked or stunk. After making dozens of these wands I have yet to see the FastSteel fail.



Part 7 – Taping the Water Wand Pack

Take enough of the aluminum tape to fit around the three pipes (about 10-inches) and do the deed, making the fit snug. In this picture its obvious that one of the pipes was a little longer than the other two. This won't effect the performance of the device at all. It does show that every Trinity Wand will be unique in some small way.

Here's another angle. Notice the infinity symbols. That's how I mark the tops in case I decide to later deploy the Trinity Wand in a standing position.



Part 7 – Preparing the Mobius Wire

I start by placing a pushpin into my backyard fence. Then I wrap a few inches of the Insulated Wrapping wire around the pin.

Stepping backward, I unroll the spool until I reach the end. Remember to watch where you're going. ☺



I bring that end back to the fence and wrap it around the same pushpin. Now the wire is folded in half and ready for the drill. At this point you could go to the other end of the wire and cut it, making two shorter wires instead of just one long one. Then all you need to do is fold each of those shorter wires in half and get the drill, attaching the loose ends to the pushpin. Works either way - I just happen to like a longer wire on my Trinity Wands. Up to you.

Now I go back to the other end of the wire, taking my drill with a long extension cord to give me power where there are no electrical outlets. I stick the wire, along with a little piece of scrap wire, into where a drill bit would go. I add the second piece of wire in order to create a snug fit, making it harder for the wire to pop out unexpectedly.



Spin the wire counter-clockwise until the twists look about like this. Here you can see the little piece of yellow scrap wire.



Part 8 – Mobius Wrapping the Wand Pack

Lay your wand pack flat with the orgonite (bottom) end on your left. Find the end of your mobius wire that is split into two wires. Here I've trimmed mine to look as you see in the picture. Tape the wire to the top wand.



Wrap your mobius wire over the top of the wand pack (away from you) and bring it all the way around until it looks like the picture.



Roll the wand pack forward so that you can see the other side.



This is what it should look like after rolling the wand forward once, the top having come at you.



Here I'm showing you how the wire in your hand will cross over the top of the one already on the wand pack. This is called foreshadowing – I'm showing you how it will look ahead of time.



You can see that something has changed in this picture from the last. I put a heavy object – in this case, one of Cbswork's HHg's – on top of the mobius wire, to hold it in place while I grabbed the end of the wire. Once I had hold of the wire end, I started to thread it <u>behind</u> the one on the wand pack.



Now the threading is complete and I have grabbed the wire with my other hand…



And pulled. Notice I removed the HHg. I will need it again on my next pass.



Here is a closeup. There is really nothing difficult about this, but I want to make sure everyone understands that all I did was tuck the wire under the one that was already there. That's all there is to a mobius knot – the wire just keeps getting tucked under all previously laid wire.



Pull the wire tight.



Now wrap the wire around the wand pack again – over the top, under the bottom – and again set the weight on the wire to hold it.



Here is the closeup. Notice the wire is being threaded behind **both** of the previously laid wires, and not just the last one. This is the KEY to the mobius wrap. The wire being threaded will **always** go behind **all** of the wires in the current bundle.



Pull tight. Now you have two full turns of mobius wire around the wand pack. If you have the longer mobius wire (25-foot) then make another 7 turns around the wand pack doing it the same way. If you opted earlier to create the shorter mobius wire (12.5-foot) then make another 3 turns around the wand pack.

This picture shows what the mobius knot looks like after 9 turns of the wire around the wand pack.

Here is the closeup. Notice I was careful to keep the knot looking neat as it grew. It wasn't difficult to do at all since the wire wanted to follow a certain groove. Now its time to start the next knot.



Wrap the wire around the wand pack a turn or two until you are lined up in the middle. This is where you want to build your next knot. I usually flip the wand pack forward at this point so that the next knot has its own face (or side) of the wand pack.



And the process starts again. If you have the longer wire, make another 9-strand knot, otherwise make the 5-strand knot, just like on the last one.

Two mobius knots down, one to go. Start the next one on the last face (side) of the wand pack that doesn't yet have one.



The last knot may have more or less strands than the previous two knots. I don't always divide up the turns perfectly so the last knot usually has more strands than the others. The finished Trinity Wand will work great, regardless.



Okay, this is what the whole thing looks like so far.



Untape the end with the split wires. Its time to use the razor blade to remove the insulation from the ends of the wires.



This is what it should look like.



Now twist the two wires together.

Tape the twisted wires to the bare metal of one of the pipes.



Part 9 – Adding the Foil

Place the wand pack on the foil like so.



Cover the wand pack.



Press the foil into the ends of the wand pack and crease the sides of the foil.

Roll the wand pack into the foil.

Tape the foil seams and ends.

Mark the ‘up’ end. That’s it!

In Conclusion

Well, that's it. Now you have a very powerful and fully functional Trinity Wand. I like to bury one on my home property and the others at various locations around my community. Lorae Ireland says they are best buried alongside rivers or tossed into lakes. These units really come alive around water. But they work well buried anywhere. I like to stand mine up, orgonite end down, when I have the time and patience during deployments. Horizontal works fine too.

If resources are favorable, I build ten of the TWs together at an easy pace over a period of three days. On day 1 I cut the pipe, bond the end caps to one end, and pour the orgonite. On day 2 I seal the copper coils, Sally Water Inserts and 2nd generation Sally Water into the pipes. On day 3 I wrap the mobius coils around the units and put on the foil.

I've built Trinties using 3/4-inch, 1-inch, 1 1/4-inch and 1 1/2-inch copper pipe. According to Lorae, the bigger they are, the more powerful. I choose the 1 1/4-inch pipe mostly because of the favorable power-to-cost ratio. If I could afford it, I'd be using the 2-inch pipe. The first ones I made for Lorae's summer 2000 western gifting spree were the 1 1/2-inch size. Later I sent her the 3/4-inch ones because money had gotten tight, but according to her those were nowhere near as powerful.

See here for Lorae Ireland's (Captainmcgoo on forums.cloud-busters.com) Trinity Wand deployment adventures across the western U.S.:

http://forums.cloud-busters.com/files/captainmcgoo...
click on "20000 miles of orgonite.doc"

See here for forums.cloud-busters.com member Cbswork's thoughts on the Trinties:

http://blogs.cloud-busters.com/dor2or/13/

The inventor of the Trinity Wand – Al Gray – can be reached at dragon@cgmailbox.com. He is a vendor for these devices.

Other Trinity Wand vendors include:

Steeve (Sdbmark at forums.cloud-busters.com):

http://www.quebecorgone.com/

Zoe (Slash.dot.z at forums.cloud-busters.com):

zoe@6dweb.com

Happy Gifting,

Jon