

Created on....17.08.2016      Last changed on/by..... 29.06.2026 ABAP7  
Author.....ABAP4

---

Title.....SAP-ASRS SQL Data Push

Type.....1      Reporting  
Status.....  
Application.....  
Class.....  
Logical database.....  
    from Application....  
Selection screen.....  
Authorization group...  
Package.....ZMM

    Start by Variants  
    Deactivate editor lock  
X Fixed point arithmetic active

```
1  *&-----*
2  *& Report  ZDEMO_SQL_ASRS_SAP
3  *&
4  *&-----*
5  *&
6  *&
7  *&-----*
8
9  REPORT zmm_sql_asrs_sap_push_mat.
10
11  TABLES: zmm_asrs.
12
13  SELECT-OPTIONS: s_type for zmm_asrs-msg_trans_type.
14
15  DATA: gs_asrs TYPE zmm_asrs,
16         gt_asrs TYPE STANDARD TABLE OF zmm_asrs,
17         gt_con  TYPE STANDARD TABLE OF zmm_dbcon_asrs,
18         gs_con  TYPE zmm_dbcon_asrs.
19  FIELD-SYMBOLS <fs_asrs> TYPE zmm_asrs.
20  DATA: dbs TYPE dbcon-con_name.
21  DATA: con(20) TYPE c.
22
23
24  START-OF-SELECTION.
25
26      SELECT *
27          FROM zmm_dbcon_asrs
28          INTO TABLE gt_con.
29
30
31
32
33
34
35
36  *WRITE sy-subrc.
37
38
39
40  DATA: lv_date TYPE char10.
41  DATA: lv_date1 TYPE char10.
42  DATA: lv_date2 TYPE char10.
43  SELECT *
44      FROM zmm_asrs
45      INTO CORRESPONDING FIELDS OF TABLE gt_asrs
46      WHERE msg_trans_type in s_type
47      AND trf_status = 'N'.
48  *  lv_date = sy-datum.
49  *  exec SQL.
50  *      SELECT MSG_REC_ID   FROM HOST_TO_WMS_TEST INTO :gs_asrs-msg_rec_id
51  *  ENDEXEC.
52  DATA: exc_ref    TYPE REF TO cx_sy_native_sql_error,
53         error_text TYPE string.
54
55  SORT gt_asrs BY plant.
56  LOOP AT gt_asrs ASSIGNING <fs_asrs>.
57      ON CHANGE OF <fs_asrs>-plant.
58          READ TABLE gt_con INTO gs_con WITH KEY werks = <fs_asrs>-plant.
59          IF sy-subrc <> 0.
60              CONTINUE.
61          ENDIF.
```

```
62      TRY.
63          IF con IS NOT INITIAL.
64              EXEC SQL.
65                  DISCONNECT :con
66              ENDEXEC.
67          ENDIF.
68          CLEAR con.
69          EXEC SQL. "#EC CI_EXECSQL
70              CONNECT TO :gs_con-DBCON
71          ENDEXEC.
72          EXEC SQL. "#EC CI_EXECSQL
73              GET CONNECTION :CON
74          ENDEXEC.
75          EXEC SQL.
76              SET CONNECTION :gs_con-DBCON
77          ENDEXEC.
78          CATCH cx_sy_native_sql_error INTO exc_ref.
79      ENDTRY.
80  ENDON.
81  gs_asrs = <fs_asrs>.
82
83  lv_date = gs_asrs-msg_dt_def.
84  IF gs_asrs-msg_dt_trm IS NOT INITIAL.
85      lv_date1 = gs_asrs-msg_dt_trm.
86  ENDIF.
87  IF gs_asrs-mfg_date IS NOT INITIAL.
88      lv_date2 = gs_asrs-mfg_date.
89  ENDIF.
90  TRY.
91      EXEC SQL.
92          INSERT INTO host_to_wms (MSG_SRC,
93                                  MSG_REC_ID,
94                                  MSG_TRANS_TYPE,
95                                  MSG_ACTION,
96                                  MSG_DT_DEF,
97                                  MSG_STAT,
98                                  MAT_CODE,
99                                  DESCRIPTION,
100                                 UOM,
101                                 ITEM_TYPE)
102          VALUES (
103                  :gs_asrs-MSG_SRC ,
104                  :gs_asrs-MSG_REC_ID ,
105                  :gs_asrs-MSG_TRANS_TYPE ,
106                  :gs_asrs-MSG_ACTION ,
107                  :lv_date,
108                  :gs_asrs-MSG_STAT ,
109                  :gs_asrs-MAT_CODE ,
110                  :gs_asrs-DESCRIPTION ,
111                  :gs_asrs-UOM ,
112                  :gs_asrs-ITEM_TYPE)
113      ENDEXEC.
114      CATCH cx_sy_native_sql_error INTO exc_ref.
115          error_text = exc_ref->get_text( ).
116
117      CONTINUE.
118  ENDTRY.
119
120  COMMIT WORK AND WAIT .
121
122  * EXEC SQL.
```

```
123 *      DISCONNECT :con
124 *      ENDEXEC.
125      <fs_asrs>-trf_status  = 'Y'.
126      ENDLOOP.
127
128      IF con IS NOT INITIAL.
129          EXEC SQL.
130              DISCONNECT :con
131              ENDEXEC.
132      ENDIF.
133      MODIFY zmm_asrs FROM TABLE gt_asrs.
```

Title:  
SAP-ASRS SQL Data Push

---

Selection texts:

S\_TYPE  
D .

DATABASE OPERATIONS

SELECT:

|                                               | Line | Page |
|-----------------------------------------------|------|------|
| ZMM_ASRS..... ZMM_SQL_ASRS_SAP_PUSH_MAT       | 44   | 2    |
| ZMM_DBCON_ASRS..... ZMM_SQL_ASRS_SAP_PUSH_MAT | 27   | 2    |

---

MODIFY:

|                                         | Line | Page |
|-----------------------------------------|------|------|
| ZMM_ASRS..... ZMM_SQL_ASRS_SAP_PUSH_MAT | 133  | 4    |

---

INTERNAL TABLE OPERATIONS

READ TABLE:

|                                       | Line | Page |
|---------------------------------------|------|------|
| GT_CON..... ZMM_SQL_ASRS_SAP_PUSH_MAT | 58   | 2    |

---