Main Memory (Part I)

Amir H. Payberah amir@sics.se

Amirkabir University of Technology (Tehran Polytechnic)



Motivation and Background

▶ Main memory is a large array of bytes, each with its own address.

- ▶ Main memory is a large array of bytes, each with its own address.
- Program must be brought (from disk) into memory and placed within a process for it to be run.
 - Machine instructions may take memory addresses as arguments, but not disk addresses.

- ▶ Main memory is a large array of bytes, each with its own address.
- ▶ Program must be brought (from disk) into memory and placed within a process for it to be run.
 - Machine instructions may take memory addresses as arguments, but not disk addresses.
- ► The CPU fetches instructions from memory according to the value of the program counter.

- ▶ Main memory is a large array of bytes, each with its own address.
- ▶ Program must be brought (from disk) into memory and placed within a process for it to be run.
 - Machine instructions may take memory addresses as arguments, but not disk addresses.
- ► The CPU fetches instructions from memory according to the value of the program counter.
- ► These instructions may cause additional loading from and storing to specific memory addresses.

► Main memory and registers are the only storage that the CPU can access directly.

- Main memory and registers are the only storage that the CPU can access directly.
- ► Register access in one CPU clock (or less)

- Main memory and registers are the only storage that the CPU can access directly.
- ► Register access in one CPU clock (or less)
- ▶ Main memory can take many cycles, causing a stall.

- ► Main memory and registers are the only storage that the CPU can access directly.
- ► Register access in one CPU clock (or less)
- Main memory can take many cycles, causing a stall.
- ► <u>Cache sits between main memory and registers</u>.

▶ We must protect the OS from access by user processes.


- ▶ We must protect the OS from access by user processes.
- ▶ We must protect user processes from one another.

- ▶ We must protect the OS from access by user processes.
- ▶ We must protect user processes from one another.
- ► This protection is provided by the hardware.

- We must protect the OS from access by user processes.
- ▶ We must protect user processes from one another.
- ► This protection is provided by the hardware.
- ► A separate memory space for each process.
 - Determining the range of legal addresses that the process may access.


Base and Limit Registers

- ► A pair of base and limit registers define the logical address space.
- ► CPU must check every memory access generated in user mode to be sure it is between base and limit for that user.



Hardware Address Protection

Any attempt by a <u>user program</u> to <u>access</u> OS memory or other <u>users' memory results</u> in a trap to the OS, which treats the attempt as a <u>fatal error</u>.



Address Binding

► Programs on disk, ready to be brought into memory to execute form an input queue.

- ► Programs on disk, ready to be brought into memory to execute form an input queue.
- ► A <u>user process can reside in any part of the physical memory.</u>
 - Without support, must be loaded into address 00000.

▶ A user program goes through several steps before being executed.

- ▶ A user program goes through several steps before being executed.
- ► Addresses may be represented in different ways during these steps.

- ▶ A user program goes through several steps before being executed.
- ► Addresses may be represented in different ways during these steps.
 - Source code addresses usually symbolic.


- ▶ A user program goes through several steps before being executed.
- ► Addresses may be represented in different ways during these steps.
 - Source code addresses usually symbolic.
 - A compiler typically binds these symbolic addresses to relocatable addresses, e.g., 14 bytes from beginning of this module.

?

- ► A user program goes through several steps before being executed.
- ► Addresses may be represented in different ways during these steps.
 - Source code addresses usually symbolic.
 - A compiler typically binds these symbolic addresses to relocatable addresses, e.g., 14 bytes from beginning of this module.
 - Linker or loader will bind relocatable addresses to absolute addresses, e.g., 74014.


Binding of Instructions and Data to Memory (1/3)

 Address binding of instructions and data to memory addresses can happen at three different stages.




Binding of Instructions and Data to Memory (1/3)

- Address binding of instructions and data to memory addresses can happen at three different stages.
- Compile time: if memory location known a priori, absolute code can be generated.
 - <u>Must recompile code</u> if starting location changes.



Binding of Instructions and Data to Memory (2/3)


- ► Load time: must generate relocatable code if memory location is not known at compile time.
 - Final binding is delayed until load time.
 - If the starting address changes, we need only reload the user code to incorporate this changed value.



Binding of Instructions and Data to Memory (3/3)

Execution time: binding delayed until run time if the process can be moved during its execution from one memory why? egment to another.

Need hardware support



Logical vs. Physical Address Space (1/2)

- ► Logical address (virtual address): address generated by the CPU.
 - Logical address space is the set of all logical addresses generated by a program.

Logical vs. Physical Address Space (1/2)

- ► Logical address (virtual address): address generated by the CPU.
 - Logical address space is the set of all logical addresses generated by a program.
- Physical address: address seen by the memory unit.
 - Physical address space is the set of all physical addresses generated by a program.

Logical vs. Physical Address Space (1/2)

- ► Logical address (virtual address): address generated by the CPU.
 - Logical address space is the set of all logical addresses generated by a program.
- Physical address: address seen by the memory unit.
 - Physical address space is the set of all physical addresses generated by a program.
- ► The concept of a logical address space that is bound to a separate physical address space is central to proper memory management.

Logical vs. Physical Address Space (2/2)

why?


- ► Logical and physical addresses are the same in compile-time and load-time address-binding schemes.
- Logical and physical addresses differ in execution-time address-binding scheme.

Memory-Management Unit (MMU) (1/2)

► Hardware device that at run time maps virtual to physical address.


Memory-Management Unit (MMU) (1/2)

- Hardware device that <u>at run time</u> maps virtual to physical <u>address</u>.
- As a simple scheme, the value in the relocation register is added to every address generated by a user process at the time it is sent to memory.
 - Base register now called <u>relocation register</u>.




Memory-Management Unit (MMU) (2/2)

- ► Two different types of addresses:
 - Logical addresses: range 0 to max
 - ullet Physical addresses: range R + 0 to R + max for a base value R




Memory-Management Unit (MMU) (2/2)

- ► Two different types of addresses:
 - Logical addresses: range 0 to max
 - Physical addresses: range R + 0 to R + max for a base value R
- ► The user program generates only logical addresses and thinks that the process runs in locations 0 to max.



Memory-Management Unit (MMU) (2/2)

- Two different types of addresses:
 - Logical addresses: range 0 to max
 - Physical addresses: range R + 0 to $R + \max$ for a base value R
- ► The user program generates only logical addresses and thinks that the process runs in locations 0 to max.
- ► These logical addresses must be mapped to physical addresses before they are used.



Dynamic Linking and Loading

► Routine/library is not loaded until it is called.

- ► Routine/library is not loaded until it is called.
- ► The main program is loaded into memory and is executed.

- ► Routine/library is not loaded until it is called.
- ▶ The main program is loaded into memory and is executed.
- When a routine is needed, if it has not been loaded, the loader loads the desired routine into memory and to update the program's address tables to reflect this change.

- Routine/library is not loaded until it is called.
- ► The main program is loaded into memory and is executed.
- When a routine is needed, if it has not been loaded, the loader loads the desired routine into memory and to update the program's address tables to reflect this change.
- ► Then control is passed to the newly loaded routine.

- Routine/library is not loaded until it is called.
- ► The main program is loaded into memory and is executed.
- When a routine is needed, if it has not been loaded, the loader loads the desired routine into memory and to update the program's address tables to reflect this change.
- ► Then control is passed to the newly loaded routine.
- All routines kept on disk in relocatable load format.

▶ Better memory-space utilization; unused routine is never loaded.

- ▶ Better memory-space utilization; unused routine is never loaded.
- Useful when large amounts of code are needed to handle infrequently occurring cases.

- ▶ Better memory-space utilization; unused routine is never loaded.
- Useful when large amounts of code are needed to handle infrequently occurring cases.
- ► No special support from the OS is required.

- ▶ Better memory-space utilization; unused routine is never loaded.
- Useful when large amounts of code are needed to handle infrequently occurring cases.
- ▶ No special support from the OS is required.
- ► Implemented through program design.

- ▶ <u>Better memory-space utilization</u>; unused routine is never loaded.
- Useful when large amounts of code are needed to handle infrequently occurring cases.
- ▶ No special support from the OS is required.
- ► <u>Implemented through program design</u>.
- ► OS can help by providing libraries to implement dynamic loading.

► Static linking: system libraries and program code combined by the loader into the binary program image.

- ► Static linking: system libraries and program code combined by the loader into the binary program image.
- ▶ Dynamic linking: linking postponed until execution time.

- ► Static linking: system libraries and program code combined by the loader into the binary program image.
- ▶ Dynamic linking: linking postponed until execution time.
- ► Stub: small piece of code, used to locate the appropriate memory-resident library routine.

- ► Static linking: <u>system libraries and program code</u> combined by the loader <u>into the binary program image</u>.
- ► Dynamic linking: <u>linking postponed until</u> execution time.
- ► Stub: <u>small piece of code</u>, <u>used to locate the appropriate</u> <u>memory-resident library routine</u>.
- ► Stub replaces itself with the address of the routine, and executes the routine.

▶ OS checks if routine is in processes memory address.


- ▶ OS checks if routine is in processes memory address.
- ▶ If not in address space, add to address space.

- OS checks if routine is in processes memory address.
- ▶ If not in address space, add to address space.
- ► Dynamic linking is particularly useful for shared libraries.


Swapping

► A process can be swapped temporarily out of memory to a backing store, and then brought back into memory for continued execution.

- A process can be swapped temporarily out of memory to a backing store, and then brought back into memory for continued execution.
- Backing store: fast disk large enough to accommodate copies of all memory images for all users; must provide direct access to these memory images.



- A process can be swapped temporarily out of memory to a backing store, and then brought back into memory for continued execution.
- Backing store: fast disk large enough to accommodate copies of all memory images for all users; must provide direct access to these memory images.
- Total memory space of processes can exceed physical memory.



▶ Does the swapped out process need to swap back in to same physical addresses?

- ▶ Does the swapped out process need to swap back in to same physical addresses?
 - Depends on address binding method.

- ▶ Does the swapped out process need to swap back in to same physical addresses?
 - Depends on address binding method.
- ▶ Pending I/O: cannot swap out as I/O would occur to wrong process.

- Does the swapped out process need to swap back in to same physical addresses?
 - · Depends on address binding method.
- Pending I/O: cannot swap out as I/O would occur to wrong process.
 - Or always transfer I/O to kernel space, then to I/O device.
 - Known as double buffering, adds overhead.

- Standard swapping not used in modern OSs, but modified version is common.
- Swap only when free memory extremely low.
- ▶ <u>Disabled again once memory demand reduced below threshold.</u>

Swapping Cost

► Major part of swap time is transfer time; which is proportional to the amount of memory swapped.

Swapping Cost

- ► Major part of swap time is transfer time; which is proportional to the amount of memory swapped.
- ▶ If next processes to be put on CPU is not in memory, need to swap out a process and swap in target process.

Swapping Cost

- ► Major part of swap time is transfer time; which is proportional to the amount of memory swapped.
- ▶ If next processes to be put on CPU is not in memory, need to swap out a process and swap in target process.
- Example:
 - 100MB process swapping to hard disk with transfer rate of 50MB/sec.
 - Swap out time of 2s + swap in of same sized process.
 - Total context switch swapping component time of 4s.

Swapping on Mobile Systems (1/2)

► Not typically supported.

Swapping on Mobile Systems (1/2)

- ► Not typically supported.
- ► Flash memory based
 - Small amount of space
 - <u>Limited number of write cycles</u>
 - Poor throughput between flash memory and CPU on mobile platform

Swapping on Mobile Systems (2/2)

▶ Instead use other methods to free memory if low.

Swapping on Mobile Systems (2/2)

- ▶ Instead use other methods to free memory if low.
- ▶ iOS asks apps to voluntarily relinquish allocated memory.

Swapping on Mobile Systems (2/2)

- ▶ Instead use other methods to free memory if low.
- ▶ iOS asks apps to voluntarily relinquish allocated memory.
- ► Read-only data thrown out and reloaded from flash if needed.

Swapping on Mobile Systems (2/2)

- ▶ Instead use other methods to free memory if low.
- ▶ iOS asks apps to voluntarily relinquish allocated memory.
- ► Read-only data thrown out and reloaded from flash if needed.
- ▶ Failure to free can result in termination.

Swapping on Mobile Systems (2/2)

- ▶ Instead use other methods to free memory if low.
- ► <u>iOS</u> <u>asks apps</u> to voluntarily relinquish allocated memory.
- Read-only data thrown out and reloaded from flash if needed.
- ► Failure to free can result in termination.
- Android terminates apps if low free memory, but first writes application state to flash for fast restart.

Contiguous Memory Allocation


► Main memory must support both OS and user processes.

- ▶ Main memory must support both OS and user processes.
- ► Limited resource, must allocate efficiently.


- ▶ Main memory must support both OS and user processes.
- ▶ Limited resource, must allocate efficiently.
- ► Contiguous allocation is one early method.

- ▶ Main memory must support both OS and user processes.
- ► <u>Limited resource</u>, must <u>allocate efficiently</u>.
- ► Contiguous allocation is one early method.
- ► Main memory usually into two partitions:
 - Resident OS, usually held in low memory with interrupt vector.
 - <u>User processes</u> then held in high memory.
 - Each process contained in single contiguous section of memory.


- Relocation registers used to protect user processes from each other, and from changing OS code and data.
 - Base register contains value of smallest physical address.
 - Limit register contains range of logical addresses.
 - MMU maps logical address dynamically.




► Memory is to divide memory into several fixed-sized partitions.




- Memory is to divide memory into several fixed-sized partitions.
- ► Each partition may contain exactly one process.



- Memory is to divide memory into several fixed-sized partitions.
- ► Each partition may contain exactly one process.
- ▶ Degree of multiprogramming limited by number of partitions.



- Memory is to divide memory into several fixed-sized partitions.
- ► Each partition may contain exactly one process.
- ▶ Degree of multiprogramming limited by <u>number of partitions.</u>
- When a partition is free, a process is selected from the input queue and is loaded into the free partition.



 Variable-partition sizes for efficiency (sized to a given process' needs).

- Variable-partition sizes for efficiency (sized to a given process' needs).
- Hole: block of available memory.

- Variable-partition sizes for efficiency (sized to a given process' needs).
- ▶ Hole: block of available memory.
- ► When a process arrives, it is allocated memory from a hole large enough to accommodate it.

- Variable-partition sizes for efficiency (sized to a given process' needs).
- Hole: block of available memory.
- ▶ When a process arrives, it is allocated memory from a hole large enough to accommodate it.
- ► Process exiting frees its partition, adjacent free partitions combined

- ► Variable-partition sizes for efficiency (sized to a given process' needs).
- Hole: block of available memory.
- ► When a process arrives, it is allocated memory from a hole large enough to accommodate it.
- Process exiting frees its partition, adjacent free partitions combined
- ► OS maintains information about: allocated partitions and free partitions (hole)

► How to satisfy a request of size n from a list of free holes?

- ► How to satisfy a request of size n from a list of free holes?
- ► First-fit: allocate the first hole that is big enough

- ▶ How to satisfy a request of size n from a list of free holes?
- ► First-fit: allocate the first hole that is big enough
- ▶ Best-fit: allocate the smallest hole that is big enough
 - Must search entire list, unless ordered by size.
 - Produces the smallest leftover hole.

- ▶ How to satisfy a request of size n from a list of free holes?
- ► First-fit: allocate the first hole that is big enough
- ▶ Best-fit: allocate the smallest hole that is big enough
 - Must search entire list, unless ordered by size.
 - · Produces the smallest leftover hole.
- Worst-fit: allocate the largest hole
 - Must also search entire list.
 - Produces the largest leftover hole.

- ► How to satisfy a request of size n from a list of free holes?
- ► First-fit: allocate the first hole that is big enough
- ▶ Best-fit: allocate the smallest hole that is big enough
 - Must search entire list, unless ordered by size.
 - Produces the smallest leftover hole.
- Worst-fit: allocate the largest hole
 - Must also search entire list.
 - Produces the largest leftover hole.
- ► First-fit and best-fit better than worst-fit in terms of speed and storage utilization.

► External fragmentation: total memory space exists to satisfy a request, but it is not contiguous.

- External fragmentation: total memory space exists to satisfy a request, but it is not contiguous.
- ▶ Internal fragmentation: allocated memory may be slightly larger than requested memory; this size difference is memory internal to a partition, but not being used.



- External fragmentation: <u>total memory space exists to satisfy a</u> request, but it is not contiguous.
- ► Internal fragmentation: allocated memory may be slightly larger than requested memory; this size difference is memory internal to a partition, but not being used.
- ► First fit analysis reveals that given N blocks allocated, 0.5N blocks lost to fragmentation: 50-percent rule

► Compaction: a solution to the problem of external fragmentation.

- ► Compaction: a solution to the problem of external fragmentation.
- Shuffle memory contents to place all free memory together in one large block.

- ► Compaction: a solution to the problem of external fragmentation.
- Shuffle memory contents to place all free memory together in one large block.
- Compaction is possible only if relocation is dynamic, and is done at execution time.


page 364

- ► Compaction: a <u>solution</u> to the problem of <u>external fragmentation</u>.
- ► Shuffle memory contents to place all free memory together in one large block.
- Compaction is possible only if relocation is dynamic, and is done at execution time.
- ? ► I/O problem
 - Latch job in memory while it is involved in I/O
 - Do I/O only into OS buffers.


- Another possible solution to the external fragmentation problem: permit the logical address space of the processes to be noncontiguous.
- ► Two techniques:
 - Segmentation
 - Paging


Segmentation

- Memory-management scheme that supports user view of memory.
- A program is a collection of segments.
- A segment is a logical unit such as:
 - Main program
 - Procedure
 - Function
 - Object
 - ...



Logical View of Segmentation





physical memory space

Segmentation Architecture

► Logical address consists of a tuple: ⟨segment_number, offset⟩


Segmentation Architecture


- ► Logical address consists of a tuple: ⟨segment_number, offset⟩
- ► Segment table: maps two-dimensional user-defined addresses into one-dimensional physical address.

Segmentation Architecture


- ► <u>Logical address consists of a tuple</u>: <u>⟨segment_number, offset⟩</u>
- Segment table: maps <u>two-dimensional</u> user-defined addresses into <u>one-dimensional</u> physical address.
- Each table entry has:
 - <u>Base</u>: contains the starting physical address where the segments reside in memory
 - Limit: specifies the length of the segment

Segmentation Hardware







▶ A reference to byte 53 of segment 2:




▶ A reference to byte 53 of segment 2: 4300 + 53 = 4353




- ▶ A reference to byte 53 of segment 2: 4300 + 53 = 4353
- ► A reference to byte 852 of segment 3:



- ▶ A reference to byte 53 of segment 2: 4300 + 53 = 4353
- ▶ A reference to byte 852 of segment 3: 3200 + 852 = 4052



- ▶ A reference to byte 53 of segment 2: 4300 + 53 = 4353
- \blacktriangleright A reference to byte 852 of segment 3: 3200 + 852 = 4052
- ▶ A reference to byte 1222 of segment 0:



- ▶ A reference to byte 53 of segment 2: 4300 + 53 = 4353
- ▶ A reference to byte 852 of segment 3: 3200 + 852 = 4052
- ► A reference to byte 1222 of segment 0: trap to OS

► Main memory

- ► Main memory
- ► Address protection: base + limit

- ► Main memory
- ► Address protection: base + limit
- ► Address binding: compile time, load time, execution time

- ► Main memory
- ► Address protection: base + limit
- ► Address binding: compile time, load time, execution time
- Logical and physical address, MMU

- Main memory
- Address protection: base + limit
- ► Address binding: compile time, load time, execution time
- Logical and physical address, MMU
- Swapping: backing store, swapping cost

- Main memory
- ► Address protection: base + limit
- ► Address binding: compile time, load time, execution time
- Logical and physical address, MMU
- Swapping: backing store, swapping cost
- Contiguous memory allocation: partitions, holes, first-fit, best-fit, worst-fit

- Main memory
- ► Address protection: base + limit
- ► Address binding: compile time, load time, execution time
- Logical and physical address, MMU
- Swapping: backing store, swapping cost
- Contiguous memory allocation: partitions, holes, first-fit, best-fit, worst-fit
- External and internal fragmentation: compaction, segmentation, paging

- Main memory
- ► Address protection: base + limit
- Address binding: compile time, load time, execution time
- Logical and physical address, MMU
- Swapping: backing store, swapping cost
- Contiguous memory allocation: partitions, holes, first-fit, best-fit, worst-fit
- External and internal fragmentation: compaction, segmentation, paging
- ► <u>Segmentation</u>: <u>noncontiguous address</u>, <u>user view of memory</u>

Questions?

Acknowledgements

Some slides were derived from Avi Silberschatz slides.