# Llamadas al sistema

Programando llamadas al sistema en forma manual

## **Hello World!!**

- Para programar un hello world necesitamos hacer 2 llamadas al sistema:
  - Escribir en pantalla el mensaje
  - Terminar el proceso
- Por ello tendremos que hacer uso de las siguientes llamadas al sistema:
  - write (man 2 write)
  - exit (man exit)

## Hello World en x86-32bit

- En x86-32bit las sistem calls tienen los siguientes números:
  - write → syscall número 4
  - exit → syscall número 1
- Linux-2.6.34.14/arch/x86/include/asm/unistd\_32.h

```
* This file contains the system call numbers.
#define
         NR restart syscall
#define
         NR exit
#define
         NR fork
#define
         NR read
#define
         NR write
#define -
         NR open
#define
         NR close
#define
         NR waitpid
#define
         NR creat
#define _
         NR link
#define
         NR unlink
         NR execve
#define
                         11
         NR chdir
                         12
                         13
```

# Hello World en x86-32bit (cont)

 Los manuales de las system calls permiten saber cuales son los parámetros

```
ssize_t write(int fd, const void *buf, size_t count);

DESCRIPTION
    write() writes up to count bytes from the buffer pointed buf to the file referred to by the file descriptor fd.

NAME
    exit - cause normal process termination

SYNOPSIS
    #include <stdlib.h>
    void exit(int status);

DESCRIPTION
    The exit() function causes normal process termination and the value of status & 0377 is returned to the parent (see wait(2)).
```

write - write to a file descriptor

#include <unistd.h>

NAME

SYNOPSIS

```
NAME
                    write - write to a file descriptor
             SYNOPSIS
                    #include <unistd.h>
                    ssize_t write(int fd, const void *buf, size_t count);
             DESCRIPTION
                    write() writes up to count bytes from the buffer pointed buf to the
                    file referred to by the file descriptor fd.
   ; sys_write(stdout, message, length)
   mov eax, 4
                ; sys_write syscall
   mov ebx, 1 ; stdout
   mov ecx, message ; message address
   mov edx, length ; message string length
   int 80h
   ; sys_exit(return_code)
   mov eax, 1 ; sys_exit syscall
   mov ebx, 0 ; return 0 (success)
   int 80h
section .data
   message: db 'Hello, world!',0x0A ; message and newline
              NAME
                     exit - cause normal process termination
              SYNOPSIS
                     #include <stdlib.h>
                     void exit(int status);
              DESCRIPTION
                     The exit() function causes normal process termination and the value of
                     status & 0377 is returned to the parent (see wait(2)).
```

start:

## Hello World en x86-64bit

- En x86-64bit las sistem calls tienen los siguientes números:
  - write → syscall número 1
  - exit → syscall número 60
- Linux-2.6.34.14/arch/x86/include/asm/unistd\_64.h

```
#define __NR_vfork 58
_SYSCALL(_NR_vfork, stub_vfork)
#define __NR_execve 59
_SYSCALL(_NR_execve, stub_execve)
#define __NR_exit 60
_SYSCALL(_NR_exit, sys_exit)
#define __NR_wait4 61
_SYSCALL(_NR_wait4, sys_wait4)
#define __NR_kill 62
_SYSCALL(_NR_kill, sys_kill)
#define __NR_uname 63
```

# Hello World en x86-64bit (cont)

- Se usan los mismos manuales de las system call que para el caso anterior
- Lo que cambia es el número de system call, el cual está en el kernel, no en el manual de la misma.
- Los procesadores X86-64 usan un esquema de registros diferentes.
- Se usa la instrucción syscall en lugar de la instrucción int 80h

```
NAME
                write - write to a file descriptor
         SYNOPSIS
                #include <unistd.h>
                ssize_t write(int fd, const void *buf, size_t count);
         DESCRIPTION
                write() writes up to count bytes from the buffer pointed buf to the
                file referred to by the file descriptor fd.
   ; sys_write(stdout, message, length)
         rax, 1
                    ; sys_write
         rdi, 1
                   ; stdout
         rsi, message ; message address
   mov rdx, length; message string length
   syscall
  ; sys_exit(return_code)
         rax, 60
                   ; sys exit
         rdi. 0
                   ; return 0 (success)
   syscall
section .data
   message: db 'Hello, world!', 0x0A ; message and newline
   length:
                  $-message
                           ; NASM definition pseudo-instruction
            eau
          NAME
                  exit - cause normal process termination
          SYNOPSIS
                  #include <stdlib.h>
                  void exit(int status);
```

#### DESCRIPTION

mov

mov

mov

The exit() function causes normal process termination and the value of status & 0377 is returned to the parent (see wait(2)).

# Referencias

### Como programar un "hello world" en x86 32bit y 64bit

http://blog.markloiseau.com/2012/05/64-bit-hello-world-in-linux-assembly-nasm/

#### Alternativas para pasar parametros a las system calls

http://www.int80h.org/bsdasm/#system-calls