CHEME 133 Module 4: Analysis of American-Style Composite Options Contracts at Expiration

Jeffrey D. Varner Smith School of Chemical and Biomolecular Engineering Cornell University, Ithaca NY 14853

Introduction

Composite options contracts are financial instruments that are composed of two or more individual options contracts. The payoff and profite of a composite contract at expiration is the sum of the values of the individual contracts. The advantage of constructing composite contracts is that they can be used to construct complex payoffs and profits startegies from simple contract components. In this module, we will analyze composite contracts at expiration, where the composite contract is composed of two or more American-style options.

General Formulation

Call and put contracts can be combined to develop composite contract structures with interesting payoff diagrams. Let \mathcal{C} be a composite contract with d legs (individual contracts) where each leg is written with respect to the same underlying asset XYZ and same expiration date. Then, the payoff of the composite contract $\hat{V}(S(T), K_1, \ldots, K_d)$ at time T (expiration) is given by:

$$\hat{V}(S(T), K_1, \dots, K_d) = \sum_{i \in \mathcal{C}} \theta_i \cdot n_i \cdot V_i(S(T), K_i)$$
(1)

where K_i denotes the strike price of contract i, θ_i denotes the contract orientation i: $\theta_i = -1$ if contract i is short (sold), otherwise $\theta_i = 1$, and the quantity n_i denotes the copy number of contract i. The profit of the composite contract \hat{P} at time T (expiration) is given by:

$$\hat{P}(S(T), K_1, \dots, K_d) = \sum_{i \in \mathcal{C}} \theta_i \cdot n_i \cdot P_i(S(T), K_i)$$
(2)

where $P_i(S(T), K_i)$ denotes the profit of contract i. Finally, the profit for contract of type \star is given by:

$$P_{\star}(K, S(T)) = V_{\star}(K, S(T)) - \mathcal{P}_{\star}(K, S(0))$$
(3)

where $\mathcal{P}_{\star}(K, S(0))$ denotes the premium of contract \star , and $V_{\star}(K, S(T))$ denotes the payoff of contract \star at expiration.

Defined-Risk Directional Composite Contracts

Directional composite contracts make a directional assumption about the price movement of the underlying asset, and can be opened for a credit or a debit. A common directional composite contract is a *spread*.

Put Vertical Spread

A put vertical spread is constructed by combining $2 \times \text{put}$ contracts, a short put contract generates income while a long put contract controls downside risk. Let contract j have a strike price of K_j and premium \mathcal{P}_j . The share price at expiration is given by S. Finally, let contract 1 be the short put leg $\theta_1 = -1$ and contract 2 be the long put leg $\theta_2 = 1$. Then, the profit for a single put vertical spread at expiration is given by:

$$\hat{P} = -P_1 + P_2 \tag{4}$$

which, after substitution of the profit functions for a put contract, gives:

$$\hat{P} = (K_2 - S)^+ - (K_1 - S)^+ + (\mathcal{P}_1 - \mathcal{P}_2)$$
(5)

where $V_p = (K - S)^+ = \max(K - S, 0)$ is the payoff function for a put contract. The first term is the net payout of the two legs of the spread, while the second term is the net cost of the two contracts. The maximum possible profit, loss, and breakeven conditions are given by:

- The maximum possible profit of $(\mathcal{P}_1 \mathcal{P}_2)$ will occur when $S \geq K_1$.
- The maximum possible loss of $K_2 K_1 + (\mathcal{P}_1 \mathcal{P}_2)$ will occur when $S \leq K_2$.
- The vertical put spread will breakeven when $S = K_1 + (\mathcal{P}_2 \mathcal{P}_1)$.

Bearish call credit spread

A bear call credit spread, is an options strategy used when a trader expects a decline in the price of the underlying asset. Assume the initial share price of the underlying asset is S_o (when we are opening the trade). For this trade, we sell a call contract at $K_1 < S_o$ for \mathcal{P}_1 , and buy a call contract at $K_2 > S_o$ for \mathcal{P}_2 . The profit function for the bear call credit spread is given by:

$$\hat{P} = (S - K_2)^+ - (S - K_1)^+ + (\mathcal{P}_1 - \mathcal{P}_2)$$
(6)

where $V_c = (S - K)^+ = \max(S - K, 0)$ is the payoff function for a call contract. The first two terms are the net payout of the two legs of the spread, while the last term is the net cost of the two contracts. The maximum possible profit, loss, and breakeven conditions are given by:

- The maximum possible profit of $(\mathcal{P}_1 \mathcal{P}_2)$ will occur when $S \leq K_1$.
- The maximum possible loss of $(\mathcal{P}_1 \mathcal{P}_2) (K_2 K_1)$ will occur when $S \geq K_2$.
- The bear call spread will breakeven when $S = K_1 + (\mathcal{P}_1 \mathcal{P}_2)$.

Neutral Composite Contracts

Neutral composite contracts make no directional assumption about the price movement of the underlying asset, and can be opened for a credit or a debit. Two common directional composite contracts are the *straddle* and the *strangle*.

Straddles

A straddle is a neutral strategy constructed by simultaneously buying (or selling) a put and a call option on the same underlying asset XYZ, with the same expiration, and the same strike price (Fig. 1).




Fig. 1: Schematic of the profit for a short straddle trade written for Advanced Micro Devices, Inc. with ticker symbol AMD. A short straddle is a neutral strategy constructed by simultaneously selling a put and a call option on the same underlying asset AMD, with the same expiration, and the same strike price. On the the other hand, a long straddle is a neutral strategy constructed by simultaneously buying a put and a call option on the same underlying asset AMD, with the same expiration, and the same strike price. A long straddle has the same breakeven points as a short straddle, but the profit and loss are reversed, i.e., the profit diagram is rotated around the breakeven line. Thus, a long straddle has a defined maximum loss and an unlimited maximum possible profit.

Depending upon the choice of the strike prices and whether an investor buys or sells both legs, a straddle can be initiated as a credit or debit and can potentially have undefined profit or loss. Let K_j denote the strike price of contract j (USD/share), where the price of contract j is \mathcal{P}_j (USD/share). Further, let index j=1 denote the put contract, j=2 denote the call contract; for a straddle $K_1=K_2\equiv K$ (both legs have the same strike). The profit for a single straddle contract \hat{P} at expiration is given by:

$$\hat{P} = \theta \cdot (P_1 + P_2) \tag{7}$$

where $\theta_1=\theta_2\equiv\theta$ denotes a direction parameter: $\theta=-1$ if each leg is sold (short), $\theta=1$ otherwise. After substitution of the profit functions for a put and a call contract, the overall profit \hat{P} for a straddle is given by:

$$\hat{P} = \theta \cdot \left[(K - S)^{+} + (S - K)^{+} - (\mathcal{P}_{1} + \mathcal{P}_{2}) \right]$$
 (8)

where $V_p = (K-S)^+ = \max(K-S,0)$ is the payoff function for the put contract, and $V_c = (S-K)^+ = \max(S-K,0)$ is the payoff function for the call contract. The profit (or loss) of a

straddle has three regimes given by:

$$\hat{P} = \begin{cases}
\theta \cdot \left[(S(T) - K) - (\mathcal{P}_1 + \mathcal{P}_2) \right] & S(T) > K \\
-\theta \cdot \left[\mathcal{P}_1 + \mathcal{P}_2 \right] & S(T) = K \\
\theta \cdot \left[(K - S(T)) - (\mathcal{P}_1 + \mathcal{P}_2) \right] & S(T) < K
\end{cases} \tag{9}$$

where S(T) denotes the share price of the underlying asset at expiration. Finally, a straddle has two possible breakeven points denoted as S^+ and S^- :

$$\mathcal{B}(T) = \begin{cases} S^{+} = K + (\mathcal{P}_{1} + \mathcal{P}_{2}) & S(T) > K \\ S^{-} = K - (\mathcal{P}_{1} + \mathcal{P}_{2}) & S(T) < K \end{cases}$$
(10)

where S^+ denotes the upper breakeven point, and S^- denotes the lower breakeven point.

Strangles

A strangle is a neutral strategy constructed by simultaneously buying (or selling) a put and a call option on the same underlying asset XYZ, with the same expiration, but with different strike prices (Fig. 2).




Fig. 2: Schematic of the profit for a short strangle trade written for Advanced Micro Devices, Inc. with ticker symbol AMD. A short strangle is a neutral undefined risk strategy constructed by simultaneously selling a put and a call option on the same underlying asset AMD, with the same expiration, but with different strike prices. On the other hand, a long strangle is a neutral strategy constructed by simultaneously buying a put and a call option on the same underlying asset AMD, with the same expiration, but with different strike prices. A long strangle has the same breakeven points as a short strangle, but the profit and loss are reversed, i.e., the profit diagram is rotated around the breakeven line. Thus, a long strangle has a defined maximum loss and an undefined maximum possible profit.

Depending upon the choice of the strike prices and whether an investor buys or sells both

legs, a strangle can be initiated for a credit or debit and can potentially have undefined profit or loss. Let K_j denote the strike price of contract j (USD/share), where the price of contract j is \mathcal{P}_j (USD/share). Further, let index j=1 denote the put contract, j=2 denote the call contract; for a strangle $K_1 < K_2$. The profit for a single strangle contract \hat{P} at expiration is given by:

$$\hat{P} = \theta \cdot (P_1 + P_2) \tag{11}$$

where $\theta_1 = \theta_2 \equiv \theta$ denotes a direction parameter: $\theta = -1$ if each leg is sold (short), $\theta = 1$ otherwise. After substitution of the profit functions for a put and a call contract, the overall profit \hat{P} for a strangle is given by:

$$\hat{P} = \theta \cdot \left[(K_1 - S)^+ + (S - K_2)^+ - (\mathcal{P}_1 + \mathcal{P}_2) \right]$$
(12)

where $V_p = (K_1 - S)^+ = \max(K_1 - S, 0)$ is the payoff for the put contract, and $V_c = (S - K_2)^+ = \max(S - K_2, 0)$ is the payoff for the call contract. The profit (or loss) of a strangle has three regimes given by:

$$\hat{P} = \begin{cases}
\theta \cdot \left[(S(T) - K_2) - (\mathcal{P}_1 + \mathcal{P}_2) \right] & S(T) > K_2 \\
-\theta \cdot \left[\mathcal{P}_1 + \mathcal{P}_2 \right] & K_1 \le S(T) \le K_2 \\
\theta \cdot \left[(K_1 - S(T)) - (\mathcal{P}_1 + \mathcal{P}_2) \right] & S(T) < K_1
\end{cases}$$
(13)

where S(T) denotes the share price of the underlying asset at expiration. Finally, a strangle has two possible breakeven points denoted as S^+ and S^- :

$$\mathcal{B}(T) = \begin{cases} S^{+} = K_{1} - (\mathcal{P}_{1} + \mathcal{P}_{2}) & S(T) > K_{2} \\ S^{-} = K_{2} + (\mathcal{P}_{1} + \mathcal{P}_{2}) & S(T) < K_{1} \end{cases}$$
(14)

where S^+ denotes the upper breakeven point, and S^- denotes the lower breakeven point.

Iron Condor

Iron Condors are examples of defined-risk neutral strategies, i.e., they make no directional assumption about the price movement of the underlying asset, and can be opened for a credit or a debit. However, unlike straddles and strangles, iron condors have a defined maximum loss and maximum possible profit (Fig. 3). An iron condor is a neutral defined risk position constructed by selling a put (1) and call (2) options on the underlying asset XYZ, while simultaneously buying a put (3) and call (4) options on XYZ. All the legs of an iron condor have the same underlying asset XYZ, and have the same expiration, but they have different strike prices where $K_3 < K_1 < K_2 < K_4$. In particular, the two short options are sold with strikes on either side of the current share price S_o of XYZ, with the short put strike price $K_1 < S_o$ and the short call strike price $K_2 > S_o$. Then, the long legs are purchased above and below the short strikes. Thus, an iron condor position has the character of a strangle combined with a vertical spread.

Let the current share price of XYZ be S_o USD/share, and let S(T) denote the share price of XYZ at expiration. Further, let K_j denote the strike price of contract j (USD/share), where the price of




Fig. 3: Schematic of the profit for an Iron Condor on Micron Technologies with ticker symbol MU. An iron condor is a neutral defined risk position constructed by selling a put and call options on the underlying asset MU, while simultaneously buying a put and call options on MU. Thus, the maximum possible profit and loss are defined at the time the trade is opened.

contract j is \mathcal{P}_j (USD/share). Finally, let index j=1 denote the short put contract, j=2 denote the short call contract, j=3 denote the long put contract and j=4 denote the long call contract; for an iron condor $K_3 < K_1 < K_2 < K_3$. Then, the profit for a single iron condor contract \hat{P} at expiration is given by:

$$\hat{P} = \theta_1 P_1 + \theta_2 P_2 + \theta_3 P_3 + \theta_4 P_4 \tag{15}$$

where $\theta_1 = \theta_2 = -1$ (short legs) and $\theta_3 = \theta_4 = 1$ (long legs). After substitution of the profit functions for put and call contracts, the overall profit \hat{P} is given by:

$$\hat{P} = -(K_1 - S)^+ - (S - K_2)^+ + (K_3 - S)^+ + (S - K_4)^+ + (\mathcal{P}_1 + \mathcal{P}_2 - \mathcal{P}_3 - \mathcal{P}_4)$$
(16)

where $(K_{\star} - S)^+ = \max(K_{\star} - S, 0)$ and $(S - K_{\star})^+ = \max(S - K_{\star}, 0)$. The profit (or loss) of an iron condor has several important regimes given by:

$$\hat{P} = \begin{cases}
K_{2} - K_{4} + \left(\mathcal{P}_{1} + \mathcal{P}_{2} - \mathcal{P}_{3} - \mathcal{P}_{4}\right) & S > K_{4} \\
K_{2} - S + \left(\mathcal{P}_{1} + \mathcal{P}_{2} - \mathcal{P}_{3} - \mathcal{P}_{4}\right) & K_{2} < S < K_{4} \\
\left(\mathcal{P}_{1} + \mathcal{P}_{2} - \mathcal{P}_{3} - \mathcal{P}_{4}\right) & K_{1} \leq S \leq K_{2} \\
S - K_{1} + \left(\mathcal{P}_{1} + \mathcal{P}_{2} - \mathcal{P}_{3} - \mathcal{P}_{4}\right) & K_{3} < S < K_{1} \\
K_{3} - K_{1} + \left(\mathcal{P}_{1} + \mathcal{P}_{2} - \mathcal{P}_{3} - \mathcal{P}_{4}\right) & S < K_{3}
\end{cases} \tag{17}$$

Finally, an iron condor has two possible breakeven points denoted as S^+ and S^- : An iron condor has two break-even points S^+ and S^- where we know that $K_2 < S^+ < K_4$ and $K_3 < S^- < K_1$.

Thus, the low break-even point S^- is given by:

$$S^{-} = K_{1} - \left(\mathcal{P}_{1} + \mathcal{P}_{2} - \mathcal{P}_{3} - \mathcal{P}_{4}\right) \tag{18}$$

while the high break-even point S^+ is given by:

$$S^{+} = K_2 + \left(\mathcal{P}_1 + \mathcal{P}_2 - \mathcal{P}_3 - \mathcal{P}_4\right) \tag{19}$$

Summary

In this module, we have analyzed the profit and loss of American-style composite contracts at expiration. We considered two types of composite contracts: directional and neutral. Directional composite contracts make a directional assumption about the price movement of the underlying asset, and can be opened for a credit or a debit. Directional composite contracts include put vertical spreads and bearish call credit spreads, and are examples of a defined-risk directional strategy. On the other hand, neutral composite contracts make no directional assumption about the price movement of the underlying asset, and can be opened for a credit or a debit. These include straddles, and strangles, which are examples of undefined profit or loss strategies, and iron flys and condors, which are examples of defined-risk neutral strategies.