

Animesh Giri

Department of Computer Science & Engineering



Transport Layer

Animesh Giri

Department of Computer Science & Engineering



TCP Congestion Control

Animesh Giri

Department of Computer Science & Engineering

In this segment


PES UNIVERSITY

- TCP congestion control: additive increase multiplicative decrease
- TCP Congestion Control: details
- TCP Slow Start
- TCP: detecting, reacting to loss
- TCP: switching from slow start to CA
- Summary: TCP Congestion Control
- TCP throughput
- TCP Futures: TCP over "long, fat pipes"
- TCP Fairness
- Why is TCP fair?
- Explicit Congestion Notification (ECN)

TCP congestion control: additive increase multiplicative decrease

- approach: sender increases transmission rate (window size), probing for usable bandwidth, until loss occurs
 - additive increase: increase cwnd by 1 MSS every RTT until loss detected
 - multiplicative decrease: cut cwnd in half after loss


AIMD saw tooth behavior: probing for bandwidth





TCP Congestion Control: details





sender limits transmission:

cwnd is dynamic, function of perceived network congestion


TCP sending rate:

 roughly: send cwnd bytes, wait RTT for ACKS, then send more bytes

rate
$$\approx \frac{\text{cwnd}}{\text{RTT}}$$
 bytes/sec

TCP Slow Start

- when connection begins, increase rate exponentially until first loss event:
 - initially **cwnd** = 1 MSS
 - double cwnd every RTT
 - done by incrementing cwnd for every ACK received
- summary: initial rate is slow but ramps up exponentially fast





TCP: detecting, reacting to loss

- loss indicated by timeout:
 - cwnd set to 1 MSS;
 - window then grows exponentially (as in slow start) to threshold, then grows linearly
- loss indicated by 3 duplicate ACKs: TCP RENO
 - dup ACKs indicate network capable of delivering some segments
 - cwnd is cut in half window then grows linearly
- TCP Tahoe always sets cwnd to 1 (timeout or 3 duplicate acks)




TCP: switching from slow start to CA

Q: when should the exponential increase switch to linear?

A: when **cwnd** gets to 1/2 of its value before timeout.


Implementation:

- variable ssthresh
- on loss event, ssthres set to 1/2 of cwnd just before loss event





Summary: TCP Congestion Control






TCP throughput

PES UNIVERSITY ONLINE

- avg. TCP thruput as function of window size, RTT?
 - ignore slow start, assume always data to send
- W: window size (measured in bytes) where loss occurs
 - avg. window size (# in-flight bytes) is ¾ W
 - avg. thruput is 3/4W per RTT

avg TCP thruput =
$$\frac{3}{4} \frac{W}{RTT}$$
 bytes/sec



TCP Futures: TCP over "long, fat pipes"



- example: 1500 byte segments, 100ms RTT, want 10 Gbps throughput
- requires W = 83,333 in-flight segments
- throughput in terms of segment loss probability, L [Mathis 1997]:


TCP throughput =
$$\frac{1.22 \cdot MSS}{RTT \sqrt{L}}$$

- → to achieve 10 Gbps throughput, need a loss rate of L = 2·10⁻¹⁰
 a very small loss rate!
- new versions of TCP for high-speed

TCP Fairness

fairness goal: if K TCP sessions share same bottleneck link of bandwidth R, each should have average rate of R/K






Why is TCP fair?

two competing sessions:

- additive increase gives slope of 1, as throughout increases
- multiplicative decrease decreases throughput proportionally





Fairness (more)

Fairness and UDP

- multimedia apps often do not use TCP
 - do not want rate throttled by congestion control
- instead use UDP:
 - send audio/video at constant rate, tolerate packet loss

Fairness, parallel TCP connections


- application can open multiple parallel connections between two hosts
- web browsers do this
- e.g., link of rate R with 9 existing connections:
 - new app asks for 1 TCP, gets rate R/10
 - new app asks for 11 TCPs, gets R/2



Explicit Congestion Notification (ECN)

network-assisted congestion control:

- two bits in IP header (ToS field) marked by network router to indicate congestion
- congestion indication carried to receiving host
- receiver (seeing congestion indication in IP datagram))
 sets ECE bit on receiver-to-sender ACK segment to notify
 sender of congestion







THANK YOU

Animesh Giri

Department of Computer Science & Engineering animeshgiri@pes.edu

+91 80 6618 6603