

Memory Management

Chandravva Hebbi

Department of Computer Science



Virtual Memory

Chandravva Hebbi

Department of Computer Science

Slides Credits for all PPTs of this course



- The slides/diagrams in this course are an adaptation,
 combination, and enhancement of material from the following resources and persons:
- 1. Slides of Operating System Concepts, Abraham Silberschatz, Peter Baer Galvin, Greg Gagne 9th edition 2013 and some slides from 10th edition 2018
- 2. Some conceptual text and diagram from Operating Systems Internals and Design Principles, William Stallings, 9th edition 2018
- 3. Some presentation transcripts from A. Frank P. Weisberg
- 4. Some conceptual text from Operating Systems: Three Easy Pieces, Remzi Arpaci-Dusseau, Andrea Arpaci Dusseau

Background

- Virtual memory is a technique that allows the execution of processes that are not completely in memory.
- One major advantage of this scheme is that programs can be larger than physical memory.
- This technique frees programmers from the concerns of memory-storage limitations.
- Virtual memory also allows processes to share files easily and to implement shared memory

Background

- Code needs to be in memory to execute, but entire program rarely used
 - Error code, unusual routines, large data structures
- Entire program code not needed at same time
- Consider ability to execute partially-loaded program
 - Program no longer constrained by limits of physical memory
 - Each program takes less memory while running -> more programs run at the same time
 - Increased CPU utilization and throughput with no increase in response time or turnaround time
 - Less I/O needed to load or swap programs into memory -> each user program runs faster

Background (Cont.)


PES UNIVERSITY

- Virtual memory separation of user logical memory from physical memory
 - Only part of the program needs to be in memory for execution
 - Logical address space can therefore be much larger than physical address space
 - Allows address spaces to be shared by several processes
 - Allows for more efficient process creation
 - More programs running concurrently
 - Less I/O needed to load or swap processes

Background (Cont.)

- Virtual address space logical view of how process is stored in memory
 - Usually start at address 0, contiguous addresses until end of space
 - Meanwhile, physical memory organized in page frames
 - MMU must map logical to physical
- Virtual memory can be implemented via:
 - Demand paging
 - Demand segmentation


Virtual Memory That is Larger Than Physical Memory





Virtual-address Space


- Usually design logical address space for stack to start at Max logical address and grow "down" while heap grows "up"
 - Maximizes address space use
 - Unused address space between the two is hole
 - No physical memory needed until heap or stack grows to a given new page
- Enables sparse address spaces with holes left for growth, dynamically linked libraries, etc
- System libraries shared via mapping into virtual address space
- Shared memory by mapping pages read-write into virtual address space
- Pages can be shared during fork(), speeding process creation






Shared Library Using Virtual Memory





Demand Paging

- Could bring entire process into memory at load time
- Or bring a page into memory only when it is needed
 - Less I/O needed, no unnecessary I/O
 - Less memory needed
 - Faster response
 - More users
- Similar to paging system with swapping (diagram on right)
- Page is needed \Rightarrow reference to it
 - invalid reference ⇒ abort
 - not-in-memory ⇒ bring to memory
- Lazy swapper never swaps a page into memory unless page will be needed
 - Swapper that deals with pages is a pager






Demand Paging – Basic Concepts

- With swapping, pager guesses which pages will be used before swapping out again
- Instead, pager brings in only those pages into memory
- How to determine that set of pages?
 - Need new MMU functionality to implement demand paging
- If pages needed are already memory resident
 - No difference from non demand-paging
- If page needed and not memory resident
 - Need to detect and load the page into memory from storage
 - Without changing program behavior
 - Without programmer needing to change code



Valid-Invalid Bit

- With each page table entry a valid—invalid bit is associated $(v \Rightarrow in\text{-memory} \text{memory} \text{resident}, i \Rightarrow not\text{-in-memory})$
- Initially valid—invalid bit is set to i on all entries
- Example of a page table snapshot:





■ During MMU address translation, if valid—invalid bit in page table entry is $\mathbf{i} \Rightarrow \mathsf{page}$ fault




Page Table When Some Pages Are Not in Main Memory










Steps in Handling Page Fault

- 1. If there is a reference to a page, first reference to that page will trap to operating system
 - Page fault
- 2. Operating system looks at another table to decide:
 - Invalid reference ⇒ abort
 - Just not in memory
- 3. Find free frame
- 4. Swap page into frame via scheduled disk operation
- 5. Reset tables to indicate page now in memory Set validation bit = v
- 6. Restart the instruction that caused the page fault

Steps in Handling Page Fault (Cont.)





Aspects of Demand Paging

- Extreme case start process with no pages in memory
 - OS sets instruction pointer to first instruction of process, non-memory-resident -> page fault
 - And for every other process pages on first access
 - Pure demand paging
- Actually, a given instruction could access multiple pages -> multiple page faults
 - Consider fetch and decode of instruction which adds 2 numbers from memory and stores result back to memory
 - Pain decreased because of locality of reference Process migrates from one locality (i.e., a set of pages that are actively used together) to another
- Hardware support needed for demand paging
 - Page table with valid / invalid bit
 - Secondary memory (swap device with swap space)
 - Instruction restart

Instruction Restart

- Consider an instruction that could access several different locations (Ex: move some bytes from one location to another possibly overlapping location)
 - Source and destination blocks overlap i.e straddle a page boundary
 - ▶ Page fault might occur after the move is partially done
 - Source block may have been modified so we cannot simply restart the instruction
 - > In one solution, the microcode computes and attempts to access both ends of both blocks.
 - Page fault can occur before anything is modified
 - > The other solution uses temporary registers to hold the values of overwritten locations.
 - ➤ If Page fault occurs, all the old values are written back into memory before the trap occurs



Performance of Demand Paging

- Stages in Demand Paging (worse case)
- 1. Trap to the operating system
- 2. Save the user registers and process state
- 3. Determine that the interrupt was a page fault
- 4. Check that the page reference was legal and determine the location of the page on the disk
- 5. Issue a read from the disk to a free frame:
 - a) Wait in a queue for this device until the read request is serviced
 - b) Wait for the device seek and/or latency time
 - Begin the transfer of the page to a free frame



Performance of Demand Paging (Cont.)

- 6. While waiting, allocate the CPU to some other user
- 7. Receive an interrupt from the disk I/O subsystem (I/O completed)
- 8. Save the registers and process state for the other user
- 9. Determine that the interrupt was from the disk
- 10. Correct the page table and other tables to show page is now in memory
- 11. Wait for the CPU to be allocated to this process again
- 12. Restore the user registers, process state, and new page table, and then resume the interrupted instruction



Performance of Demand Paging (Cont.)

- Three major activities
 - Service the interrupt careful coding means just several hundred instructions needed
 - Read the page lots of time
 - Restart the process again just a small amount of time
- Page Fault Rate $0 \le p \le 1$ (p is the probability of a page fault)
 - if p = 0 no page faults
 - if p = 1, every reference is a fault
- Effective Access Time (EAT)

EAT =
$$(1 - p)$$
 x memory access
+ p x page-fault service time



Demand Paging Example

- Memory access time = 200 nanoseconds
- Average page-fault service time = 8 milliseconds
- EAT = $(1 p) \times 200 + p$ (8 milliseconds) = $(1 - p) \times 200 + p \times 8,000,000$ = $200 + p \times 7,999,800$
- EAT is directly proportional to page-fault rate
- If one access out of 1,000 causes a page fault i.e p = 0.001, then EAT = 8200 ns or 8.2 microseconds.

This is a slowdown by a factor of 40!! (i.e. 8200/200)

- If we want performance degradation < 10 percent</p>
 - 220 > 200 + 7,999,800 x p20 > 7,999,800 x p
 - p < .0000025
 - < one page fault in every 400,000 memory accesses



Demand Paging Optimizations

- Swap space I/O faster than file system I/O even if on the same device
 - Swap space is allocated in larger blocks, less management needed than file system
- Copy entire process image to swap space at process load time
 - Then page in and out of swap space
 - Used in older BSD Unix



Demand Paging Optimizations (Cont.)

- Demand page in from program binary on disk, but discard rather than paging out when freeing frame
 - Used in Solaris and current BSD
 - Still need to write to swap space
 - ▶ Pages not associated with a file (like stack and heap) anonymous memory
 - ▶ Pages modified in memory but not yet written back to the file system
- Mobile systems
 - Typically don't support swapping
 - Instead, demand page from file system and reclaim read-only pages (such as code) from applications
 - if memory becomes constrained and demand page such data from file system later if needed



THANK YOU

Chandravva Hebi
Department of Computer Science Engineering
chandravvahebbi@pes.edu