Computational Linear Algebra: Floating Point Representation and Rounding Error

David Shuman

February 1, 2022

Normalized numbers have the form

$$[\pm]1.[\mathit{mantissa}]*2^{[\mathit{exponent}]}$$

Normalized numbers have the form

$$[\pm]1.[mantissa]*2^{[exponent]}$$

Example:

$$(23.171875)_{10} = (10111.001011)_2 = +1.0111001011 * 2^4$$

Normalized numbers have the form

$$[\pm]1.[mantissa]*2^{[exponent]}$$

Example:

$$(23.171875)_{10} = (10111.001011)_2 = +1.0111001011 * 2^4$$

▶ The leading 1 is not stored, it is implied


▶ Different types of numbers have different types of bits for each part:

Precision	Sign	Exponent	Mantissa	Total
single	1	8	23	32
double	1	11	52	64
long double	1	15	64	80

Different types of numbers have different types of bits for each part:

Precision	Sign	Exponent	Mantissa	Total
single	1	8	23	32
double	1	11	52	64
long double	1	15	64	80

▶ We will almost always be using the 64-bit "double" precision:



The sign is 0 for positive numbers and 1 for negative numbers.



- \blacktriangleright [\pm]1.[mantissa] * $2^{[exponent]}$
- ► Back to our example:

$$23.171875 = 10111.001011 = +1.0111001011 * 2^4$$

- \blacktriangleright [\pm]1.[mantissa] * $2^{[exponent]}$
- ► Back to our example:

$$23.171875 = 10111.001011 = +1.0111001011 * 2^4$$

► The sign is 0

- \blacktriangleright [\pm]1.[mantissa] * $2^{[exponent]}$
- ► Back to our example:

$$23.171875 = 10111.001011 = +1.0111001011 * 2^4$$

- ► The sign is 0
- ► The mantissa is

or separated into four bit chunks:

Exponents

▶ 11 bits allow us to represent $2^{11} = 2048$ different integers

Exponents

- ▶ 11 bits allow us to represent $2^{11} = 2048$ different integers
- ▶ We need both positive and negative exponents, and we keep two integers for special cases, so we have 2046 left to cover integers from -1022 to 1023:

binary	0000000000	0000000001	0000000010	 11111111110	11111111111
decimal	0	1	2	 2046	2047
exponent	special	-1022	-1021	 1023	special

Exponents

- ▶ 11 bits allow us to represent $2^{11} = 2048$ different integers
- ▶ We need both positive and negative exponents, and we keep two integers for special cases, so we have 2046 left to cover integers from -1022 to 1023:

binary	00000000000	0000000001	0000000010	• • •	11111111110	111111111111
decimal	0	1	2		2046	2047
exponent	special	-1022	-1021		1023	special

- ▶ 1023 is the exponent bias. We add this amount to the actual exponent, and then store that number (note: this is the same as adding 1024 and subtracting 1)
- ► Subtract 1023 after storing (or subtract 1024 and add 1)
- ightharpoonup Thus $+1.0111001011 * 2^4$ is

0 1000000011	011100101100 · · · 0
--------------	----------------------



Special cases:

- Exponent of 2047 is equal to ∞ if the mantissa is all zeros, and equal to NaN (Not a Number) otherwise
- Exponent of 0 used to represent subnormal (very small) numbers. See the book as we will not harp on these

Special cases:

- Exponent of 2047 is equal to ∞ if the mantissa is all zeros, and equal to NaN (Not a Number) otherwise
- ► Exponent of 0 used to represent subnormal (very small) numbers. See the book as we will not harp on these

More examples:

1. $(-101101.0011101)_2$ is represented as

```
1 | 10000000100 | 01101001110100 · · · 0
```

Special cases:

- Exponent of 2047 is equal to ∞ if the mantissa is all zeros, and equal to NaN (Not a Number) otherwise
- ► Exponent of 0 used to represent subnormal (very small) numbers. See the book as we will not harp on these

More examples:

1. $(-101101.0011101)_2$ is represented as

```
1 | 10000000100 | 01101001110100 · · · 0
```

Special cases:

- \blacktriangleright Exponent of 2047 is equal to ∞ if the mantissa is all zeros, and equal to NaN (Not a Number) otherwise
- ► Exponent of 0 used to represent subnormal (very small) numbers. See the book as we will not harp on these

More examples:

1. $(-101101.0011101)_2$ is represented as

1	10000000100	01101001110100 · · · 0
---	-------------	------------------------

2. What do these IEEE numbers represent in binary?

```
1
10000110001
0111000101100 · · · 0

0
01111011110
0111000101100 · · · 0
```

Special cases:

- \blacktriangleright Exponent of 2047 is equal to ∞ if the mantissa is all zeros, and equal to NaN (Not a Number) otherwise
- ► Exponent of 0 used to represent subnormal (very small) numbers. See the book as we will not harp on these

More examples:

1. $(-101101.0011101)_2$ is represented as

1	1000000100	01101001110100 · · · 0
---	------------	------------------------

2. What do these IEEE numbers represent in binary?

```
1
10000110001
0111000101100 · · · 0

0
01111011110
0111000101100 · · · 0
```

 $-1.0111000101100 * 2^{50}$ and $+1.0111000101100 * 2^{-33}$



Rounding

Rounding

If we always chop (drop/ignore/truncate) the bits after b_{52} then we will systematically be rounding down. This can accumulate, so we use rounding:

▶ If what is left over is < 1/2:

1.
$$b_1b_2b_3\cdots b_{51}b_{52}$$
 0 · · · · · · · · · round down by truncating

just drop the bits beyond position 52

▶ If what is left over is > 1/2:

1.
$$b_1b_2b_3\cdots b_{51}b_{52}$$
 $\underbrace{1\cdots\cdots\cdots}_{\substack{\text{round up by}\\ \text{adding 1 to }b_{52}}}$

add 1 to bit b_{52} carrying as necessary

▶ If what is left over is = 1/2:

1.
$$b_1b_2b_3\cdots b_{51}b_{52}$$
 1 0 · · · · · · · · · all 0's

- $\begin{array}{ll} \text{if } b_{52}=1 \colon & \text{(round up)} \\ & \text{add } 1 \text{ to } b_{52} \\ \text{if } b_{52}=0 \colon & \text{(round down)} \\ & \text{do nothing} \end{array}$
- ▶ in this way we always end up with $b_{52} = 0$
- these two possibilities are equally likely



The number machine epsilon, denoted $\varepsilon_{\rm mach}$ or ε_M , is the distance between 1 and the next smallest representable number

- ▶ The number machine epsilon, denoted $\varepsilon_{\rm mach}$ or ε_M , is the distance between 1 and the next smallest representable number
- ► In our IEEE double precision representation, this next smallest number is

$$1 + \varepsilon_M = +1.$$
 000 · · · · · · 001 = $1 + 2^{-52}$,

- ▶ The number machine epsilon, denoted $\varepsilon_{\rm mach}$ or ε_M , is the distance between 1 and the next smallest representable number
- ► In our IEEE double precision representation, this next smallest number is

$$1 + \varepsilon_M = +1.$$
 000 · · · · · · 001 = $1 + 2^{-52}$,

▶ So $\varepsilon_M = 2^{-52}$

- ▶ The number machine epsilon, denoted $\varepsilon_{\rm mach}$ or ε_M , is the distance between 1 and the next smallest representable number
- ► In our IEEE double precision representation, this next smallest number is

$$1 + \varepsilon_M = +1. \boxed{000 \cdot \cdots \cdot 001} = 1 + 2^{-52},$$

- ► So $\varepsilon_M = 2^{-52}$
- Note: $2^{-52} = (2^{10})^{-5.2} \approx (10^3)^{-5.2} = 10^{-15.6} \approx 10^{-16}$

- ▶ The number machine epsilon, denoted $\varepsilon_{\rm mach}$ or ε_M , is the distance between 1 and the next smallest representable number
- ► In our IEEE double precision representation, this next smallest number is

$$1 + \varepsilon_M = +1.$$
 000 · · · · · · 001 = $1 + 2^{-52}$,

- ► So $\varepsilon_M = 2^{-52}$
- Note: $2^{-52} = (2^{10})^{-5.2} \approx (10^3)^{-5.2} = 10^{-15.6} \approx 10^{-16}$
- ► .Machine\$double.eps

- The number machine epsilon, denoted $\varepsilon_{\rm mach}$ or ε_M , is the distance between 1 and the next smallest representable number
- ► In our IEEE double precision representation, this next smallest number is

$$1 + \varepsilon_M = +1.$$
 000 · · · · · · 001 = $1 + 2^{-52}$,

- ► So $\varepsilon_M = 2^{-52}$
- Note: $2^{-52} = (2^{10})^{-5.2} \approx (10^3)^{-5.2} = 10^{-15.6} \approx 10^{-16}$
- ► .Machine\$double.eps
- ▶ Find gap between 2²⁰ and next smallest representable number



Rounding Error

Example:



$$(9.4)_{10} = (1001.\overline{0110})_2$$

Rounding Error

Example:

$$(9.4)_{10} = (1001.\overline{0110})_2$$

- $fl(9.4) = +1. \boxed{0010\ 1100\ 1100\ 1100\ 1100\ 1100\ 1100\ 1100\ 1100\ 1100\ 1100\ 1100\ 1100\ 1100} *2^3$
- So we truncated the tail by $.\overline{1100} * 2^{-52} * 2^3 = .\overline{0110} * 2^{-51} * 2^3 = 0.4 * 2^{-48} = 0.8 * 2^{-49}$
- And by rounding up, we added $2^{-52} * 2^3 = 1.0 * 2^{-49}$
- ► Therefore $fl(9.4) = 9.4 + 0.2 * 2^{-49}$

Absolute Rounding Error:

$$|x_c - x| = |fl(9.4) - 9.4| = 0.2 * 2^{-49}$$

Relative Rounding Error:

$$\qquad \qquad \frac{|x_c - x|}{|x|} = \frac{|fl(9.4) - 9.4|}{9.4} = \frac{0.2 \cdot 2^{-49}}{9.4} = \frac{8}{47} \cdot 2^{-52}$$

► The relative rounding error is always less than or equal to $\frac{\epsilon_{mach}}{2}$



Addition and Subtraction of Floating Point Numbers

- ► There is a register dedicated to doing computations so that the additions can be done with higher precision
- ► To add/subtract two numbers:
 - 1. Line up decimals
 - 2. Do the addition/subtraction (in higher precision, so you don't need to worry about rounding yet)
 - Once the arithmetic is complete, round to convert back to floating point form