



# Configuring backups on your instance

#### In this article

About GitHub Enterprise Server Backup Utilities

Prerequisites

Installing GitHub Enterprise Server Backup Utilities

Upgrading GitHub Enterprise Server Backup Utilities

Scheduling a backup

Restoring a backup

Monitoring backup or restoration progress

As part of a disaster recovery plan, you can protect production data on your GitHub Enterprise Server instance by configuring automated backups.

### **About GitHub Enterprise Server Backup Utilities 3**

GitHub Enterprise Server Backup Utilities is a backup system you install on a separate host, which takes backup snapshots of your GitHub Enterprise Server instance at regular intervals over a secure SSH network connection. You can use a snapshot to restore an existing GitHub Enterprise Server instance to a previous state from the backup host.

Only data added since the last snapshot will transfer over the network and occupy additional physical storage space. To minimize performance impact, backups are performed online under the lowest CPU/IO priority. You do not need to schedule a maintenance window to perform a backup.

Major releases and version numbers for GitHub Enterprise Server Backup Utilities align with feature releases of GitHub Enterprise Server. We support the four most recent versions of both products. For more information, see "GitHub Enterprise Server releases."

For more detailed information on features, requirements, and advanced usage, see the <u>GitHub Enterprise Server Backup Utilities README</u> in the GitHub Enterprise Server Backup Utilities project documentation.

## Prerequisites @

To use GitHub Enterprise Server Backup Utilities, you must have a host system separate from your GitHub Enterprise Server instance. For details about how the system should be configured, see <u>Requirements</u> in the github/backup-utils repository.

You can also integrate GitHub Enterprise Server Backup Utilities into an existing environment for long-term permanent storage of critical data.

We recommend that the backup host and your GitHub Enterprise Server instance be geographically distant from each other. This ensures that backups are available for recovery in the event of a major disaster or network outage at the primary site.

Physical storage requirements will vary based on Git repository disk usage and expected

growth patterns:

Hardware	Recommendation
vCPUs	2
Memory	2 GB
Storage	Five times the primary instance's allocated storage

More resources may be required depending on your usage, such as user activity and selected integrations.

For more information, see <u>GitHub Enterprise Server Backup Utilities requirements</u> in the GitHub Enterprise Server Backup Utilities project documentation.

## **Installing GitHub Enterprise Server Backup Utilities**



To install GitHub Enterprise Server Backup Utilities on your backup host, we recommend you download the relevant GitHub Enterprise Server Backup Utilities release as a compressed archive, then extract and install the contents. For more information, see <a href="Getting started">Getting started</a> in the github/backup-utils repository.

Downloading the release as a compressed archive ensures you are using the correct version of GitHub Enterprise Server Backup Utilities for your GitHub Enterprise Server instance, and that your existing backup configuration file, backup.config, will be preserved when installing a new version.

Backup snapshots are written to the disk path set by the <code>GHE\_DATA\_DIR</code> data directory variable in your <code>backup.config</code> file. Snapshots need to be stored on a filesystem which supports symbolic and hard links.

**Note:** We recommend ensuring your snapshots are not kept in a subdirectory of the GitHub Enterprise Server Backup Utilities installation directory, to avoid inadvertently overwriting your data directory when upgrading GitHub Enterprise Server Backup Utilities versions.

- 1 Download the relevant GitHub Enterprise Server Backup Utilities release from the Releases page of the github/backup-utils repository.
- 2 To extract the repository using tar, run the following command.

tar -xzvf /path/to/github-backup-utils-vMAJOR.MINOR.PATCH.tar.gz

3 To change into the local repository directory, run the following command.

cd backup-utils

4 To copy the included backup.config-example file to backup.config , run the following command.

cp backup.config-example backup.config

5 To customize your configuration, edit backup.config in a text editor.

a. Set the GHE\_HOSTNAME value to your primary GitHub Enterprise Server instance's hostname or IP address.

**Note:** If your GitHub Enterprise Server instance is deployed as a cluster or in a high availability configuration using a load balancer, the GHE\_HOSTNAME can be the load balancer hostname, as long as it allows SSH access (on port 122) to your GitHub Enterprise Server instance.

To ensure a recovered instance is immediately available, perform backups targeting the primary instance even in a geo-replication configuration.

- b. Set the GHE\_DATA\_DIR value to the filesystem location where you want to store backup snapshots. We recommend choosing a location on the same filesystem as your backup host, but outside of where you cloned the Git repository in step 1.
- 6 To grant your backup host access to your instance, open your primary instance's settings page at <a href="http(s)://HOSTNAME/setup/settings">http(s)://HOSTNAME/setup/settings</a> and add the backup host's SSH key to the list of authorized SSH keys. For more information, see "<a href="Accessing the administrative shell (SSH)">Accessing the administrative shell (SSH)</a>."
- On your backup host, verify SSH connectivity with your GitHub Enterprise Server instance with the ghe-host-check command.

```
./bin/ghe-host-check
```

8 To create an initial full backup, run the following command.

./bin/ghe-backup

For more information on advanced usage, see the <u>GitHub Enterprise Server Backup</u> <u>Utilities README</u> in the GitHub Enterprise Server Backup Utilities project documentation.

## **Upgrading GitHub Enterprise Server Backup Utilities**



When upgrading GitHub Enterprise Server Backup Utilities, you must choose a release that will work with your current version of GitHub Enterprise Server. Your installation of GitHub Enterprise Server Backup Utilities must be at least the same version as your GitHub Enterprise Server instance, and cannot be more than two versions ahead. For more information, see <a href="GitHub Enterprise Server version requirements">GitHub Enterprise Server Backup Utilities project documentation.</a> You can upgrade GitHub Enterprise Server Backup Utilities in a Git repository by fetching and checking out the latest changes.

Alternatively, if you don't use a Git repository for your installation, you can extract a new archive into place, or you can change your approach to use a Git repository instead.

### Verifying the installation type &

You can verify the installation method for GitHub Enterprise Server Backup Utilities and determine the best way to upgrade your installation.

- 1 On your backup host, navigate to your GitHub Enterprise Server Backup Utilities directory, usually backup-utils.
- 2 To check if a valid working directory exists inside a Git repository, run the following command.

```
git rev-parse --is-inside-work-tree
```

If the output is true, GitHub Enterprise Server Backup Utilities was installed by cloning the project's Git repository. If the output includes fatal: not a git repository (or any of the parent directories), GitHub Enterprise Server Backup Utilities was likely installed by extracting a compressed archive file. If your installation is in a Git repository, you can install the latest version using Git. If the installation is from a compressed archive file, you can either download and extract the latest version, or you can reinstall GitHub Enterprise Server Backup Utilities using Git to simplify future upgrades.

- Upgrading an installation in a Git repository
- Using Git instead of compressed archives for upgrades

### Upgrading an installation in a Git repository *∂*

1 On your backup host, navigate to your GitHub Enterprise Server Backup Utilities directory, usually backup-utils.

**Note:** We recommend creating a copy of your existing backup.config file in a temporary location, like \$HOME/backup.config, before upgrading GitHub Enterprise Server Backup Utilities.

2 Download the latest project updates by running the git fetch command.

git fetch

3 To update to the latest project release version, use the stable branch by running the git checkout stable command.

git checkout stable

Alternatively, to use a specific project version, run the following command, replacing X.Y.Z with the desired release version.

git checkout vX.Y.Z

4 To verify you have successfully upgraded, run the following command.

./bin/ghe-backup --version

5 To verify SSH connectivity between your configured GitHub Enterprise Server, run the following command.

./bin/ghe-host-check

### Using Git instead of compressed archives for upgrades &

If your backup host has internet connectivity and you previously used a compressed archive ( .tar.gz ) to install or upgrade GitHub Enterprise Server Backup Utilities, we recommend using a Git repository for your installation instead. Upgrading using Git requires less work and preserves your backup configuration.

To use Git instead of a compressed archive for upgrades, you must back up your existing configuration, clone the repository, copy your configuration into place, verify the installation, verify SSH connectivity, then delete the old installation.

- 1 On your backup host, navigate to your GitHub Enterprise Server Backup Utilities directory, usually backup-utils.
- To back up your existing GitHub Enterprise Server Backup Utilities configuration, copy your current backup.config file to a safe location, such as your home directory.

cp backup.config \$HOME/backup.config.saved-\$(date +%Y%m%d-%H%M%S)

- 3 Change to the local directory on your backup host where you want to install the GitHub Enterprise Server Backup Utilities Git repository.
- 4 To clone the <u>project repository</u> to the directory on your backup host, run the following command.

git clone https://github.com/github/backup-utils.git

5 To change into the cloned repository, run the following command.

cd backup-utils

6 To update to the latest project release version, use the stable branch by running the git checkout stable command.

git checkout stable

Alternatively, to use a specific project version, run the following command, replacing X.Y.Z with the desired release version.

git checkout vX.Y.Z

7 To restore your backup configuration from earlier, copy your existing backup configuration file to the local repository directory. Replace the path in the command with the location of the file saved in step 2.

cp PATH/TO/BACKUP/FROM/STEP/2 backup.config

**Note:** You can choose where to restore your backup configuration file to after cloning. For more information about where configuration files can be located, see <u>Getting started</u> in the GitHub Enterprise Server Backup Utilities project documentation.

- **3** To confirm that the paths to directories or scripts in your backup configuration file are correct, review the file in a text editor.
- 9 To verify you have successfully upgraded, run the following command.

./bin/ghe-backup --version

To verify SSH connectivity between your configured GitHub Enterprise Server, run the following command.

./bin/ghe-host-check

- ① Confirm that your backup data is not in the directory for the old installation.
- Delete your old GitHub Enterprise Server Backup Utilities directory from step 1 (where the compressed archive installation was located).

### Scheduling a backup @

You can schedule regular backups on the backup host using the <code>cron(8)</code> command or a similar command scheduling service. The configured backup frequency will dictate the worst case recovery point objective (RPO) in your recovery plan. For example, if you have scheduled the backup to run every day at midnight, you could lose up to 24 hours of data in a disaster scenario. We recommend starting with an hourly backup schedule, guaranteeing a worst case maximum of one hour of data loss if the primary site data is destroyed.

If backup attempts overlap, the <code>ghe-backup</code> command will abort with an error message, indicating the existence of a simultaneous backup. If this occurs, we recommended decreasing the frequency of your scheduled backups. For more information, see the "Scheduling backups" section of the <a href="GitHub Enterprise Server Backup Utilities README">GitHub Enterprise Server Backup Utilities README</a> in the GitHub Enterprise Server Backup Utilities project documentation.

## Restoring a backup &

In the event of prolonged outage or catastrophic event at the primary site, you can restore your GitHub Enterprise Server instance by provisioning another instance and performing a restore from the backup host. You must add the backup host's SSH key to the target GitHub Enterprise instance as an authorized SSH key before restoring an instance.

When performing backup restores to your GitHub Enterprise Server instance, you can only restore data from at most two feature releases behind. For example, if you take a backup from GitHub Enterprise Server 3.0.x, you can restore the backup to an instance running GitHub Enterprise Server 3.2.x. You cannot restore data from a backup of GitHub Enterprise Server 2.22.x to an instance running 3.2.x, because that would be three jumps between versions (2.22 to 3.0 to 3.1 to 3.2). You would first need to restore to an instance running 3.1.x, and then upgrade to 3.2.x.

Network settings are excluded from the backup snapshot. After restoration, you must manually configure networking on the target GitHub Enterprise Server instance.

- 1 Ensure maintenance mode is enabled on the primary instance and all active processes have completed. For more information, see "Enabling and scheduling maintenance mode."
- 2 Stop replication on all replica nodes in a high-availability configuration. For more information, see "About high availability configuration."
- 3 If your GitHub Enterprise Server instance has GitHub Actions enabled, you must configure the external storage provider for GitHub Actions on the replacement instance. For more information, see "Backing up and restoring GitHub Enterprise Server with GitHub Actions enabled."

### Starting the restore operation *?*

To restore your GitHub Enterprise Server instance from your backup host using the last successful snapshot, use the <code>ghe-restore</code> command. You can use the following additional options with <code>ghe-restore</code>.

- The -c flag overwrites the settings, certificate, and license data on the target host even if it is already configured. Omit this flag if you are setting up a staging instance for testing purposes and you wish to retain the existing configuration on the target.
   For more information, see the "Using backup and restore commands" section of the GitHub Enterprise Server Backup Utilities README in the github/backup-utils repository.
- The -s flag allows you to select a different backup snapshot.

After you run ghe-restore, the command confirms the restoration, then outputs details and status during the operation.

```
$ ghe-restore -c 169.154.1.1
> Checking for leaked keys in the backup snapshot that is being restored ...
> * No leaked keys found
> Connect 169.154.1.1:122 OK (v2.9.0)

> WARNING: All data on GitHub Enterprise appliance 169.154.1.1 (v2.9.0)
> will be overwritten with data from snapshot 20170329T150710.
> Please verify that this is the correct restore host before continuing.
> Type 'yes' to continue: yes

> Starting restore of 169.154.1.1:122 from snapshot 20170329T150710
# ...output truncated
> Completed restore of 169.154.1.1:122 from snapshot 20170329T150710
> Visit https://169.154.1.1/setup/settings to review appliance configuration.
```

Optionally, to validate the restore, configure an IP exception list to allow access to a specified list of IP addresses. For more information, see "<a href="Enabling and scheduling maintenance mode">Enabling and scheduling maintenance mode</a>."


On an instance in a high-availability configuration, after you restore to new disks on an existing or empty instance, <code>ghe-repl-status</code> may report that Git or Alambic replication is out of sync due to stale server UUIDs. These stale UUIDs can be the result of a retired node in a high-availability configuration still being present in the application database, but not in the restored replication configuration.

To remediate after the restoration completes and before starting replication, you can tear down stale UUIDs using <code>ghe-repl-teardown</code> . If you need further assistance, visit <code>GitHub Enterprise Support</code>.

## Monitoring backup or restoration progress *₹*


During a backup or restoration operation, you can use the <code>ghe-backup-progress</code> utility on your backup host to monitor the operation's progress. The utility prints the progress of each job sequentially.

To monitor progress on the backup host, from the directory containing GitHub Enterprise Server Backup Utilities, run the following command.



By default, the utility prints progress continuously until the operation is complete. You can press any key to return to the prompt.

Optionally, you can run the following command to print the current progress, the last completed job, and then immediately exit.



#### Legal

© 2023 GitHub, Inc. <u>Terms</u> <u>Privacy</u> <u>Status</u> <u>Pricing</u> <u>Expert services</u> <u>Blog</u>