



This version of GitHub Enterprise was discontinued on 2023-03-15. No patch releases will be made, even for critical security issues. For better performance, improved security, and new features, <u>upgrade to the latest version of GitHub Enterprise</u>. For help with the upgrade, <u>contact GitHub Enterprise support</u>.

Enforcing repository management policies in your enterprise

In this article

About policies for repository management in your enterprise

Configuring the default visibility of new repositories

Enforcing a policy for base repository permissions

Enforcing a policy for repository creation

Enforcing a policy for forking private or internal repositories

Enforcing a policy for inviting collaborators to repositories

Enforcing a policy for the default branch name

Enforcing a policy for changes to repository visibility

Enforcing a policy for repository deletion and transfer

Enforcing a policy for deleting issues

Enforcing a policy for Git push limits

Configuring the merge conflict editor for pull requests between repositories

Configuring force pushes

Configuring anonymous Git read access

You can enforce policies for repository management within your enterprise's organizations, or allow policies to be set in each organization.

Who can use this feature

Enterprise owners can enforce policies for repository management in an enterprise.

About policies for repository management in your enterprise $\mathscr O$

You can enforce policies to control how members of your enterprise on GitHub Enterprise Server manage repositories. You can also allow organization owners to manage policies for repository management. For more information, see "Creating and managing repositories and "Organizations and teams documentation."

Configuring the default visibility of new repositories




Each time someone creates a new repository within your enterprise, that person must choose a visibility for the repository. When you configure a default visibility setting for the enterprise, you choose which visibility is selected by default. For more information on

repository visibility, see "About repositories."

If an enterprise owner disallows members from creating certain types of repositories, members will not be able to create that type of repository even if the visibility setting defaults to that type. For more information, see "Enforcing a policy for repository creation."

1 In the top-right corner of GitHub Enterprise Server, click your profile photo, then click **Enterprise settings**.




- 2 In the enterprise account sidebar, click **Policies**.
- 3 Under ♠ Policies, click Options.
- 4 Under "Default repository visibility", use the drop-down menu and select a default visibility.


Warning: If you add an image attachment to a pull request or issue comment, anyone can view the anonymized image URL without authentication, even if the pull request is in a private repository, or if private mode is enabled. To prevent unauthorized access to the images, ensure that you restrict network access to the systems that serve the images, including your GitHub Enterprise Server instance.

Enforcing a policy for base repository permissions &

Across all organizations owned by your enterprise, you can set a base repository permission level (none, read, write, or admin) for organization members, or allow owners to administer the setting on the organization level.



- 2 In the enterprise account sidebar, click & Policies.
- 3 Under "কু Policies", click **Repositories**.
- 4 Under "Base permissions", review the information about changing the setting. Optionally, to view the current configuration for all organizations in the enterprise account before you change the setting, click **◊ View your organizations' current configurations**.



5. Under "Base permissions", select the dropdown menu and click a policy.


Enforcing a policy for repository creation @

Across all organizations owned by your enterprise, you can allow members to create repositories, restrict repository creation to organization owners, or allow owners to administer the setting on the organization level.

If you allow members to create repositories in your organizations, you can choose which types of repositories (public, private, and internal) that members can create.

For more information about internal repositories, see "Creating a new repository."

Organization owners can always create any type of repository, and outside collaborators can never create any type of repository. For more information, see "About repositories."



- 2 In the enterprise account sidebar, click **Policies**.
- 3 Under "本 Policies", click **Repositories**.
- 4 Under "Repository creation", review the information about changing the setting. Optionally, to view the current configuration for all organizations in the enterprise account before you change the setting, click **◊ View your organizations' current configurations**.


All organizations: Enabled ▼

O View your organizations' current configurations without the enterprise's policy.


- 1 Under "Repository creation", select a policy.
- 2 If you selected Members can create repositories, select one or more repository types.

Enforcing a policy for forking private or internal repositories *∂*

Across all organizations owned by your enterprise, you can allow people with access to a private or internal repository to fork the repository, never allow forking of private or internal repositories, or allow owners to administer the setting on the organization level.




- 2 In the enterprise account sidebar, click & Policies.
- 3 Under "কু Policies", click **Repositories**.
- 4 Under "Repository forking", review the information about changing the setting. Optionally, to view the current configuration for all organizations in the enterprise account before you change the setting, click **◊ View your organizations' current configurations**.




2. Under "Repository forking", select the dropdown menu and click a policy.

Enforcing a policy for inviting collaborators to repositories *ℯ*

Across all organizations owned by your enterprise, you can allow members to invite collaborators to repositories, restrict invitations to organization owners, or allow organization owners to administer the setting on the organization level.




- 2 In the enterprise account sidebar, click 4 Policies.
- 3 Under "কু Policies", click **Repositories**.
- 4 Under "Repository invitations", review the information about changing the setting. Optionally, to view the current configuration for all organizations in the enterprise account before you change the setting, click ◆ View your organizations' current configurations.



4. Under "Repository invitations", select the dropdown menu and click a policy.

Enforcing a policy for the default branch name &

Across all organizations owned by your enterprise, you can set the default branch name for any new repositories that members create. You can choose to enforce that default branch name across all organizations or allow individual organizations to set a different one.




- 2 In the enterprise account sidebar, click & Policies.
- 3 Under "কু Policies", click **Repositories**.
- 4 Under "Default branch name", enter the default branch name that new repositories should use.
- **5** Optionally, to enforce the default branch name for all organizations in the enterprise, select **Enforce across this enterprise**.
- 6 Click Update.

Enforcing a policy for changes to repository visibility




Across all organizations owned by your enterprise, you can allow members with admin access to change a repository's visibility, restrict repository visibility changes to organization owners, or allow owners to administer the setting on the organization level. When you prevent members from changing repository visibility, only enterprise owners can change the visibility of a repository.

If an enterprise owner has restricted repository creation to organization owners only, then members will not be able to change repository visibility. If an enterprise owner has restricted member repository creation to private repositories only, then members will only be able to change the visibility of a repository to private. For more information, see "Enforcing a policy for repository creation."




- 2 In the enterprise account sidebar, click 4 Policies.
- 3 Under "কু Policies", click **Repositories**.
- 4 Under "Repository visibility change", review the information about changing the setting. Optionally, to view the current configuration for all organizations in the enterprise account before you change the setting, click ◆ View your organizations' current configurations.



1 Under "Repository visibility change", select the dropdown menu and click a policy.

Enforcing a policy for repository deletion and transfer *∂*

Across all organizations owned by your enterprise, you can allow members with admin permissions to delete or transfer a repository, restrict repository deletion and transfers to organization owners, or allow owners to administer the setting on the organization level.



- 2 In the enterprise account sidebar, click & Policies.
- 3 Under "কু Policies", click **Repositories**.
- 4 Under "Repository deletion and transfer", review the information about changing the setting. Optionally, to view the current configuration for all organizations in the enterprise account before you change the setting, click **◊ View your** organizations' current configurations.


All organizations: Enabled ▼

O View your organizations' current configurations without the enterprise's policy.


1 Under "Repository deletion and transfer", select the dropdown menu and click a policy.

Enforcing a policy for deleting issues *₽*

Across all organizations owned by your enterprise, you can allow members with admin access to delete issues in a repository, restrict issue deletion to organization owners, or allow owners to administer the setting on the organization level.



- 2 In the enterprise account sidebar, click & Policies.
- 3 On the **Repository policies** tab, under "Repository issue deletion", review the information about changing the setting. Optionally, to view the current configuration for all organizations in the enterprise account before you change the setting, click **View your organizations' current configurations**.




4. Under "Repository issue deletion", select the dropdown menu and click a policy.

Enforcing a policy for Git push limits &

To keep your repository size manageable and prevent performance issues, you can configure a file size limit for repositories in your enterprise.

By default, when you enforce repository upload limits, people cannot add or update files larger than $100 \ \mathrm{MB}$.




- 2 In the enterprise account sidebar, click & Policies.
- 3 Under ♠ Policies, click Options.
- 4 Under "Repository upload limit", use the drop-down menu and click a maximum object size.
- 5 Optionally, to enforce a maximum upload limit for all repositories in your enterprise, select **Enforce on all repositories**



Configuring the merge conflict editor for pull requests between repositories *∂*

Requiring users to resolve merge conflicts locally on their computer can prevent people from inadvertently writing to an upstream repository from a fork.




- 2 In the enterprise account sidebar, click **p Policies**.
- 3 Under ♠ Policies, click Options.
- 4 Under "Conflict editor for pull requests between repositories", use the drop-down menu, and click **Disabled**.

Configuring force pushes *∂*

Each repository inherits a default force push setting from the settings of the user account or organization that owns the repository. Each organization and user account inherits a default force push setting from the force push setting for the enterprise. If you change the force push setting for the enterprise, the policy applies to all repositories owned by any user or organization.

Blocking force pushes to all repositories *₽*




- 2 In the enterprise account sidebar, click **p Policies**.
- 3 Under 4 Policies, click Options.
- 4 Under "Force pushes", select the dropdown menu, and click **Allow**, **Block**, or **Block** to the default branch.
- **5** Optionally, to override organization and repository level settings for force pushes, select **Enforce on all repositories**.

Blocking force pushes to a specific repository &

Note: Each repository automatically inherits default settings from the organization or user that owns it. You cannot override the default setting if the repository's owner has enforced the setting on all of their repositories.

- 1 Sign in to your GitHub Enterprise Server instance at http(s)://HOSTNAME/login.
- 2 From an administrative account on GitHub Enterprise Server, in the upper-right corner of any page, click \mathcal{Q} .
- 3 If you're not already on the "Site admin" page, in the upper-left corner, click **Site** admin.
- 4 Under "Search users, organizations, teams, repositories, gists, and applications", type the name of the repository in the text field. Then to the right of the field, click **Search**.



- 5 Under "Search results Repositories", click the name of the repository.
- 6 In the upper-right corner of the page, click 袋 Admin.




Under "Push and Pull", to the right of "Force pushes", select the dropdown menu, and click **Block** or **Block to the default branch**.

Blocking force pushes to repositories owned by a user account or organization $\mathscr O$

Repositories inherit force push settings from the user account or organization to which they belong. User accounts and organizations in turn inherit their force push settings from the force push settings for the enterprise.

You can override the default inherited settings by configuring the settings for a user account or organization.

- 1 Sign in to your GitHub Enterprise Server instance at http(s)://HOSTNAME/login.
- 2 From an administrative account on GitHub Enterprise Server, in the upper-right corner of any page, click \mathcal{Q} .
- If you're not already on the "Site admin" page, in the upper-left corner, click **Site** admin.
- 4 Under "Search users, organizations, teams, repositories, gists, and applications", type the name of the user or organization in the text field. Then to the right of the field, click **Search**.



5 In the search results, click the name of the user or organization.



6 In the upper-right corner of the page, click 袋 Admin.



- 1 Under "Repository default settings" in the "Force pushes" section, select a policy.
 - To block force pushes to all branches, select **Block**.
 - To only block force pushes to the default branch, select Block to the default branch.
- 8 Optionally, to override repository-specific settings, select **Enforce on all repositories**. Note that this will **not** override an enterprise-wide policy.



Configuring anonymous Git read access &

- The Git protocol is unauthenticated and unencrypted. An attacker could intercept repository data transferred over connections using this protocol.
- If you enable anonymous Git read access, you're responsible for all access and use of the
 feature. GitHub is not responsible for any unintended access, security risks, or misuse of the
 feature.
- You may not use this feature to violate your license from GitHub, including the limit on the number of user licenses for your GitHub Enterprise Server instance.

If you have <u>enabled private mode</u> for your GitHub Enterprise Server instance, you can allow repository administrators to enable anonymous Git read access to public repositories.

Enabling anonymous Git read access allows users to bypass authentication for custom tools on your enterprise. When you or a repository administrator enable this access setting for a repository, unauthenticated Git operations (and anyone with network access to GitHub Enterprise Server) will have read access to the repository without authentication.

Anonymous Git read access is disabled by default. When you upgrade to GitHub Enterprise Server 3.6 or later, anonymous Git read access is automatically disabled at the application level, and git:// connections on port 9418 will return the following error.

The unauthenticated git protocol on port 9418 is no longer supported.

Anonymous Git read access will be entirely removed in a future release of GitHub Enterprise Server. GitHub recommends using SSH instead of the Git protocol. For more information about this change, see the-GitHub Blog.


If necessary, you can prevent repository administrators from changing anonymous Git access settings for repositories on your enterprise by locking the repository's access settings. After you lock a repository's Git read access setting, only a site administrator can change the setting.

To see the repositories with anonymous Git read access enabled, filter the repositories list in the site admin dashboard.

Notes:

- You cannot change the Git read access settings for forked repositories since they inherit their access settings from the root repository by default.
- If a public repository becomes private, then anonymous Git read access will automatically be disabled for that repository and it forks.
- If a repository with anonymous authentication contains Git LFS assets, it will fail to download
 the Git LFS assets since they still require authentication. We strongly recommend not
 enabling anonymous Git read access for a repository with Git LFS assets.


Setting anonymous Git read access for all repositories &



- 2 In the enterprise account sidebar, click **p Policies**.
- 3 Under ♠ Policies, click Options.
- 4 Under "Anonymous Git read access", use the drop-down menu, and click **Enabled**.
- Optionally, to prevent repository admins from changing anonymous Git read access settings in all repositories on your enterprise, select Prevent repository admins from changing anonymous Git read access.

Setting anonymous Git read access for a specific repository &


- 1 From an administrative account on GitHub Enterprise Server, in the upper-right corner of any page, click \mathcal{Q} .
- 2 If you're not already on the "Site admin" page, in the upper-left corner, click **Site** admin.
- 3 Under "Search users, organizations, teams, repositories, gists, and applications", type the name of the repository in the text field. Then to the right of the field, click **Search**.



- 4 Under "Search results Repositories", click the name of the repository.
- 5 In the upper-right corner of the page, click & Admin.



6 Under "Danger Zone", next to "Enable Anonymous Git read access", click **Enable**.



- Review the changes. To confirm, click Yes, enable anonymous Git read access.
- Optionally, to prevent repository admins from changing this setting for this repository, select Prevent repository admins from disabling anonymous Git read access.

Legal

© 2023 GitHub, Inc. <u>Terms</u> <u>Privacy</u> <u>Status</u> <u>Pricing</u> <u>Expert services</u> <u>Blog</u>