



Dockerfile support for GitHub Actions

Create an action

6 of 7 in learning path

Next: Setting exit codes for actions

In this article

About Dockerfile instructions

Dockerfile instructions and overrides

Supported Linux capabilities

When creating a Dockerfile for a Docker container action, you should be aware of how some Docker instructions interact with GitHub Actions and an action's metadata file.

Note: GitHub-hosted runners are not currently supported on GitHub Enterprise Server. You can see more information about planned future support on the <u>GitHub public roadmap</u>.

About Dockerfile instructions &

A Dockerfile contains instructions and arguments that define the contents and startup behavior of a Docker container. For more information about the instructions Docker supports, see "Dockerfile reference" in the Docker documentation.

Dockerfile instructions and overrides &

Some Docker instructions interact with GitHub Actions, and an action's metadata file can override some Docker instructions. Ensure that you are familiar with how your Dockerfile interacts with GitHub Actions to prevent any unexpected behavior.

USER ₽

Docker actions must be run by the default Docker user (root). Do not use the USER instruction in your Dockerfile, because you won't be able to access the GITHUB_WORKSPACE directory. For more information, see "Variables" and USER reference in the Docker documentation.

FROM @

The first instruction in the <code>Dockerfile</code> must be <code>FROM</code>, which selects a Docker base image. For more information, see the <code>FROM</code> reference in the Docker documentation.

These are some best practices when setting the FROM argument:

• It's recommended to use official Docker images. For example, python or ruby.

- Use a version tag if it exists, preferably with a major version. For example, use node:10 instead of node:latest.
- It's recommended to use Docker images based on the <u>Debian</u> operating system.

WORKDIR @

GitHub Enterprise Server sets the working directory path in the <code>GITHUB_WORKSPACE</code> environment variable. It's recommended to not use the <code>WORKDIR</code> instruction in your <code>Dockerfile</code>. Before the action executes, GitHub Enterprise Server will mount the <code>GITHUB_WORKSPACE</code> directory on top of anything that was at that location in the <code>Dockerimage</code> and set <code>GITHUB_WORKSPACE</code> as the working directory. For more information, see "<code>Variables</code>" and the <code>WORKDIR reference</code> in the <code>Docker documentation</code>.

ENTRYPOINT *P*

If you define entrypoint in an action's metadata file, it will override the ENTRYPOINT defined in the Dockerfile . For more information, see "Metadata syntax for GitHub Actions."

The Docker ENTRYPOINT instruction has a *shell* form and *exec* form. The Docker ENTRYPOINT documentation recommends using the *exec* form of the ENTRYPOINT instruction. For more information about *exec* and *shell* form, see the ENTRYPOINT reference in the Docker documentation.

You should not use WORKDIR to specify your entrypoint in your Dockerfile. Instead, you should use an absolute path. For more information, see <u>WORKDIR</u>.

If you configure your container to use the <code>exec</code> form of the <code>ENTRYPOINT</code> instruction, the <code>args</code> configured in the action's metadata file won't run in a command shell. If the action's <code>args</code> contain an environment variable, the variable will not be substituted. For example, using the following <code>exec</code> format will not print the value stored in <code>\$GITHUB_SHA</code>, but will instead print <code>"\$GITHUB_SHA"</code>.

```
ENTRYPOINT ["echo $GITHUB_SHA"]
```

If you want variable substitution, then either use the *shell* form or execute a shell directly. For example, using the following *exec* format, you can execute a shell to print the value stored in the GITHUB SHA environment variable.

```
ENTRYPOINT ["sh", "-c", "echo $GITHUB_SHA"]
```

To supply args defined in the action's metadata file to a Docker container that uses the exec form in the ENTRYPOINT, we recommend creating a shell script called entrypoint.sh that you call from the ENTRYPOINT instruction:

Example *Dockerfile &*

```
# Container image that runs your code
FROM debian:9.5-slim

# Copies your code file from your action repository to the filesystem path `/` of
the container
COPY entrypoint.sh /entrypoint.sh

# Executes `entrypoint.sh` when the Docker container starts up
ENTRYPOINT ["/entrypoint.sh"]
```

Example entrypoint.sh file @

Using the example Dockerfile above, GitHub Enterprise Server will send the args configured in the action's metadata file as arguments to entrypoint.sh . Add the #!/bin/sh shebang at the top of the entrypoint.sh file to explicitly use the system's POSIX-compliant shell.

```
#!/bin/sh

# `$#` expands to the number of arguments and `$@` expands to the supplied `args`
printf '%d args:' "$#"
printf " '%s'" "$@"
printf '\n'
```

Your code must be executable. Make sure the entrypoint.sh file has execute
permissions before using it in a workflow. You can modify the permission from your
terminal using this command:

```
chmod +x entrypoint.sh
```

When an ENTRYPOINT shell script is not executable, you'll receive an error similar to this:

```
Error response from daemon: OCI runtime create failed: container_linux.go:348:
starting container process caused "exec: \"/entrypoint.sh\": permission denied":
unknown
```

CMD @

If you define args in the action's metadata file, args will override the CMD instruction specified in the Dockerfile. For more information, see "Metadata syntax for GitHub Actions".

If you use CMD in your Dockerfile , follow these guidelines:

- 1 Document required arguments in the action's README and omit them from the CMD instruction.
- 2 Use defaults that allow using the action without specifying any args .
- 3 If the action exposes a --help flag, or something similar, use that to make your action self-documenting.

Supported Linux capabilities &

GitHub Actions supports the default Linux capabilities that Docker supports. Capabilities can't be added or removed. For more information about the default Linux capabilities that Docker supports, see "Runtime privilege and Linux capabilities" in the Docker documentation. To learn more about Linux capabilities, see "Overview of Linux capabilities" in the Linux man-pages.

Previous

Next

Metadata syntax for GitHub Actions

Setting exit codes for actions

				