CS525: Advanced Database Organization

Notes 2: Storage Hardware

Yousef M. Elmehdwi

Department of Computer Science

Illinois Institute of Technology

yelmehdwi@iit.edu

August 23rd, 2018

Slides: adapted from a courses taught by Hector Garcia-Molina, Stanford, Paris Koutris. & Leonard McMillan


Outline

- Study of data storage in a database management systems
- We shall learn the basic techniques for managing data within the computer
- There are two issues we must address which are related to how a DBMS deals with very large amounts of data efficiently:
 - How does a computer system store and manage very large volumes of data?
 - What representations and data structures best support efficient manipulations of this data?

Today

- Hardware: Disks
- Access Times
- Optimizations
- Other Topics:
 - Storage costs
 - Using secondary storage
 - Disk failures

Hardware



Data Storage

- How does a DBMS store and access data?
 - main memory (fast, temporary)
 - disk (slow, permanent)
- How do we move data from disk to main memory?
 - buffer manager
- How do we organize relational data into files?

Disks and Files

- DBMS stores information on ("hard") disks.
- This has major implications for DBMS design!
 - READ: transfer data from disk to main memory (RAM).
 - WRITE: transfer data from RAM to disk.
 - Both are high-cost operations, relative to in-memory operations, so must be planned carefully!


Why Not Store Everything in Memory?

- Relatively high cost
- Main memory is not persistent (volatile)
 - We want data to be saved between runs. (Obviously!)
- Data Size > Memory Size > Address Space
- Note: many "main memory only" databases are available, and used increasingly for applications with small storage requirements and as memory sizes increase

Typical Storage Hierarchy

- CPU Registers temporary variables
- Cash Fast copies of frequently accessed memory locations
- Main memory (RAM) for currently used "addressable" data.
- Disk for main database (secondary storage)
- Tapes for archiving older versions of the data (tertiary storage)

Memory hierarchy



¹©2013 Gribble, Lazowska, Levy, Zahorjan

Disks


- The use of secondary storage is one of the important characteristics of a DBMS.
- To motivate many of the ideas used in DBMS implementation, we must examine the operation of disks in detail

Disks

- Secondary storage device of choice
- Main advantage over tapes: random access vs. sequential
 - Sequential: read the data contiguously
 - Random: read the data from anywhere at any time
- Data is stored and retrieved in units called disk blocks or pages
- Retrieval time depends upon the location of the disk
 - Therefore, relative placement of pages on disk has major impact on DBMS performance! Why?

Components of a Disk


- Platter: circular hard surface on which data is stored by inducing magnetic changes
 - Platters are 2-sided and magnetic
- Platters rotates (7200 RPM -15000 RPM)
 - RPM (Rotations Per Minute)
- All disk heads move at the same time (in or out)




Disks

- Platter has circular tracks
- Tracks are divided into sectors
- Sector: the unit of write operation for a disk
- However:
 - Sector is too small to be efficient
 - Computer systems read/write a block (multiple sectors) at once.
- A block (page) consists of one or more multiple contiguous hardware sectors
 - Between main memory and disk the data is moved in blocks
 - Block size: 4K-64K bytes
- Gaps are non-magnetic and used to identify the start of a sector

Top View of a Platter



Terminology: cylinder




- Cylinder: all tracks at the same distance from the center/tracks that are under the heads at the same time
- Disk head does not need to move when accessing (read/write) data in the same cylinder

Disk Storage Characteristics

- # Cylinders= # tracks per surface (platter)
 - \bullet e.g., 10 tracks \Rightarrow 10 cylinders and we can refer to them cylinder zero to cylinder nine
- ullet # tracks per cylinder= # of heads or 2× # platter
- Average # sectors per track
- bytes per sector
- ⇒disk capacity/size

Today

- Hardware: Disks
- Access Times
- Optimizations
- Other Topics:
 - Storage costs
 - Using secondary storage
 - Disk failures



- The time taken between the moment at which the command to read
 a block is issued and the time that the contents of the block appear
 in main memory is called the latency of the disk.
- The access time is also called the latency of the disk.

- Basic operations:
 - READ: transfer data from disk to buffer
 - WRITE: transfer data from buffer to disk
- Note that blocks can be read or written only when:
 - The heads are positioned at the cylinder containing the track on which the block is located, and
 - The sectors contained in the block move under the disk head as the entire disk assembly rotates.

access time = seek time + rotational delay + transfer time +other delay


- Other Delays:
 - CPU time to issue I/O
 - Contention for controller
 - Different programs can be using the disk
 - Contention for bus, memory
 - Different programs can be transferring data
 - These delays are negligible compared to Seek time + rotational delay + transfer time
 - "Typical" Value: 0

access time = seek time + rotational delay + transfer time

- Seek time: time to move the arm to position disk head on the right track (position the read/write head at the proper cylinder)
- Seek time can be 0 if the heads happen already to be at the proper cylinder.
- If not, the heads require some minimum time to start moving and to stop again, plus additional time that is roughly proportional to the distance traveled.
- The average seek time is often used as a way to characterize the speed of the disk.

access time = seek time + rotational delay + transfer time

- rotational delay: time to wait for sector to rotate under the disk head
- i.e., wait for the beginning of the block



Average Rotational Delay


- On the average, the desired sector will be about half way around the circle when the heads arrive at its cylinder.
- Average rotational delay is time for $\frac{1}{2}$ revolution
- Example: Given a total revolution of 7200 RPM
 - One rotation = $\frac{60s}{7200}$ = 8.33 ms
 - ullet Average rotational latency $= 4.16 \ ms$

access time = seek time + rotational delay + transfer time

- data transfer time: time to move the data to/from the disk surface
- Transfer time is the time it takes the sectors of the block and any gaps between them to rotate past the head.
- Given a transfer rate, the transfer time= $\frac{Amount\ data\ transferred}{transfer\ rate}$
- Transfer Rate: # bits transferred/sec


Steps to access data on a disk

- 1. Move the disk heads to the desired cylinder
- Time to seek a cylinder = seek time




Steps to access data on a disk

- 2. Wait for the desired sector to arrive under the disk head
- Time to wait for a sector = rotational delay



Steps to access data on a disk

3. Transfer the data from sector to main memory (through the disk controller)



- Seek time and rotational delay dominate.
- Key to lower I/O cost: reduce seek/rotation delays!

Arranging Blocks on Disk

- So far: One (Random) Block Access
- What about: Reading "Next" block?
- Blocks in a file should be arranged sequentially on disk (by "next") to minimize seek and rotational delay.
- Next block concept:
 - blocks on same track, followed by
 - blocks on same cylinder, followed by
 - blocks on adjacent cylinder
- For a sequential scan, pre-fetching several blocks at a time is a big win.

If we do things right

- (e.g., Double Buffer, Stagger Blocks...)
- Time to get blocks should be proportional to the size of blocks, and the seek time and rotational latency thus become trivial
- time to get block = $\frac{Block \ size}{transfer \ rate} + \frac{Negligible}{transfer \ rate}$
- Negligible:
 - skip gap
 - switch track
 - once in a while, next cylinder

Rule of Thumb

- Random I/O: Expensive
- Sequential I/O: Much less

Cost for Writing similar to Reading

- The process of writing a block is, in its simplest form, quite similar to reading a block
- ... unless we want to verify!
- need to add (full) rotation $+\frac{Block\ size}{transfer\ rate}$

To Modify a Block?

It is not possible to modify a block on disk directly. Rather, even if we wish to modify only a few bytes, we must do the following:

- Read Block into Memory
- Modify in Memory
- Write Block
- [Verify?]

SSD (SOLID STATE DRIVE)

- SSDs use flash memory
- No moving parts (no rotate/seek motors)
 - eliminates seek time and rotational delay
 - very low power and lightweight
- Data transfer rates: 300-600 MB/s
- SSDs can read data (sequential or random) very fast!
- Small storage $(0.1 0.5 \times \text{ of HDD})$
- expensive (20× of HDD)
- Writes are much more expensive than reads $(10\times)$
- Limited lifetime
 - 1-10K writes per page
 - the average failure rate is 6 years

Today

- Hardware: Disks
- Access Times
- Optimizations
- Other Topics:
 - Storage costs
 - Using secondary storage
 - Disk failures

Optimizations (in controller or O.S.)

Effective ways to speed up disk accesses:

- Disk Scheduling Algorithms
- Pre-fetch (Double buffering)
- Arrays (RAID)
- Mirrored Disks
- On Disk Cache

Disk Scheduling

- Situation: Have many read/write requests
- Question: In which order do you process the requests?

Double Buffering

- Another suggestion for speeding up some secondary-memory algorithms is called double buffering.
- In some scenarios, we can predict the order in which blocks will be requested from disk by some process.
- Pre-fetching (double buffering) is the method of fetching the necessary blocks into the buffer in advance
- Requires enough buffer space
- Speedup factor up to n, where n is the number of blocks requested by a process

Double Buffering Algorithm

Problem

- Have a File
 - Sequence of Blocks B1, B2, ...
- Have a Program
 - Process B1
 - Process B2
 - Process B3
 - •

Single Buffer Solution (Naïve Solution)


- $lue{1}$ Read B1 ightarrow Buffer
- Process Data in Buffer
- Read B2 \rightarrow Buffer
- Process Data in Buffer
- **5**

Single Buffer Solution


Let:

- P = time to process/block
- R = time to read in 1 block
- n = # blocks
 - 1. Read B1 \rightarrow Buffer \Rightarrow R
 - 2. Process Data in Buffer \Rightarrow P
 - 3. Read B2 \rightarrow Buffer \Rightarrow R
 - 4. Process Data in Buffer \Rightarrow P
- Time to process n block =n(P+R)


Double Buffering Solution



Double Buffering Solution



Double Buffering Solution



Double Buffer Solution

Let:

- P = time to process/block
- R = time to read in 1 block
- n = # blocks
- \bullet Say P \geq R

What is processing time?

- Double buffering time = R+nP
- Single buffer time = n(R+P)

Using disk array to accelerate disk access

- Why use multiple disks
 - Multiple disks → multiple disk heads
 - $\bullet \ \ \mathsf{Multiple} \ \mathsf{outputs} = \mathsf{Increased} \ \mathsf{data} \ \mathsf{rate}$

Techniques: multiple disks

- Block Striping
 - Store blocks of a file over multiple disks
- Mirror disk
 - Store the same data on multiple disks
 - Mirrored disks contain identical content
 - Read operation: n times as fast
 - Write operation: about the same as 1 disk
- RAID
 - Redundant Array of Independent (inexpensive) Disks

Disk Failures

We consider ways in which disks can fail and what can be done to mitigate these failures:

- Intermittent read failure (Cause: power fluctuations/failure)
- Intermittent write failure (Cause: power fluctuation/failure)
- Media decay (Disk surface worn out)
- Permanent failure (Disk crash)

Coping with Read/Write Failures

- Detection
 - Read (verify) after writing data
 - Better: Use checksum
- Correction
 - Redundancy

Coping with media decay

- Disk has a number of spare blocks
- When writing a block fails for n times
 - Mark block as bad
 - Replace block with one of the spare blocks

Coping with Disk Crash

- Different ways to achieve redundancy
 - Exact copy (mirror)
 - RAID

Example

- Rotate at 3600 RPM
- Only 1 surface
- 16 MB usable capacity (usable capacity excludes the gaps)
- 128 cylinders
- seek time:
 - average = 25 ms.
 - adjacent cylinders = 5 ms.
- 1 KB block = 1 sector
- 10% overhead between blocks
 - gaps represent 10% of the circle and
 - sectors represent the remaining 90%

- 1 KB blocks = sectors
- 10% overhead between blocks
- capacity = $16 \text{ MB} = (2^{20})16 = 2^{24}$
- # cylinders = $128 = 2^7$
- bytes/cylinder = $\frac{total\ capacity}{total\ \#\ cylinders} = \frac{2^{20} \times 16}{128} = \frac{2^{24}}{2^7} = 2^{17} = 128 \text{KB}$
- #blocks/cylinder $= \frac{capacity\ of\ each\ cylinder}{size\ of\ block} = \frac{128KB}{1KB} = 128$

• 3600 RPM \rightarrow 60 revolutions/sec \rightarrow 1 rev. = 16.66 msec.


One track:



- ullet Time over useful data $=16.66 \times 0.9 = 14.99 \; \text{ms}$
- ullet Time over gaps= $16.66 \times 0.1 = 1.66 \text{ ms}$
- Transfer time for 1 block $=\frac{14.99}{128}=0.117$ ms
- Transfer time for 1 block+gap= $\frac{16.66}{128} = 0.13$ ms

- Access time (T_1) = Time to read one random block
- ullet $T_1 = \text{seek} + \text{rotational delay} + \text{transfer time for 1 block}$
- $T_1 = 25 + \frac{16.66}{2} + 0.117 = 33.45$ ms.
- Why we did not use the time it takes to transfer 1 block+gap here?

Suppose OS deals with 4 KB blocks



- Access time = $T_4 = 25 + \frac{16.66}{2} + 0.117 \times 1 + 0.13 \times 3 = 33.83$ ms
- Compare to $T_1 = 33.45 \text{ms}$
- Q) The time to read a full track is?

Summary

- Secondary storage, mainly disks
- I/O times
- I/Os should be avoided, especially random ones

Reading

• Chapter 2: data storage in Assignments & Projects/reading folder, except Sections: 2.3.3, 2.3.4, 2.3.5, 2.4.4, 2.5.4, 2.6

Next

• File and System Structure