Promtail Installation on Ubuntu

#check cpu architecture

```
uname -a
```

```
npci@node1:-$ #check cpu architecture
uname -a
Linux node1 6.8.0-40-generic #40~22.04.3-Ubuntu SMP PREEMPT_DYNAMIC Tue Jul 30 17:30:19 UTC 2 x86_64 x86_64 x86_64 GNU/Linux
npci@node1:-$
```

Note: If curl is not installed, use any of the below commands to install sudo snap install curl # version 8.1.2, or sudo apt install curl # version 7.81.0-1ubuntu1.17

#example for Loki on the linux operating system and amd64 architecture curl -O -L "https://github.com/grafana/loki/releases/download/v2.4.1/promtail-linux-amd64.zip"

#extract the binary unzip "promtail-linux-amd64.zip"

```
npci@node1:~$ #extract the binary
unzip "promtail-linux-amd64.zip"
Archive: promtail-linux-amd64.zip
inflating: promtail-linux-amd64
```

#make sure it is executable chmod a+x "promtail-linux-amd64"

```
npci@node1:~$ #make sure it is executable
chmod a+x "promtail-linux-amd64"
npci@node1:~$
```

#copy binary to /usr/local/bin/ sudo cp promtail-linux-amd64 /usr/local/bin/promtail

```
npci@node1:~$ #copy binary to /usr/local/bin/
sudo cp promtail-linux-amd64 /usr/local/bin/promtail
```

#verify installation by checking version promtail --version

Now, it's time to create a config file for Promtail. #create dir in /etc sudo mkdir -p /etc/promtail /etc/promtail/logs

```
npci@node1:~$ #create dir in /etc
sudo mkdir -p /etc/promtail /etc/promtail/logs
npci@node1:~$
```

#promtail config file for nginx

sudo curl -o /etc/promtail/promtail-config.yaml -L

"https://gist.githubusercontent.com/theLazyCat775/6fe9125e529221166e9f02b00244638a/raw/8 4f510e6f62d0e60ab95dbe7f9732a629a27eb6d/promtail-config.yaml"

promtail-config.yaml

server:

http_listen_port: 9080 grpc_listen_port: 0

positions:

filename: /etc/promtail/positions.yaml

clients:

- url: http://localhost:3100/loki/api/v1/push

scrape_configs:

- job_name: nginx static configs:

- targets:

- localhost

labels:

job: nginx

hostname: your-hostname
__path__: /var/log/nginx/*.log

Configure Promtail to run as a service.

#Create a file called promtail.service sudo vi /etc/systemd/system/promtail.service

npci@node1:~\$ sudo nano /etc/systemd/system/promtail.service
npci@node1:~\$ sudo nano /etc/systemd/system/promtail.service

Add the script and save.

[Unit]

Description=Promtail service

After=network.target

[Service]

Type=simple

User=root

ExecStart=/usr/local/bin/promtail -config.file /etc/promtail/promtail-config.yaml

Restart=on-failure

RestartSec=20

StandardOutput=append:/etc/promtail/logs/promtail.log

StandardError=append:/etc/promtail/logs/promtail.log

[Install]

WantedBy=multi-user.target

Run below command to start promtail as a service.

sudo systemctl daemon-reload #To reload systemd sudo systemctl start promtail #to start promtail sudo systemctl status promtail #to check status sudo systemctl restart promtail #to restart