

### Lab Exercises

# Setting up Management Authentication and Authorization for IBM Access Manager

Course code LIL0151X



#### February 2018 edition

#### **NOTICES**

This information was developed for products and services offered in the USA.

IBM may not offer the products, services, or features discussed in this document in other countries. Consult your local IBM representative for information on the products and services currently available in your area. Any reference to an IBM product, program, or service is not intended to state or imply that only that IBM product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any IBM intellectual property right may be used instead. However, it is the user's responsibility to evaluate and verify the operation of any non-IBM product, program, or service.

IBM may have patents or pending patent applications covering subject matter described in this document. The furnishing of this document does not grant you any license to these patents. You can send license inquiries, in writing, to:

IBM Director of Licensing IBM Corporation North Castle Drive, MD-NC119 Armonk, NY 10504-1785 United States of America

The following paragraph does not apply to the United Kingdom or any other country where such provisions are inconsistent with local law: INTERNATIONAL BUSINESS MACHINES CORPORATION PROVIDES THIS PUBLICATION "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF NON-INFRINGEMENT, MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE. Some states do not allow disclaimer of express or implied warranties in certain transactions, therefore, this statement may not apply to you.

This information could include technical inaccuracies or typographical errors. Changes are periodically made to the information herein; these changes will be incorporated in new editions of the publication. IBM may make improvements and/or changes in the product(s) and/or the program(s) described in this publication at any time without notice.

Any references in this information to non-IBM websites are provided for convenience only and do not in any manner serve as an endorsement of those websites. The materials at those websites are not part of the materials for this IBM product and use of those websites is at your own risk.

IBM may use or distribute any of the information you supply in any way it believes appropriate without incurring any obligation to you.

Information concerning non-IBM products was obtained from the suppliers of those products, their published announcements or other publicly available sources. IBM has not tested those products and cannot confirm the accuracy of performance, compatibility or any other claims related to non-IBM products. Questions on the capabilities of non-IBM products should be addressed to the suppliers of those products.

This information contains examples of data and reports used in daily business operations. To illustrate them as completely as possible, the examples include the names of individuals, companies, brands, and products. All of these names are fictitious and any similarity to the names and addresses used by an actual business enterprise is entirely coincidental.

#### **TRADEMARKS**

IBM, the IBM logo, and ibm.com are trademarks or registered trademarks of International Business Machines Corp., registered in many jurisdictions worldwide. Other product and service names might be trademarks of IBM or other companies. A current list of IBM trademarks is available on the web at "Copyright and trademark information" at www.ibm.com/legal/copytrade.shtml.

Adobe, the Adobe logo, PostScript, and the PostScript logo are either registered trademarks or trademarks of Adobe Systems Incorporated in the United States, and/or other countries.

Cell Broadband Engine is a trademark of Sony Computer Entertainment, Inc. in the United States, other countries, or both and is used under license therefrom.

Intel, Intel logo, Intel Inside, Intel Inside logo, Intel Centrino, Intel Centrino logo, Celeron, Intel Xeon, Intel SpeedStep, Itanium, and Pentium are trademarks or registered trademarks of Intel Corporation or its subsidiaries in the United States and other countries.

IT Infrastructure Library is a Registered Trade Mark of AXELOS Limited.

ITIL is a Registered Trade Mark of AXELOS Limited.

Java and all Java-based trademarks and logos are trademarks or registered trademarks of Oracle and/or its affiliates.

Linear Tape-Open, LTO, the LTO Logo, Ultrium, and the Ultrium logo are trademarks of HP, IBM Corp. and Quantum in the U.S. and other countries.

Linux is a registered trademark of Linus Torvalds in the United States, other countries, or both.

Microsoft, Windows, Windows NT, and the Windows logo are trademarks of Microsoft Corporation in the United States, other countries, or both

UNIX is a registered trademark of The Open Group in the United States and other countries.

#### © Copyright International Business Machines Corporation 2018.

This document may not be reproduced in whole or in part without the prior written permission of IBM.

US Government Users Restricted Rights - Use, duplication or disclosure restricted by GSA ADP Schedule Contract with IBM Corp.

## **Contents**

Exercises	1
Lab environment	.1
Starting LDAP	4
Exercise 1 Configuring management authentication	5
Exercise 2 Configuring management authorization	8

© Copyright IBM Corp. 2018 iii

## **Exercises**

This lab demonstrates how to set up management authentication and authorization for IBM Access Manager. In this lab, you learn how to configure external authentication and authorization using LDAP. You also verify that the different user groups can authenticate with Access Manager and then test the user's authorizations.

## Lab environment

You use the following virtual machines to perform the exercises in this lab:

#### 1. UserVM


This is a Linux server used to perform all configuration in appliances.

#### 2. IBM Access Manager appliance VM

This VM hosts the IBM Access Manager V9.0.2.0 appliance.

#### 3. IBM Directory Server appliance VM (LDAP VM)

This VM hosts IBM Directory Server V8.0.1 appliance.



Use the information in the following tables to log on to these systems.

System details	IP Address	Host name	Short name
Appliance VM	192.168.42.196	iamidpa.ibmemm.edu	iamidpa
User VM	192.168.42.195	iamd.ibmemm.edu	iamd
LDAP VM	192.168.42.111	sds1.com	sds1

Application/Server	User	Password
Appliance login	admin	P@ssw0rd
User VM login	user / root	P@ssw0rd
IAM Appliance administration console	admin	P@ssw0rd
https://iamidpa.ibmemm.edu/core/login		
LDAP Appliance administration console	admin	P@ssw0rd
https://sds1.com		

LDAP Users	Group Membership	Password
binduser	admins	P@ssw0rd
admin	admins	object00
bob	auditors	object00
peter	auditors	object00



**Hint:** All passwords are the word *password* spelled with a capital letter *P*, @ sign, and zero for the letter O.




**Important:** Before beginning the exercises, ensure that the **iamspa**, **iamspb**, and **iamd** systems are powered up and running.



**Note:** You use the **iamd** system to perform all configuration for this lab exercises.


#### LDAP structure overview

The IBM Directory Server appliance VM includes an LDAP instance organized as shown in the following figure.




The LDAP instance includes users and groups set up as described here:


The LDAP instance has two groups: admins and auditors.



The admins group includes two user members: admin and binduser.



• The auditors group has two user members: bob (Bob Garcia) and peter (Peter Wade).



## **Starting LDAP**

- 1. Select the **iamd** virtual image.
- 2. If needed, log in with user name user and password P@ssw0rd.
- 3. To log in to the local management interface (LMI), open a browser.
- 4. Navigate to <a href="https://sds1.com">https://sds1.com</a>.
- Log in with user name admin and password P@ssw0rd.
  The LMI window opens.
- 6. In the Server Control section, select **Directory Server** and click **Start**.




© Copyright IBM Corp. 2018 4

# Exercise 1 Configuring management authentication

In this exercise, you configure the management authentication on the **iamidpa** system with external LDAP and then verify that the admin and admin@local users can access the local management interface (LMI).

## Task 1 Setting up management authentication

- 1. Select the **iamd** virtual image.
- 2. If needed, log in with user name user and password P@ssw0rd.
- 3. To log in to the LMI, open a browser.
- 4. Navigate to https://iamidpa.ibmemm.edu.
- Login with user name admin and password P@ssw0rd.
  The LMI window opens.
- 6. Navigate to Manage System Settings > System Settings: Management Authentication.




© Copyright IBM Corp. 2018 5

6

7. Select the Remote LDAP User Registry option.



- 8. Click Next.
- 9. In the LDAP tab's Host name field, enter sds1.com.
- 10. In the Port field, enter 389.
- 11. Clear the **Anonymous Bind** check box.
- 12. In the Bind DN field, enter cn=binduser, ou=adminusers, o=myorg, c=us.
- 13. In the Bind Password field, enter P@ssw0rd.




14. Click Next.


The LDAP General tab opens.

- 15. In the **User Attribute** field, verify that **uid** is the default.
- 16. In the Group Member Attribute field, enter uniquemember.
- 17. In the Base DN field, enter c=us.

18. In the Administrative Group DN field, enter cn=admins, ou=groups, o=myorg, c=us.




- 19. Click Next.
- 20. On the **LDAP SSL** tab, leave the default settings.



- 21. Click Save.
- 22. To deploy the changes, click the **Click here to review the changes or apply them to the system** link.
- 23. In the Deploy Pending Changes window, click **Deploy**.
- 24. Verify that the System Notification Successfully deployed all pending changes.
- 25. In the LMI, click admin > Logout.

## Task 2 Log in as an external user

- 1. Navigate to https://iamidpa.ibmemm.edu.
- Log in with user name admin and password object00.The LMI window opens.





**Note:** You should be able to log in successfully as the user **admin**, which is located on the external LDAP system sds1.com.

3. In the LMI, click admin > Logout.

## Task 3 Log in as a local user

- 1. Navigate to https://iamidpa.ibmemm.edu.
- 2. Log in with user name admin@local and password P@sswOrd, and click login.





**Note:** You should be able to log in successfully. Notice that **admin@local** is a local user instead of an external LDAP user admin.

3. In the LMI, click admin@local > Logout.

## Exercise 2 Configuring management authorization

In this exercise, you configure the management authorization for the admins and auditors groups on the **iamidpa** system using external LDAP. When the authorizations are configured, you then log in to the appliance as an auditor and admin to test each user group's functionality.

© Copyright IBM Corp. 2018 8

## Task 1 Setting up management authorization

- 1. Navigate to <a href="https://iamidpa.ibmemm.edu">https://iamidpa.ibmemm.edu</a>.
- 2. If needed, log in with user name admin@local and password P@ssw0rd.
- 3. Navigate to Manage System Settings > System Settings: Management Authorization.



4. Select the Enable Authorization Roles check box.




- 5. To deploy the changes, click the Click here to review the changes or apply them to the system link.
- 6. In the Deploy Pending Changes window, click **Deploy**.
- 7. Verify that the System Notification Successfully deployed all pending changes.

© Copyright IBM Corp. 2018 9

10


8. Navigate to Manage System Settings > System Settings: Management Authentication.



- 9. Click the LDAP tab.
- 10. In the Bind Password field, type P@ssw0rd.




**Note:** You must retype the **Bind Password** value every time you change the Management Authentication configuration.



11. Click Next.

The **LDAP Generate** tab displays.

12. In the Administrative Group DN field, update the string to ou=groups, o=myorg, c=us.




- 13. Click Next.
- 14. On the **LDAP SSL** tab, leave the default settings.
- 15. Click **Save** and then **Deploy** to deploy the changes.
- 16. Verify that the System Notification Successfully deployed all pending changes.
- 17. Navigate to Manage System Settings > System Settings: Management Authorization.

18. In the Roles list, select **Global Administrators**.



19. In the right pane, click the **Remote LDAP User Registry** tab.



20. Above the Group name area, click Edit.



13


- 21. Click the **Groups** tab.
- 22. For the Groups name, enter admins and then click Search.

#### **Edit Remote LDAP Members**


The remote LDAP user registry can be set on the following page: Management Authentication




23. In the Search list, select admins and click Add.



24. Verify that **admins** is listed in the Group name list.



- 25. Click **OK**.
- 26. In the Roles list, select Security Viewer.



27. In the right pane, click the **Remote LDAP User Registry** tab.




28. Above the Group name area, click Edit.




29. For the Groups name, enter auditors and then click Search.

#### **Edit Remote LDAP Members**


The remote LDAP user registry can be set on the following page: Management Authentication



30. In the Search list, select **auditors** and click **Add**.



31. Verify that **auditors** is listed in the Group name list.



- 32. Click **OK**.
- 33. Click **Save** and then **Deploy**.
- 34. In the LMI, click admin@local > Logout.

## Task 2 Testing the auditors authorizations

- 1. Navigate to <a href="https://iamidpa.ibmemm.edu">https://iamidpa.ibmemm.edu</a>.
- 2. Log in with user name bob and password object00.





**Note:** You should be able to log in successfully with user **bob**, which is a member of the auditors group that is located in external LDAP system sds1.com.

3. Select Manage System Settings.





Note: You should see fewer management options.

Navigate to Secure Web Settings > Manage: Runtime Component.



Go to Application Log Files to view the Policy Server and User Registry log files.

5. Click Restart.





**Note:** You should get an error message because bob does not have permission to restart the appliance.

## Task 3 Testing the admin authorizations

- 1. Navigate to <a href="https://iamidpa.ibmemm.edu">https://iamidpa.ibmemm.edu</a>.
- 2. Log in with user name admin and password object00.





Note: You should be able to log in successfully.

- 3. Navigate to Secure Web Settings > Manage: Runtime Component.
- 4. Click Restart.





Note: The admin user should be able to restart the runtime component successfully.



