DMT Content Provision Guide

Rules and naming conventions for master data, conversion content and facelift content

Generated 16 Oct 2026 from the DMT Settings page

Contents

1 Overview 2

2 Processing Sequence 3

3 Folder Structure 4

4 Master Data Files 5

5 Content Text Files 6

6 Master Data Automation 8

7 Facelift Automation 9

8 Master Data Syncing 10

9 Scheduling Rules 11

10 Jobs, Reports, Validation 12

This guide is also available on the DMT **Settings** page. Follow the folder and file naming conventions exactly - DMT discovers markets, locales, models, manual types and files by their names.

Overview

DMT loads master data and manual content from a network location into Kapture for the MC, MME and MNAO markets.

Settings

Your source network path, saved per user. It can be changed at any time - a running job keeps the path it started with.

Schedule

Folder Based Content Load (conversion) and **IPM Facelift VIN Update** (facelift automation).

History

Job status, item details, report download, abort, and the Preview link of a conversion job.

Preview / Publish

Conversion loads documents as **Draft**. Review them on the Preview page, then publish from there.

Meta Data Validation

Upload VIN, ESI category, display order and CD text files to check them against MDM and Kapture before a load.

Master Data Syncing

Sends MDM master data that is waiting for sync to the Kapture categories, per market and item type.

Network path: mandatory, at most 300 characters. It can point at the folder that holds `MDM`, `GMS3_Content` and `Facelift_Content`, or directly at the `GMS3_Content` folder (then `MDM` and `Facelift_Content` must sit beside it).

Processing Sequence

Process in this order. Each step depends on the one before it.

1. **Place master data (MDM folder)**
   MDM Excel exports for every locale you will process (see Master Data Files).

2. **Sync master data to Kapture**
   Run **Master Data Syncing** for the market, or choose the load type **Master Data with Content / Master Data with Facelift** so the job loads it first.

3. **Facelift - IPM Facelift VIN Update**
   If Excel files are in `Facelift_Content`: Validate Data, Identify, View, Schedule. Old VINs are replaced by new VINs on existing documents.

4. **Conversion - Folder Based Content Load**
   Market, Locale, Model, Manual Type, Go, select rows, choose the load type, Schedule. Documents are created / updated in Kapture as Draft.

5. **Review the reports and the Preview**
   Download the reports zip from History and check the Failure / Missing Categories reports.

6. **Publish**
   Publish from the job's Preview page. Follow the publish job on the History page.

Facelift before conversion: when Excel files are present in `Facelift_Content`, the conversion Go asks *"The IPM Facelift VIN Update ... must be executed before the Conversion. Have you executed it?"* Answer Yes only after the facelift job has finished.

Jobs run in parallel (at most 5 Pending / Processing at once): conversions and publish jobs run side by side when they work on different rows; facelift (IPM Facelift VIN Update, Document Identification) and Master Data Syncing jobs run side by side too, but never together with a conversion or publish job. See Scheduling Rules.

Folder Structure

Folder names are used as they are. Keep the exact names and nesting below.

```
<Network path>
 |-- MDM                                          master data Excel files (all locales, flat)
 |-- Facelift_Content                             facelift VIN Excel files (flat, any locale mix)
 `-- GMS3_Content
      `-- <MARKET>                                MC | MME | MNAO
           `-- <locale>                           ja-JP, en-UK, en-US, fr-CA ...
                `-- <model folder>                NewM_familia_van_ncp | CX-5_KM
                     `-- <manual type>            WM, SH, WD, e-WD, BSM ...
                          `-- <facelift folder>   FL0000, FL0001 ...
                               |-- vin.txt        VIN ranges (vin1.txt ... allowed)
                               |-- d01.txt ...    display order, named in vin.txt
                               |-- CD00.txt ...   CD processing (MC / MME only)
                               |-- scmvin.txt     MME, WM only
                               `-- <material folder>   E-W1J-7EC7_HTML, ..._PDF, ..._XML
                                    |-- esicat.txt   document list + ESI codes
                                    `-- html | html5 | pdf | djvu | ent.gms3 | img.gms3 | figure(s)
```

NAMING PER LEVEL

Level	Convention	Example
Market	Exactly `MC`, `MME` or `MNAO`. Other folders are listed but not processed.	`MC`
Locale	Language-country with a hyphen. It must match the locale in the MDM Excel file names and be a locale configured in DMT.	`ja-JP`, `en-UK`, `en-US`
Model (MC / MME)	`NewM_<model>_<code>` or `OldM_<model>_<code>`. In MC, any other prefix is handled as OEM content.	`NewM_BT-50_tf`, `Isuzu_titan_lh`
Model (MNAO)	`<model>_<code>`, no NewM / OldM prefix. The model is the part before the last `_`.	`CX-5_KM`, `BT-50_TF`
Manual type	Shown as the folder name. `WD` and `e-WD` switch on wiring diagram handling.	`WM`, `e-WD`
Facelift folder	One folder per facelift. A new facelift folder creates new articles.	`FL0012`
Material folder	The suffix after the last `_` gives the format (`_HTML`, `_XML`, `_PDF`).	`E-WZE-8FC2_HTML`

> **Facelift-only location:** `GMS3_Content` is not needed when only `MDM` and `Facelift_Content` are provided.

Master Data Files (MDM folder)

MDM export files, one per locale and master data type, placed directly in the `MDM` folder.

File name

`<CC>_<LOCALE>_<TYPE>.xlsx`
CC = 2-letter country code, LOCALE = `xx-XX`, TYPE = one of the types below. `.xlsx` or `.xls` only.

Examples

`JP_JA-JP_CARLINE.xlsx`
`UK_EN-UK_ALL_VIN.xlsx`
`US_EN-US_DRIVELINE_AXLE_TYPE.xlsx`

TYPES (LOADED IN THIS ORDER)

#	TYPE	Data columns
1	`CARLINE`	CARLINE CODE, CAR NAME ENG LANG, CAR NAME REGIONAL LANG, WMI CODE, MODEL TYPE, ESI CATEGORY FLAG, IC DISPLAY CARLINE CODE. **MNAO:** columns 5-6 are YEAR START, YEAR END (4 digits, end not before start).
2	`CAT`	LEVEL 1 CODE, LEVEL 1, LEVEL 2 CODE, LEVEL 2, LEVEL 3 CODE, LEVEL 3
3	`ENGINE_BOOK`	3 columns
4	`ENGINE_TYPE`	ENGINE BOOK CODE, ENGINE TYPE CODE, NAME, GROUP TYPE (the engine book must exist)
5	`TRANSMISSION_BOOK`	3 columns
6	`TRANSMISSION_TYPE`	3 columns
7	`DRIVELINE_AXLE_TYPE`	3 columns (code, regional name, English name)
8	`BODY_TYPE`	3 columns (code, regional name, English name)
9	`ALL_VIN`	MODEL, CARLINE CODE, GROUP, WMI, VDS, VIS START, VIS END, ENGINE CODE, TRANSMISSION_CODE (the carline must exist)

SHEET LAYOUT

- Sheet name `EXPORTED DATA`, header in row 1, data from row 2.
- The column right after the data columns must be headed `Indicator`.
- Indicator: A / ADD | U / UPDATE | blank = add or update; D / DELETE = mark the row deleted. Any other value fails the row.
- Mandatory fields that are empty fail the row (*"X is empty."*).

en-CA (MNAO): content never comes for en-CA, but an en-US load also loads `CA_EN-CA_*.xlsx` when present and syncs its waiting categories. A missing en-CA file is not an error.

Avoid: two files with the same locale and type (only one is used), other file types in the folder, and a country / language that is not set up in MDM (the load stops for that locale).

Content Text Files

Fields are separated by `||`, one entry per line, each line ending with `;`.

VIN FILE - FACELIFT FOLDER (`VIN.TXT`, `VIN1.TXT` ...)

Market	Fields	Layout
MC	8	`MANUAL TYPE||FL FOLDER||MATERIAL||CARLINE||VDS||VIS START||VIS END||DISPLAY ORDER FILE`
MME	9	`MANUAL TYPE||FL FOLDER||MATERIAL||CARLINE||WMI||VDS||VIS START||VIS END||DISPLAY ORDER FILE`
MNAO	11	`MANUAL TYPE||FL FOLDER||MATERIAL||CARLINE||WMI||VDS||VIS START||VIS END||MODEL||YEAR||DISPLAY ORDER FILE` All 11 fields are required, e.g. `WM||FL0012||E-WZE-8FC2_MY2026_HTML||TF||AMP2||TFR**JT*||600001||649999||CX90||2026MY||d01.txt;`

- **SCM VIN file** (MME, manual type WM only): `scmvin.txt`, 9 fields ending with the source ENT file name.
- **Overhaul books** (Engine / AT / MT): VIN data comes from MDM, no VIN file is needed.

DISPLAY ORDER FILE - FACELIFT FOLDER (`D01.TXT`, `D02.TXT` ...)

The name starts with `d`, ends with `.txt` and must be exactly the name given in the last field of the VIN file. A `delete.txt` file is not used any more and is ignored.

`MODEL FOLDER||MANUAL TYPE||FL FOLDER||MATERIAL||PROCESSING FOLDER||FILE NAME||TITLE||ENGINE TYPE||TRANSMISSION TYPE||BODY TYPE||DRIVE AXLE TYPE||LEVEL 1 .. LEVEL 6||SEQUENCE`

- Levels are **names** (1 to 6 levels); the sequence is always the last field.
- Engine / AT / MT overhaul books leave out TITLE and the four type fields.

CD FILE - FACELIFT FOLDER (`CD00.TXT` ..., MC / MME ONLY)

Name starts with `CD`; same layout as the display order file. MNAO has no CD file.

> **Display order and CD files are complete lists:** for every material folder named in vin.txt, a document that is not listed - or whose line is invalid (an empty folder / file name field) or carries a wrong path - **loses its view content** (display order) and **its CD data** (CD file, MC / MME) on the next load. A material folder without any line loses all of it. The document itself stays in Kapture and, when converted, still shows in that job's Preview without a place in the tree. Removed rows are reported as `DELETE` in DISPLAY_ORDER.xlsx / CD_PROCESSING_DATA.xlsx. See **Examples** at the end of this tab.

ESI CATEGORY FILE - MATERIAL FOLDER (`ESICAT.TXT`)

Case	Layout
MC / MME / MNAO	`FL FOLDER||MATERIAL||PROCESSING FOLDER||FILE NAME||TITLE||ESI CODE 1||ESI CODE 2||ESI CODE 3` e.g. `FL0012||E-WZE-8FC2_MY2026_HTML||html||si_1049129.html||removal||Y1||Y10001||01;`
MME wiring diagrams	9 fields: `STEERING TYPE(S)` after TITLE (e.g. `LEFT_HAND_DRIVE,RIGHT_HAND_DRIVE`).

> **esicat.txt is the document list:** a document already loaded for the material folder but no longer listed in esicat.txt is **deleted (unpublished)** by the next load. To remove a document cleanly, remove it from esicat.txt, the display order / CD files and the folder.

EXAMPLES - CHANGING THE DISPLAY ORDER (MC FAMILIA VAN, FOLDER `E-W1J-7EC7_PDF`)

Example 1 - a document is dropped from the display order

Change: the line of `J_DTSNAMELIST_7.pdf` is removed from `d01.txt`. The PDF stays in the folder and in `esicat.txt`.

`d01.txt (facelift folder FL0001)`

```
NewM_familia_van_ncp||WM||FL0001||E-W1J-7EC7_PDF||pdf||J_DTSNAMELIST_6.pdf||...||0010;
~~NewM_familia_van_ncp||WM||FL0001||E-W1J-7EC7_PDF||pdf||J_DTSNAMELIST_7.pdf||...||0011;~~   line removed
NewM_familia_van_ncp||WM||FL0001||E-W1J-7EC7_PDF||pdf||J_DTSNAMELIST_8.pdf||...||0012;
```

`DISPLAY_ORDER.xlsx (reports zip of the job)`

SOURCE FILE	DOCUMENT ID	OPERATION	STATUS	ERROR MESSAGE
...\E-W1J-7EC7_PDF\pdf\J_DTSNAMELIST_7.pdf	SM231910	**DELETE**	SUCCESS	VIEW CONTENT DELETED - DOCUMENT IS NOT IN THE DISPLAY ORDER FILE.

> **Result:** SM231910 is converted and stays in Kapture, but its **view content and CD data are removed** (it no longer appears under any display order position). In the job's Preview it is shown **without a place in the tree**.

Example 2 - a document is listed, but its file is not delivered

Change: `J_DTSNAMELIST_2.pdf` was loaded and **published** earlier. This time `d01.txt` still lists it, but the PDF is not in the folder, so the job does not convert it.

`d01.txt`

```
NewM_familia_van_ncp||WM||FL0001||E-W1J-7EC7_PDF||pdf||J_DTSNAMELIST_1.pdf||...||0003;
NewM_familia_van_ncp||WM||FL0001||E-W1J-7EC7_PDF||pdf||J_DTSNAMELIST_2.pdf||...||0004;   still listed
```

`E-W1J-7EC7_PDF\pdf (folder)`

```
J_DTSNAMELIST_1.pdf
~~J_DTSNAMELIST_2.pdf~~   not delivered
```

> **Result:** its **view content is still written** from the display order line and **keeps its status** - Published stays Published (a draft stays Draft). It is **not in this job's Preview**, because the job did not convert it.

Master Data Automation

The load type decides whether the job first loads master data from the MDM folder and syncs it to Kapture.

Conversion - "Master Data with Content"

1. **Load MDM Excel**
   For each locale of the selected rows (en-US also brings en-CA), its MDM files are loaded into MDM.
2. **Sync categories to Kapture**
   Every waiting row of the locale is written to the Kapture categories.
3. **Convert documents**
   Content is processed with the categories in place.
4. **Reports**
   MASTER_DATA_LOAD_REPORT + MASTER_DATA_CATEGORY_REPORT in the zip.

Facelift - "Master Data with Facelift"

1. **Load MDM Excel**
   Per market, for the locales of the facelift job (new VIN ranges come from ALL_VIN).
2. **Sync categories to Kapture**
   New VIN categories are created before any document.
3. **Swap VINs on documents**
   Old VIN categories are replaced by the new ones.
4. **Reports**
   Master data reports added to the job zip.

RULES

- The same Excel rules apply as in **Master Data Files**.
- Label rule: when several rows share a reference key, the **last row with a name** gives the label; a blank name keeps the existing label.
- A master data failure never stops the job: content is still processed, and the job ends as FAILURE so the report is reviewed.
- Reports list only added, updated, deleted and failed rows; no report is written when there is nothing to report.

> **"Only Content" / "Only Facelift":** no master data is loaded. Only Content is refused while categories of the selected locales are still waiting for sync. Only Facelift is refused when a new VIN category is not yet in Kapture.

Facelift Automation - IPM Facelift VIN Update

Replaces old VIN ranges by new VIN ranges on documents that are already in Kapture. No upload: DMT reads the `Facelift_Content` folder.

EXCEL FILE

- Any name, `.xlsx` / `.xls` / `.xlsm`; first sheet; header in row 1. Several files and mixed locales are allowed. Open-file locks (`~$...`) are skipped.
- All 11 columns are required on every row:

1	2	3	4	5	6	7	8	9	10	11
LOCALE	OLD CARLINE CODE	OLD WMI	OLD VDS	OLD VIS START	OLD VIS END	NEW CARLINE CODE	NEW WMI	NEW VDS	NEW VIS START	NEW VIS END

FLOW

1. **Validate Data**
   Locale in MDM and Kapture; old VIN in MDM and Kapture; new VIN in MDM and Kapture, or in the locale's ALL_VIN MDM file. More than 10 errors are given as a downloadable error file.
2. **Identify**
   Creates the identification job that finds the impacted SM / OSM / WD documents.
3. **View and select items**
   Choose "Master Data with Facelift" or "Only Facelift", then Schedule.
4. **Facelift job**
   VIN categories are swapped and bulk updated; documents that were published are published again.
5. **Old VIN deactivation**
   Only when the whole job succeeds, the old VIN ranges are made inactive in MDM (OLD_VIN_DEACTIVATION_REPORT). A range that is also a new range of the job is kept.

After the facelift: remove or archive the processed Excel files from `Facelift_Content`. While they are there, every conversion Go asks whether the facelift has been executed.

Not together with content jobs: Identify and the facelift job are refused while a conversion or publish job is Pending / Processing (and a conversion / publish is refused while they run). See Scheduling Rules.

Master Data Syncing

Sends MDM rows that are waiting for sync to the Kapture categories, for every locale mapped to the market.

ITEMS PER MARKET

Market	Items offered
MNAO	Model and Year · VIN Range · ESI Category · Engine Type · Transmission Type · Driveline/Axle Type · Body Type
MC / MME	Carline + VIN · ESI Category · Engine Type · Transmission Type · Driveline/Axle Type · Body Type

Only items with waiting rows are listed. Select the market and at least one item (or All).

RULES

- Only active MDM rows waiting for sync are taken. A locale without its own rows uses the rows of its alternate locale (for example en-UK for MME, en-US for en-CA).
- Every level of a row is attempted. A missing category is created under its parent; a **missing parent fails that level**. The top category is never created here.
- A row is marked synced only when all its levels succeeded in every locale it was processed for. Failed rows stay waiting and are retried by the next run.
- Label rule: last row with a name wins; a blank name keeps the existing label. Each category is also completed in all Kapture default locales.
- Reports: CATEGORY_TRANSACTIONS and CATEGORY_FAILURES in the job zip.

Gate on the Schedule screen: while categories of the selected locales are waiting for sync, an "Only Content" conversion is refused with *"<n> Categories are still remaining for Syncing in Kapture for <market> Market ..."*. Run Master Data Syncing first or choose "Master Data with Content".

Not together with content jobs: Master Data Syncing is refused while a conversion or publish job is Pending / Processing, and the other way round. It can run beside facelift jobs and other syncing jobs. See Scheduling Rules.

Scheduling Rules

Checks made before a job can be scheduled - conversion (Schedule screen), publish (Preview), IPM Facelift VIN Update, Document Identification and Master Data Syncing.

Check	Rule
Selection	Market is mandatory for Go; at least one row must be selected to Schedule.
Job limit	At most 5 jobs (all types) can be Pending or Processing at the same time; the next one is refused until one finishes. Meta Data Validation is not counted.
Content vs master jobs	**Content jobs** (Conversion MC / MME / MNAO, Publish) run in parallel with each other. **Master jobs** (IPM Facelift VIN Update, Document Identification, Master Data Syncing) run in parallel with each other. A content job is refused while a master job is Pending / Processing, and a master job is refused while a content job is.
Item already processing	A row (locale + model folder + manual type + facelift folder + material folder) can be in only one Pending / Processing conversion or publish job, in any market. A job without a facelift / material folder covers all of them, so it overlaps every row of that locale, model and manual type. Locales are compared without case and with `_` and `-` alike (`en_US` = `en-US`).
VIN + display order	A row with documents needs a VIN file and its display order file. Refused when: no VIN or display order file, only one of the two, VIN lines without proper VINs, or the display order file named in vin.txt is missing.
Material folders	Refused when none of the material folders named in the VIN file exists under the facelift folder.
Master data waiting	"Only Content" refused while categories of the selected locales wait for sync (see Master Data Syncing).
Facelift pending	Facelift Excel present: Go asks for confirmation that the facelift has been executed.
Publish	Refused while the conversion job is still running, when nothing is left to publish, or when its items are being processed by other jobs.

Network path changes are allowed at any time. Each job takes the path when it starts (a facelift job when it is scheduled), so jobs started from different paths can run side by side.

MESSAGES YOU MAY SEE

- Job limit: *"The job cannot be scheduled now - the limit of 5 jobs Pending / Processing at the same time is reached: <jobs> ..."*
- Conversion / publish while a master job runs: *"The Conversion / Publish job cannot be scheduled now - an IPM Facelift VIN Update / Document Identification / Master Data Syncing job is Pending / Processing: <jobs> ..."*
- Master job while a content job runs: *"The job cannot be scheduled now - a Conversion / Publish job is Pending / Processing: <jobs> ..."*
- Row overlap: *"Row No.<n> is already Processing under - <job>."*

Jobs left Pending after a server restart are not cleaned up automatically. They still count towards the limit and keep their rows busy - abort them from the History page.

Jobs, Reports and Meta Data Validation

How DMT names its jobs and reports, and the file naming expected by Meta Data Validation.

JOB NAMES

Job	Name
Conversion	`MGSS_CONV_<MC|MME|MNAO>_yyyyMMdd_<id>`
Publish	`MGSS_PUB_<market>_yyyyMMdd_<conversion job id>`
Facelift identification	`MGSS_DI_SYNCyyyyMMdd_<id>`
Facelift job	`MGSS_MDSYNC_yyyyMMdd_<id>`
Master Data Syncing	`MGSS_MDSYNC_<MARKET>_<id>`

REPORTS (IN THE JOB ZIP)

Job	Reports
Conversion	TRANSACTION_REPORT, FAILURE_REPORT, MISSING_CATEGORIES, DISPLAY_ORDER, CD_PROCESSING_DATA (MC / MME), VIEW_CONTENT_REPORT (MNAO: VIEW_CONTENT_MODEL_YEAR_REPORT + VIEW_CONTENT_VIN_REPORT), INNER_LINKS_REPORT, OTHER_MANUAL_LINKS_REPORT, VOLTAGE_*_JS_REPORT (WD)
Master data load	MASTER_DATA_LOAD_REPORT, MASTER_DATA_CATEGORY_REPORT
Facelift	OLD_VIN_DEACTIVATION_REPORT, VIN_MANUAL_TYPE_MAPPING_REPORT (MME)
Master Data Syncing	CATEGORY_TRANSACTIONS, CATEGORY_FAILURES

> **DISPLAY_ORDER / CD_PROCESSING_DATA:** the `OPERATION` column shows `INSERT` for listed documents and `DELETE` for documents whose view content / CD data was removed because they are no longer listed.

META DATA VALIDATION UPLOADS

Market	File types
MC	VIN, ESI Category New / Old, Display Order, CD Processing
MME	VIN, ESI Category Manuals New / Old, ESI Category WD New / Old, Display Order, CD Processing
MNAO	VIN (11 fields), ESI Category, Display Order

`.txt` files only; the name must start with `vin` (VIN), `esi` (ESI Category), `d` (Display Order) or `cd` (CD Processing). Formats are the same as in **Content Text Files**.