Package 'PCMBase'

March 15, 2024

Type Package

Title Simulation and Likelihood Calculation of Phylogenetic Comparative Models

Version 1.2.14

Maintainer Venelin Mitov <vmitov@gmail.com>

Description Phylogenetic comparative methods represent models of continuous trait data associated with the tips of a phylogenetic tree. Examples of such models are Gaussian continuous time branching stochastic processes such as Brownian motion (BM) and Ornstein-Uhlenbeck (OU) processes, which regard the data at the tips of the tree as an observed (final) state of a Markov process starting from an initial state at the root and evolving along the branches of the tree. The PCMBase R package provides a general framework for manipulating such models. This framework consists of an application programming interface for specifying data and model parameters, and efficient algorithms for simulating trait evolution under a model and calculating the likelihood of model parameters for an assumed model and trait data. The package implements a growing collection of models, which currently includes BM, OU, BM/OU with jumps, two-speed OU as well as mixed Gaussian models, in which different types of the above models can be associated with different branches of the tree. The PCMBase package is limited to trait-simulation and likelihood calculation of (mixed) Gaussian phylogenetic models. The PCMFit package provides functionality for inference of these models to tree and trait data. The package web-site <https://venelin.github.io/PCMBase/>

provides access to the documentation and other resources.

Encoding UTF-8

License GPL (>= 3.0)

LazyData true

Depends R (>= 3.1.0)

Imports ape, abind, expm, mvtnorm, data.table, ggplot2, xtable

Suggests testthat, knitr, rmarkdown, ggtree, cowplot, covr, mvSLOUCH, BiocManager

RoxygenNote 7.1.2

ByteCompile yes

VignetteBuilder knitr, rmarkdown

URL https://venelin.github.io/PCMBase/, https://venelin.github.io

 $\pmb{BugReports} \ \text{https://github.com/venelin/PCMBase/issues}$

NeedsCompilation no

Repository CRAN

Author Venelin Mitov [aut, cre, cph] (venelin.github.io),

Krzysztof Bartoszek [ctb],

Georgios Asimomitis [ctb],

Tanja Stadler [ths]

Date/Publication 2024-03-15 20:10:02 UTC

R topics documented:

Args_MixedGaussian_MGPMDefaultModelTypes	5
Args_MixedGaussian_MGPMScalarOUType	6
Args_MixedGaussian_MGPMSurfaceOUType	6
as.MixedGaussian	7
dataFig3	8
FormatCellAsLatex	8
FormatTableAsLatex	9
is.GaussianPCM	9
is.MixedGaussian	10
	10
is.PCMTree	11
MatchListMembers	11
MGPMScalarOUType	12
MGPMSurfaceOUType	12
MixedGaussian	13
MixedGaussianTemplate	14
PCM	15
PCMAbCdEf	17
PCMAddToListAttribute	18
PCMApplyTransformation	19
PCMBaseIsADevRelease	20
PCMBaseTestObjects	20
PCMColorPalette	22
	22
	23
PCMCond.GaussianPCM	24
	25
	26
PCMDefaultModelTypes	27
PCMDefaultObject	
·	29
	29

PCMDescribeParameters	
PCMExtractDimensions	. 30
PCMExtractRegimes	. 30
PCMFindMethod	. 31
PCMFixParameter	. 32
PCMGenerateModelTypes	. 32
PCMGenerateParameterizations	. 33
PCMGetAttribute	
PCMGetVecParamsRegimesAndModels	
PCMInfo	
PCMLik	
PCMLikDmvNorm	
PCMLikTrace	
PCMListMembers	
PCMListParameterizations	
PCMLmr	
PCMMapModelTypesToRegimes	
PCMMean	
PCMMeanAtTime	
PCMModels	
PCMModelTypes	
PCMNumRegimes	
PCMNumTraits	
PCMOptions	
PCMPairSums	
PCMParam	
PCMParamBindRegimeParams	
PCMParamCount	
PCMParamGetShortVector	
PCMParamLoadOrStore	
PCMParamLocateInShortVector	
PCMParamLowerLimit	. 58
PCMParamRandomVecParams	
PCMParamSetByName	
PCMParamType	
PCMParamUpperLimit	. 63
PCMParentClasses	. 63
PCMParseErrorMessage	. 64
PCMPExpxMeanExp	. 64
PCMPLambdaP_1	. 65
PCMPlotGaussianDensityGrid2D	. 66
PCMPlotGaussianSample2D	
PCMPlotMath	
PCMPlotTraitData2D	
PCMPresentCoordinates	
PCMRegimes	
PCMSetAttribute	. 70
PCMSim	71

PCMSpecify	73
PCMTable	73
PCMTableParameterizations	74
PCMTrajectory	75
PCMTree	77
PCMTreeBackbonePartition	79
PCMTreeDropClade	81
PCMTreeDtNodes	82
PCMTreeEdgeTimes	83
PCMTreeEvalNestedEDxOnTree	84
PCMTreeExtractClade	85
PCMTreeGetBranchLength	
PCMTreeGetDaughters	
PCMTreeGetLabels	
PCMTreeGetParent	
PCMTreeGetPartition	
PCMTreeGetPartNames	
PCMTreeGetPartRegimes	90
PCMTreeGetPartsForNodes	90
PCMTreeGetRegimesForEdges	91
PCMTreeGetRegimesForNodes	91
PCMTreeGetTipsInPart	92
PCMTreeGetTipsInRegime	93
PCMTreeInsertSingletons	94
PCMTreeJumps	96
PCMTreeListAllPartitions	97
PCMTreeListCladePartitions	98
PCMTreeListDescendants	
PCMTreeListRootPaths	
PCMTreeLocateEpochOnBranches	
PCMTreeLocateMidpointsOnBranches	
PCMTreeMatchLabels	
PCMTreeMatrixNodesInSamePart	
PCMTreeNearestNodesToEpoch	
PCMTreeNodeTimes	
PCMTreeNumNodes	
PCMTreeNumParts	
PCMTreeNumTips	
•	
PCMTreePostorder	
PCMTreePreorder	
PCMTreeSetLabels	
PCMTreeSetPartition	
PCMTreeSetPartRegimes	
PCMTreeSetRegimesForEdges	
PCMTreeSplitAtNode	
PCMTreeTableAncestors	14
PCMTreeToString	115

122

PCMTreeVCV						 								
PCMUnfixParameter														
PCMVar														
PCMVarAtTime														
RequireSuggestedPackages .														
TruePositiveRate														
UpperTriFactor														
White						 								

Args_MixedGaussian_MGPMDefaultModelTypes

Arguments to be passed to the constructor MixedGaussian when constructing a MGPM model with some of the default MGPM model types.

Description

Index

Arguments to be passed to the constructor MixedGaussian when constructing a MGPM model with some of the default MGPM model types.

Usage

 $Args_MixedGaussian_MGPMDefaultModelTypes(omitGlobalSigmae_x = TRUE)$

Arguments

omitGlobalSigmae_x

logical, indicating if the returned list should specify the global Sigmae_x parameter as '_Omitted'. Default: TRUE.

Value

a list of named arguments. Currently only a named element Sigmae_x with specification depending on $\mbox{omitGlobalSigmae}_x$.

See Also

MGPMDefault Model Types

Args_MixedGaussian_MGPMScalarOUType

Arguments for the MixedGaussian constructor for scalar OU MGPM models.

Description

Arguments for the MixedGaussian constructor for scalar OU MGPM models.

Usage

Args_MixedGaussian_MGPMScalarOUType()

Value

a list.

Args_MixedGaussian_MGPMSurfaceOUType

Arguments for the MixedGaussian constructor for SURFACE OU MGPM models.

Description

Arguments for the MixedGaussian constructor for SURFACE OU MGPM models.

Usage

Args_MixedGaussian_MGPMSurfaceOUType()

Value

a list.

as.MixedGaussian 7

as.MixedGaussian	${\it Convert\ a\ {\it GaussianPCM}\ model\ object\ to\ a\ {\it MixedGaussian}\ model\ object}$
------------------	---

Description

Convert a Gaussian PCM model object to a MixedGaussian model object

Usage

```
as.MixedGaussian(o, modelTypes = NULL)
```

Arguments

0

an R object: either a GaussianPCM or a MixedGaussian.

modelTypes

NULL (the default) or a (possibly named) character string vector. Each such string denotes a mixed Gaussian regime model class, e.g. the result of calling MGPMDefaultModelTypes(). If specified, an attempt is made to match the deduced Gaussian regime model type from o with the elements of modelTypes and an error is raised if the match fails. If the match succeeds the converted MixedGaussian object will have the specified modelTypes parameter as an attribute "modelTypes".

Value

a MixedGaussian object.

Examples

```
mg <- as.MixedGaussian(PCMBaseTestObjects$model.ab.123.bSigmae_x)
stopifnot(
   PCMLik(
    X = PCMBaseTestObjects$traits.ab.123,
   PCMBaseTestObjects$tree.ab,
   PCMBaseTestObjects$model.ab.123.bSigmae_x) ==
PCMLik(
   X = PCMBaseTestObjects$traits.ab.123,
   PCMBaseTestObjects$tree.ab,
   mg))</pre>
```

8 FormatCellAsLatex

dataFig3

Data for Fig3 in the TPB manuscript

Description

A list containing simulated tree, models and data used in Fig. 3

Usage

dataFig3

Format

This is a list containing the following named elements representing simulation parameters, a simulated tree and PCM objects, used in Fig. 3. For details on all these objects, read the file data-raw/Fig3.Rmd.

FormatCellAsLatex

Latex representation of a model parameter or other found in a data.table object

Description

Latex representation of a model parameter or other found in a data.table object

Usage

FormatCellAsLatex(x)

Arguments

Χ

an R object. Currently, character vectors of length 1, numeric vectors and matrices are supported.

Value

a character string

FormatTableAsLatex 9

FormatTableAsLatex

Latex representation of a data.table with matrix and vectors in its cells

Description

Latex representation of a data.table with matrix and vectors in its cells

Usage

```
FormatTableAsLatex(x, argsXtable = list(), ...)
```

Arguments

```
x a data.tableargsXtable a list (empty list by default) passed to xtable...additional arguments passed to print.xtable.
```

Value

a character string representing a parseable latex text.

Examples

```
dt <- data.table::data.table(
    A = list(
        matrix(c(2, 0, 1.2, 3), 2, 2),
        matrix(c(2.1, 0, 1.2, 3.2, 1.3, 3.4), 3, 2)),
    b = c(2.2, 3.1))
print(FormatTableAsLatex(dt))</pre>
```

is.GaussianPCM

Check if an object is a 'GaussianPCM'

Description

Check if an object is a 'GaussianPCM'

Usage

```
is.GaussianPCM(x)
```

Arguments

Χ

any object

is.PCM

Value

TRUE if x inherits from the S3 class 'GaussianPCM', FALSE otherwise.

is.MixedGaussian

Check if an object is a 'MixedGaussian' PCM

Description

Check if an object is a 'MixedGaussian' PCM

Usage

```
is.MixedGaussian(x)
```

Arguments

Х

any object

Value

TRUE if x inherits from the S3 class 'MixedGaussian', FALSE otherwise.

is.PCM

Check if an object is a PCM.

Description

Check if an object is a PCM.

Usage

```
is.PCM(x)
```

Arguments

Χ

an object.

Value

TRUE if 'x' inherits from the S3 class "PCM".

is.PCMTree 11

is.PCMTree

Check that a tree is a PCMTree

Description

Check that a tree is a PCMTree

Usage

```
is.PCMTree(tree)
```

Arguments

tree

a tree object.

Value

a logical TRUE if 'inherits(tree, "PCMTree")' is TRUE.

 ${\tt MatchListMembers}$

Find the members in a list matching a member expression

Description

Find the members in a list matching a member expression

Usage

```
MatchListMembers(object, member, enclos = "?", q = "'", ...)
```

Arguments

object a list containing named elements.

member a member expression. Member expressions are character strings denoting named

elements in a list object (see examples).

enclos a character string containing the special symbol '?'. This symbol is to be re-

placed by matching expressions. The result of this substitution can be anything

but, usually would be a valid R expression. Default: "?".

q a quote symbol, Default: "'".

... additional arguments passed to grep. For example, these could be ignore.case=TRUE

or perl=TRUE.

Value

a named character vector, with names corresponding to the matched member quoted expressions (using the argument q as a quote symbol), and values corresponding to the 'enclos-ed' expressions after substituting the '?'.

See Also

PCMListMembers

Examples

```
model <- PCMBaseTestObjects$model_MixedGaussian_ab
MatchListMembers(model, "Sigma_x", "diag(model?[,,1L])")
MatchListMembers(model, "S.*_x", "diag(model?[,,1L])")
MatchListMembers(model, "Sigma_x", "model?[,,1L][upper.tri(model?[,,1L])]")
MatchListMembers(model, "a$Sigma_x", "model?[,,1L][upper.tri(model?[,,1L])]")</pre>
```

MGPMScalarOUType

Class name for the scalar OU MGPM model type

Description

Class name for the scalar OU MGPM model type

Usage

MGPMScalarOUType()

Value

a character vector of one named element (ScalarOU)

MGPMSurfaceOUType

Class name for the SURFACE OU MGPM model type

Description

Class name for the SURFACE OU MGPM model type

Usage

```
MGPMSurfaceOUType()
```

Value

a character vector of one named element (SURFACE)

MixedGaussian 13

MixedGaussian

Create a multi-regime Gaussian model (MixedGaussian)

Description

Create a multi-regime Gaussian model (MixedGaussian)

Usage

```
MixedGaussian(
    k,
    modelTypes,
    mapping,
    className = paste0("MixedGaussian_", do.call(paste0, as.list(mapping))),
    X0 = structure(0, class = c("VectorParameter", "_Global"), description =
        "trait values at the root"),
    ...,
    Sigmae_x = structure(0, class = c("MatrixParameter", "_UpperTriangularWithDiagonal",
        "_WithNonNegativeDiagonal", "_Global"), description =
        "Upper triangular factor of the non-phylogenetic variance-covariance")
)
```

Arguments

k integer specifying the number of traits. modelTypes, mapping

These two arguments define the mapping between the regimes in the model and actual types of models. For convenience, different combinations are possible as explained below:

- modelTypes is a (possibly named) character string vector. Each such string denotes a mixed Gaussian regime model class, e.g. the result of calling MGPMDefaultModelTypes(). In that case mapping can be either an integer vector with values corresponding to indices in modelTypes or a character string vector. If mapping is a character string vector, first it is matched against names (modelTypes) and if the match fails either because of names (modelTypes) being NULL or because some of the entries in mapping are not present in names (modelTypes), then an attempt is made to match mapping against modelTypes, i.e. it is assumed that mapping contains actual class names.
- modelTypes is a (possibly named) list of PCM models of k traits. In this case mapping can again be an integer vector denoting indices in modelTypes or a character string vector denoting names in modelTypes.

As a final note, mapping can also be named. In this case the names are assumed to be the names of the different regimes in the model. If mapping is not named, the regimes are named automatically as as.character(seq_len(mapping)). For example, if modelTypes = c("BM", "OU") and mapping = c(a = 1, b = 1, c = 2, d = 1) defines an MixedGaussian with four different regimes named 'a',

'b', 'c', 'd', and model-types BM, BM, OU and BM, corresponding to each

regime.

className a character string defining a valid S3 class name for the resulting MixedGaus-

sian object. If not specified, a className is generated using the expression

paste0("MixedGaussian_", do.call(paste0, as.list(mapping))).

x0 specification for the global vector X0 to be used by all models in the MixedGaus-

sian.

... specifications for other _Global parameters coming after X0.

Sigmae_x sepcification of a _Global Sigmae_x parameter. This is used by Submodels only

if they have Sigmae_x _Omitted.

Details

If X0 is not NULL it has no sense to use model-types including X0 as a parameter (e.g. use BM1 or BM3 instead of BM or BM2). Similarly if Sigmae_x is not NULL there is no meaning in using model-types including Sigmae_x as a parameter, (e.g. use OU2 or OU3 instead of OU or OU1).

Value

an object of S3 class className inheriting from MixedGaussian, GaussianPCM and PCM.

See Also

PCMTreeGetPartNames
PCMModels()

 $\begin{tabular}{lll} {\bf Mixed Gaussian Template} & {\it Create \ a \ template \ Mixed Gaussian \ object \ containing \ a \ regime \ for \ each \ model \ type \end{tabular}$

Description

Create a template MixedGaussian object containing a regime for each model type

Usage

MixedGaussianTemplate(mg, modelTypes = NULL)

Arguments

mg a MixedGaussian object or an object that can be converted to such via as .MixedGaussian.

modelTypes a (possibly named) character string vector. Each such string denotes a mixed

Gaussian regime model class, e.g. the result of calling MGPMDefaultModelTypes(). If specified, an attempt is made to match PCMModelTypes(as.MixedGaussian(mg)) with the elements of modelTypes and an error is raised if the match fails. If not named, the model types and regimes in the resulting MixedGaussian object are named by the capital latin letters A,B,C,.... Default: NULL, which is interpreted as PCMModelTypes(as.MixedGaussian(mg, NULL)).

PCM 15

Value

a MixedGaussian with the same global parameter settings as for mg, the same modelTypes as modelTypes, and with a regime for each model type. The function will stop with an error if mg is not convertible to a MixedGaussian object or if there is a mismatch between the model types in mg and modelTypes.

Examples

```
mg <- MixedGaussianTemplate(PCMBaseTestObjects$model.ab.123.bSigmae_x)
mgTemplBMOU <- MixedGaussianTemplate(PCMBaseTestObjects$model.OU.BM)</pre>
```

PCM

Create a phylogenetic comparative model object

Description

This is the entry-point function for creating model objects within the PCMBase framework representing a single model-type with one or several model-regimes of this type associated with the branches of a tree. For mixed Gaussian phylogenetic models, which enable multiple model-types, use the MixedGaussian function.

Usage

```
PCM(
  model,
  modelTypes = class(model)[1],
  k = 1L,
  regimes = 1L,
  params = NULL,
  vecParams = NULL,
  offset = 0L,
  spec = NULL,
  ...
)
```

Arguments

mode1

This argument can take one of the following forms:

- a character vector of the S3-classes of the model object to be created (one model object can have one or more S3-classes, with the class PCM at the origin of the hierarchy);
- an S3 object which's class inherits from the PCM S3 class.

The Details section explains how these two types of input are processed.

modelTypes

a character string vector specifying a set (family) of model-classes, to which the constructed model object belongs. These are used for model-selection.

k

integer denoting the number of traits (defaults to 1).

16 PCM

regimes a character or integer vector denoting the regimes.

NULL (default) or a list of parameter values (scalars, vectors, matrices, or arrays) or sub-models (S3 objects inheriting from the PCM class). See details.

NULL (default) or a numeric vector the vector representation of the variable parameters in the model. See details.

offset integer offset in vecParams; see Details.

NULL or a list specifying the model parameters (see PCMSpecify). If NULL (default), the generic PCMSpecify is called on the created object of class model.

... additional parameters intended for use by sub-classes of the PCM class.

Details

This is an S3 generic. The PCMBase package defines three methods for it:

PCM.PCM: A default constructor for any object with a class inheriting from "PCM".

PCM.character: A default PCM constructor from a character string specifying the type of model.

PCM.default: A default constructor called when no other constructor is found. When called this constructor raises an error message.

Value

an object of S3 class as defined by the argument model.

See Also

MixedGaussian

Examples

```
# a Brownian motion model with one regime
modelBM <- PCM(model = "BM", k = 2)
# print the model
modelBM

# a BM model with two regimes
modelBM.ab <- PCM("BM", k = 2, regimes = c("a", "b"))
modelBM.ab

# print a single parameter of the model (in this case, the root value)
modelBM.ab$X0

# assign a value to this parameter (note that the brackets [] are necessary
# to preserve the parameter attributes):
modelBM.ab$X0[] <- c(5, 2)

PCMNumTraits(modelBM)
PCMNumRegimes(modelBM)
PCMNumRegimes(modelBM.ab)</pre>
```

PCMAbCdEf 17

```
# number of numerical parameters in the model
PCMParamCount(modelBM)
# Get a vector representation of all parameters in the model
PCMParamGetShortVector(modelBM)
# Limits for the model parameters:
lowerLimit <- PCMParamLowerLimit(modelBM)</pre>
upperLimit <- PCMParamUpperLimit(modelBM)</pre>
# assign the model parameters at random: this will use uniform distribution
# with boundaries specified by PCMParamLowerLimit and PCMParamUpperLimit
# We do this in two steps:
# 1. First we generate a random vector. Note the length of the vector equals PCMParamCount(modelBM)
randomParams <- PCMParamRandomVecParams(modelBM, PCMNumTraits(modelBM), PCMNumRegimes(modelBM))
# 2. Then we load this random vector into the model.
PCMParamLoadOrStore(modelBM, randomParams, 0, PCMNumTraits(modelBM), PCMNumRegimes(modelBM), TRUE)
print(modelBM)
PCMParamGetShortVector(modelBM)
# generate a random phylogenetic tree of 10 tips
tree <- ape::rtree(10)
#simulate the model on the tree
traitValues <- PCMSim(tree, modelBM, X0 = modelBM$X0)</pre>
# calculate the likelihood for the model parameters, given the tree and the trait values
PCMLik(traitValues, tree, modelBM)
# create a likelihood function for faster processing for this specific model.
# This function is convenient for calling in optim because it recieves and parameter
# vector instead of a model object.
likFun <- PCMCreateLikelihood(traitValues, tree, modelBM)</pre>
likFun(randomParams)
```

PCMAbCdEf

Quadratic polynomial parameters A, b, C, d, E, f for each node

Description

An S3 generic function that has to be implemented for every model class. This function is called by PCMLik.

Usage

```
PCMAbCdEf(
    tree,
```

18 PCMAddToListAttribute

```
model,
SE = matrix(0, PCMNumTraits(model), PCMTreeNumTips(tree)),
metaI = PCMInfo(NULL, tree, model, verbose = verbose),
verbose = FALSE
)
```

Arguments

tree a phylo object with N tips.

model an S3 object specifying both, the model type (class, e.g. "OU") as well as the

concrete model parameter values at which the likelihood is to be calculated (see

also Details).

SE a k x N matrix specifying the standard error for each measurement in X. Al-

ternatively, a k x k x N cube specifying an upper triangular k x k factor of the variance covariance matrix for the measurement error for each tip $i=1, \ldots, N$. When SE is a matrix, the k x k measurement error variance matrix for a tip i is calculated as VE[, , i] < diag(SE[, i] * SE[, i], nrow = k). When SE is a cube, the way how the measurement variance matrix for a tip i is calculated depends on the runtime option PCMBase.Transpose.Sigma_x as follows:

if getOption("PCMBase.Transpose.Sigma_x", FALSE) == FALSE (default): $VE[,,i] \leftarrow SE[,,i] \%*\% t(SE[,,i])$

if getOption("PCMBase.Transpose.Sigma_x", FALSE) == TRUE: VE[,,i] < t(SE[,,i]) %*% SE[,,i]

Note that the above behavior is consistent with the treatment of the model parameters Sigma_x, Sigmae_x and Sigmaj_x, which are also specified as upper

triangular factors. Default: matrix(0.0, PCMNumTraits(model), PCMTreeNumTips(tree)).

metaI a list returned from a call to PCMInfo(X, tree, model, SE), containing meta-

data such as N, M and k. Alternatively, this can be a character string naming a function or a function object that returns such a list, e.g. the functionPCMInfo or

the function PCMInfoCpp from the PCMBaseCpp package.

verbose logical indicating if some debug-messages should printed.

PCMAddToListAttribute Add a value to a list-valued attribute of a member or members matching a pattern

Description

Add a value to a list-valued attribute of a member or members matching a pattern

Usage

```
PCMAddToListAttribute(
  name,
  value,
```

```
object,
member = "",
enclos = "?",
spec = TRUE,
inplace = TRUE,
...
)
```

Arguments

a character string denoting the attribute name. name the value for the attribute. value object a PCM or a list object. a member expression. Member expressions are character strings denoting named member elements in a list object (see examples). Default: "". a character string containing the special symbol '?'. This symbol is to be reenclos placed by matching expressions. The result of this substitution can be anything but, usually would be a valid R expression. Default: "?". a logical (TRUE by default) indicating if the attribute should also be set in the spec corresponding member of the spec attribute (this is for PCM objects only). logical (TRUE by default) indicating if the attribute should be set to the object inplace in the current environment, or a modified object should be returned.

additional arguments passed to MatchListMembers.

Value

if inplace is TRUE no value is returned. Otherwise, a modified version of object is returned.

PCMApplyTransformation

Map a parametrization to its original form.

Description

This is an S3 generic that transforms the passed argument by applying the transformation rules for its S3 class.

This is an S3 generic. See 'PCMApplyTransformation._CholeskyFactor' for an example.

Usage

```
PCMApplyTransformation(o, ...)
```

Arguments

o a PCM object or a parameter

... additional arguments that can be used by implementing methods.

Details

This function returns the same object if it is not transformable.

Value

a transformed version of o.

See Also

is.Transformable

PCMBaseIsADevRelease Check if the PCMBase version corresponds to a dev release

Description

Check if the PCMBase version corresponds to a dev release

Usage

PCMBaseIsADevRelease()

Value

a logical

PCMBaseTestObjects

Test objects for the PCMBase package

Description

A list containing simulated trees, trait-values and model objects for tests and examples of the PCM-Base package

Usage

PCMBaseTestObjects

PCMBaseTestObjects

Format

This is a list containing the following named elements representing parameters of BM, OU and MixedGaussian models with up to three traits and up to two regimes, model objects, simulated trees with partition of their nodes in up to two parts (corresponding to the two regimes), and trait data simulated on these trees.

21

a.H, b.H H matrices for OU models for regimes 'a' and 'b'.

a.Theta, **b.Theta** Theta vectors for OU models for regimes 'a' and 'b'.

a.Sigma_x, b.Sigma_x Sigma_x matrices for BM and OU models for regimes 'a' and 'b'.

a.Sigmae_x, **b.Sigmae_x** Sigmae_x matrices regimes 'a' and 'b'.

a.X0, b.X0 X0 vectors for regimes 'a' and 'b'.

H an array resulting from abind(a.H, b.H).

Theta a matrix resulting from cbind(Theta.a, Theta.b).

Sigma_x an array resulting from abind(a.Sigma_x, b.Sigma_x).

Sigmae_x an array resulting from abind(a.Sigmae_x, b.Sigmae_x).

model.a.1, model.a.2, model.a.3 univariate models with a single regime for each of 3 traits.

model.a.1.Omitted_X0 same as model.a.1 but omitting X0; suitable for nesting in an MGPM
model.

model.a.123, model.b.123 single-regime 3-variate models.

model.a.123.Omitted_X0 single-regime 3-variate model with omitted X0 (suitable for nesting in an MGPM.

model.a.123.Omitted_X0__bSigmae_x same as model.a.123.Omitted_X0 but with the value of Sigmae_x copied from model.b.123.

model.a.123.Omitted_X0__Omitted_Sigmae_x same as model.a.123 but omitting X0 and Sigmae x.

model.b.123.Omitted_X0, model.b.123.Omitted_X0__Omitted_Sigmae_x analogical to corresponding model.a.123...

model.ab.123 a two-regime 3-variate model.

model.ab.123.bSigmae_x a two-regime 3-variate model having Sigmae_x from b.Sigmae_x.

model_MixedGaussian_ab a two-regime MGPM model with a local Sigmae_x for each regime.

model_MixedGaussian_ab_globalSigmae_x a two-regime MGPM model with a global Sigmae_x.

N number of tips in simulated trees

tree_15_tips a tree of 15 tips used for testing clade extraction.

tree.a a tree with one part only (one regime)

tree.ab a tree partitioned in two parts (two regimes)

traits.a.1 trait values simulated with model.a.1.

traits.a.123 trait values simulated with model.a.123.

traits.a.2 trait values simulated with model.a.2.

traits.a.3 trait values simulated with model.a.3.

traits.ab.123 trait values simulated with model.ab.123 on tree.ab.

tree a tree of 5 tips used for examples.

X 3-trait data for 5 tips used together with tree for examples.

model.OU.BM a mixed Gaussian phylogenetic model for 3 traits and an OU and BM regime used in examples.

PCMColorPalette

A fixed palette of n colors

Description

A fixed palette of n colors

Usage

```
PCMColorPalette(
   n,
   names,
   colors = structure(hcl(h = seq(15, 375, length = n + 1), l = 65, c =
      100)[seq_len(n)], names = names)
)
```

Arguments

n an integer defining the number of colors in the resulting palette.

names a character vector of length 'n'.

colors a vector of n values convertible to colors. Default: structure(hcl(h = seq(15,

375, length = n + 1), l = 65, c = 100)[seq_len(n)], names = names)

Value

A vector of character strings which can be used as color specifications by R graphics functions.

PCMCombineListAttribute

Combine all member attributes of a given name into a list

Description

Combine all member attributes of a given name into a list

Usage

```
PCMCombineListAttribute(object, name)
```

PCMCond 23

Arguments

object a named list object.

name a character string denoting the name of the attribute.

Value

a list of attribute values

PCMCond

Conditional distribution of a daughter node given its parent node

Description

An S3 generic function that has to be implemented for every model class.

Usage

```
PCMCond(
   tree,
   model,
   r = 1,
   metaI = PCMInfo(NULL, tree, model, verbose = verbose),
   verbose = FALSE
)
```

Arguments

tree a phylo object with N tips.

model an S3 object specifying both, the model type (class, e.g. "OU") as well as the

concrete model parameter values at which the likelihood is to be calculated (see

also Details).

r an integer specifying a model regime

metaI a list returned from a call to PCMInfo(X, tree, model, SE), containing meta-

data such as N, M and k. Alternatively, this can be a character string naming a function or a function object that returns such a list, e.g. the functionPCMInfo or

the function PCMInfoCpp from the PCMBaseCpp package.

verbose logical indicating if some debug-messages should printed.

Value

an object of type specific to the type of model

PCMCond.GaussianPCM

PCMCond.GaussianPCM

Conditional distribution of a daughter node given its parent node

Description

An S3 generic function that has to be implemented for every model class.

Usage

```
## S3 method for class 'GaussianPCM'
PCMCond(
  tree,
 model,
  r = 1,
 metaI = PCMInfo(NULL, tree, model, verbose = verbose),
  verbose = FALSE
)
```

Arguments

a phylo object with N tips. tree model

an S3 object specifying both, the model type (class, e.g. "OU") as well as the

concrete model parameter values at which the likelihood is to be calculated (see

also Details).

an integer specifying a model regime r

a list returned from a call to PCMInfo(X, tree, model, SE), containing metametaI

> data such as N, M and k. Alternatively, this can be a character string naming a function or a function object that returns such a list, e.g. the functionPCMInfo or

the function PCMInfoCpp from the PCMBaseCpp package.

verbose logical indicating if some debug-messages should printed.

Value

For GaussianPCM models, a named list with the following members:

```
omega
                 d
Phi
```

PCMCondVOU 25

PCMCondV0U	Variance-covariance matrix of an OU process with optional measure- ment error and jump at the start

Description

Variance-covariance matrix of an OU process with optional measurement error and jump at the start

Usage

```
PCMCondVOU(
   H,
   Sigma,
   Sigmae = NULL,
   Sigmaj = NULL,
   xi = NULL,
   e_Ht = NULL,
   threshold.Lambda_ij = getOption("PCMBase.Threshold.Lambda_ij", 1e-08)
)
```

a numerical k x k matrix - selection strength parameter.

Arguments H

a numerical k x k matrix - neutral drift unit-time variance-covariance matrix. Sigma a numerical k x k matrix - environmental variance-covariance matrix. Sigmae is the variance matrix of the normal jump distribution (default is NULL). Sigmaj хi a vector of 0's and 1's corresponding to each branch in the tree. A value of 1 indicates that a jump takes place at the beginning of the branch. This arugment is only used if Sigmaj is not NULL. Default is NULL. e_Ht a numerical k x k matrix - the result of the matrix exponential expm(-t*H). threshold.Lambda_ij a 0-threshold for abs(Lambda i + Lambda j), where Lambda i and Lambda j are eigenvalues of the parameter matrix H. This threshold-values is used as a condition to take the limit time of the expression '(1-exp(-Lambda_ij*time))/Lambda_ij' as '(Lambda_i+Lambda_j) -> 0'. You can control this value by the global option "PCMBase.Threshold.Lambda_ij". The default value (1e-8) is suitable for branch lengths bigger than 1e-6. For smaller branch lengths, you may want to increase the threshold value using, e.g. 'options(PCMBase.Threshold.Lambda_ij=1e-

Value

6)".

a function of one numerical argument (time) and an integer indicating the branch-index that is used to check the corresponding element in xi.

26 PCMCreateLikelihood

PCMCreateLikelihood

Create a likelihood function of a numerical vector parameter

Description

Create a likelihood function of a numerical vector parameter

Usage

```
PCMCreateLikelihood(
   X,
   tree,
   model,
   SE = matrix(0, PCMNumTraits(model), PCMTreeNumTips(tree)),
   metaI = PCMInfo(X, tree, model, SE),
   positiveValueGuard = Inf
)
```

Arguments

Χ

a k x N numerical matrix with possible NA and NaN entries. For $i=1,\ldots,N$, the column i of X contains the measured trait values for species i (the tip with integer identifier equal to i in tree). Missing values can be either not-available (NA) or not existing (NaN). These two values are treated differently when calculating likelihoods (see PCMPresentCoordinates).

tree

a phylo object with N tips.

model

an S3 object specifying both, the model type (class, e.g. "OU") as well as the concrete model parameter values at which the likelihood is to be calculated (see also Details).

SE

a k x N matrix specifying the standard error for each measurement in X. Alternatively, a k x k x N cube specifying an upper triangular k x k factor of the variance covariance matrix for the measurement error for each tip $i=1, \ldots, N$. When SE is a matrix, the k x k measurement error variance matrix for a tip i is calculated as VE[, , i] <- diag(SE[, i] * SE[, i], nrow = k). When SE is a cube, the way how the measurement variance matrix for a tip i is calculated depends on the runtime option PCMBase.Transpose.Sigma_x as follows:

```
\label{eq:continuous} \begin{split} &\textbf{if} \ \texttt{getOption("PCMBase.Transpose.Sigma\_x", FALSE)} == \texttt{FALSE} \ \textbf{(default):} \\ &VE[,\,,\,i] <- \mathtt{SE}[,\,,\,i] \ \%*\% \ \texttt{t}(\mathtt{SE}[,\,,\,i]) \\ &\textbf{if} \ \texttt{getOption("PCMBase.Transpose.Sigma\_x", FALSE)} == \texttt{TRUE:} \ VE[,\,,\,i] <- \texttt{t}(\mathtt{SE}[,\,,\,i]) \ \%*\% \ \mathtt{SE}[,\,,\,i] \end{split}
```

Note that the above behavior is consistent with the treatment of the model parameters Sigma_x, Sigmae_x and Sigmaj_x, which are also specified as upper triangular factors. Default: matrix(0.0, PCMNumTraits(model), PCMTreeNumTips(tree)).

metaI

a list returned from a call to PCMInfo(X, tree, model, SE), containing metadata such as N, M and k. Alternatively, this can be a character string naming a function or a function object that returns such a list, e.g. the functionPCMInfo or the function PCMInfoCpp from the PCMBaseCpp package.

positiveValueGuard

positive numerical value (default Inf), which serves as a guard for numerical error. Values exceeding this positiveGuard are most likely due to numerical error and PCMOptions()\$PCMBase.Value.NA is returned instead.

Details

It is possible to specify a function for the argument metal. This function should have three parameters (X, tree, model) and should return a metaInfo object. (see PCMInfo).

Value

a function of a numerical vector parameter called p returning the likelihood of X given the tree and the model with parameter values specified by p.

PCMDefaultModelTypes

Class names for the the default PCM and MGPM model types

Description

Utility functions returning named character vector of the model class-names for the default model types used for PCM and MixedGaussian model construction.

Usage

```
PCMDefaultModelTypes()
MGPMDefaultModelTypes()
```

Value

Both, PCMFDefaultModelTypes and MGPMDefaultModelTypes return a character string vector with named elements (A,B,C,D,E,F) defined as follows (Mitov et al. 2019a):

- **A.** BM (H = 0, diagonal Σ): BM, uncorrelated traits.
- **B.** BM (H = 0, symmetric Σ): BM, correlated traits.
- C. OU (diagonal H, diagonal Σ): OU, uncorrelated traits.
- **D.** OU (diagonal H, symmetric Σ): OU, correlated traits, but simple (diagonal) selection strength matrix.
- **E.** OU (symmetric H, symmetric Σ): An OU with nondiagonal symmetric H and nondiagonal symmetric Σ .
- **F.** OU (asymmetric H, symmetric Σ): An OU with nondiagonal asymmetric H and nondiagonal symmetric Σ .

28 PCMDefaultObject

The only difference between the two functions is that the model types returned by PCMFDefaultModelTypes have a global parameter X0, while the model types returned by MGPMFDefaultModelTypes have an omitted parameter X0.

References

[Mitov et al. 2019a] Mitov, V., Bartoszek, K., & Stadler, T. (2019). Automatic generation of evolutionary hypotheses using mixed Gaussian phylogenetic models. Proceedings of the National Academy of Sciences of the United States of America, 35, 201813823. http://doi.org/10.1073/pnas.1813823116

See Also

Args_MixedGaussian_MGPMDefaultModelTypes

PCMDefaultObject	Generate a default object of a given PCM model type or parameter type
------------------	---

Description

This is an S3 generic. See, e.g. 'PCMDefaultObject.MatrixParameter'.

Usage

```
PCMDefaultObject(spec, model, ...)
```

Arguments

spec any object having a class attribute. The value of this object is not used, but its

class is used for method-dispatch.

model a PCM object used to extract attributes needed for creating a default object of

class specified in class(spec), such as the number of traits (k) or the regimes

and the number of regimes;

... additional arguments that can be used by methods.

Value

a parameter or a PCM object.

PCMDescribe 29

PCMDescribe

Human friendly description of a PCM

Description

Human friendly description of a PCM

Usage

```
PCMDescribe(model, ...)
```

Arguments

```
model a PCM model object
```

. . . additional arguments used by implementing methods.

Details

This S3 generic function is intended to be specified for user models

Value

a character string

PCMDescribeParameters Describe the parameters of a PCM

Description

This is an S3 generic.

Usage

```
PCMDescribeParameters(model, ...)
```

Arguments

```
model a PCM object.
```

... additional arguments that can be used by implementing methods.

Value

a named list with character elements corresponding to each parameter.

30 PCMExtractRegimes

PCMExtractDimensions Given a PCM or a parameter object, extract an analogical object for a subset of the dimensions (traits) in the original object.

Description

Given a PCM or a parameter object, extract an analogical object for a subset of the dimensions (traits) in the original object.

Usage

```
PCMExtractDimensions(obj, dims = seq_len(PCMNumTraits(obj)), nRepBlocks = 1L)
```

Arguments

obj a PCM or a parameter object.

dims an integer vector; should be a subset or equal to seq_len(PCMNumTraits(obj))

(the default).

nRepBlocks a positive integer specifying if the specified dimensions should be replicated to

obtain a higher dimensional model, where the parameter matrices are block-

diagonal with blocks corresponding to dims. Default: 1L.

Details

This is an S3 generic

Value

an object of the same class as obj with a subset of obj's dimensions multiplied nRepBlocks times.

PCMExtractRegimes Given a PCM or a parameter object, extract an analogical object for a subset of the regimes in the original object.

Description

Given a PCM or a parameter object, extract an analogical object for a subset of the regimes in the original object.

Usage

```
PCMExtractRegimes(obj, regimes = seq_len(PCMNumRegimes(obj)))
```

PCMFindMethod 31

Arguments

obj a PCM or a parameter object.

regimes an integer vector; should be a subset or equal to seq_len(PCMNumRegimes(obj))

(the default).

Details

This is an S3 generic

Value

an object of the same class as obj with a subset of obj's regimes

PCMFindMethod Find the S3 method for a given PCM object or class-name and an S3

generic

Description

Find the S3 method for a given PCM object or class-name and an S3 generic

Usage

```
PCMFindMethod(x, method = "PCMCond")
```

Arguments

x a character string denoting a PCM S3 class name (e.g. "OU"), or a PCM object.

method a character string denoting the name of an S3 generic function. Default: "PCM-

Cond".

Value

a function object corresponding to the S3 method found or an error is raised if no such function is found for the specified object and method.

PCMFixParameter

Fix a parameter in a PCM model

Description

Fix a parameter in a PCM model

Usage

```
PCMFixParameter(model, name)
```

Arguments

```
model a PCM object name a character string
```

Value

a copy of the model with added class '_Fixed' to the class of the parameter name

PCMGenerateModelTypes Generate default model types for given PCM base-classes

Description

This function calls 'PCMListParameterizations' or 'PCMListDefaultParameterizations' and generates the corresponding 'PCMParentClasses' and 'PCMSpecify' methods in the global environment.

Usage

```
PCMGenerateModelTypes(
  baseTypes = list(BM = "default", OU = "default", White = "all"),
  sourceFile = NULL
)
```

Arguments

baseTypes

a named list with character string elements among c("default", "all") and names specifying base S3-class names for which the parametrizations (subclasses) will be generated. Defaults to list(BM="default", OU = "default", White = "all"). The element value specifies which one of 'PCMListParameterizations' or 'PCMListDefaultParameterizations' should be used:

"all" for calling 'PCMListParameterizations'

"default" for calling 'PCMListDefaultParameterizations'

sourceFile

NULL or a character string indicating a .R filename, to which the automatically generated code will be saved. If NULL (the default), the generated source code is evaluated and the S3 methods are defined in the global environment. Default: NULL.

Value

This function has side effects only and does not return a value.

See Also

PCMListDefaultParameterizations

PCMGenerateParameterizations

Generate possible parameterizations for a given type of model

Description

A parameterization of a PCM of given type, e.g. OU, is a PCM-class inheriting from this type, which imposes some restrictions or transformations of the parameters in the base-type. This function generates the S3 methods responsible for creating such parameterizations, in particular it generates the definition of the methods for the two S3 generics 'PCMParentClasses' and 'PCMSpecify' for al parameterizations specified in the 'tableParameterizations' argument.

Usage

```
PCMGenerateParameterizations(
  model,
  listParameterizations = PCMListParameterizations(model),
  tableParameterizations = PCMTableParameterizations(model, listParameterizations),
  env = .GlobalEnv,
  useModelClassNameForFirstRow = FALSE,
  sourceFile = NULL
)
```

Arguments

```
model a PCM object.
```

listParameterizations
a list or a sublist returned by 'PCMListParameterizations'. I

a list or a sublist returned by 'PCMListParameterizations'. Default: 'PCMListParameterizations(model)'.

tableParameterizations

a data.table containing the parameterizations to generate. By default this is generated from 'listParameterizations' using a call 'PCMTableParameterizations(model, listParameterizations)'. If specified by the user, this parameter takes precedence over 'listParameterizations' and 'listParameterizations' is not used.

34 PCMGetAttribute

env an environment where the method definitions will be stored. Default: 'env = .GlobalEnv'.

useModelClassNameForFirstRow

A logical specifying if the S3 class name of 'model' should be used as a S3 class for the model defined in the first row of 'tableParameterizations'. Default:

FALSE.

sourceFile NULL or a character string indicating a .R filename, to which the automatically

generated code will be saved. If NULL (the default), the generated source code is evaluated and the S3 methods are defined in the global environment. Default:

NULL.

Value

This function does not return a value. It only has a side effect by defining S3 methods in 'env'.

PCMGetAttribute Value of an attribute of an object or values for an attribute found in its members

Description

Value of an attribute of an object or values for an attribute found in its members

Usage

```
PCMGetAttribute(name, object, member = "", ...)
```

Arguments

name attribute name.

object a PCM model object or a PCMTree object.

member a member expression. Member expressions are character strings denoting named

elements in a list object (see examples). Default: "".

... additional arguments passed to MatchListMembers.

Value

if member is an empty string, attr(object, name). Otherwise, a named list containing the value for the attribute for each member in object matched by member.

Examples

```
PCMGetAttribute("class", PCMBaseTestObjects$model_MixedGaussian_ab)
PCMGetAttribute(
  "dim", PCMBaseTestObjects$model_MixedGaussian_ab,
  member = "$Sigmae_x")
```

PCMGetVecParamsRegimesAndModels

Get a vector of all parameters (real and discrete) describing a model on a tree including the numerical parameters of each model regime, the integer ids of the splitting nodes defining the regimes on the tree and the integer ids of the model types associated with each regime.

Description

Get a vector of all parameters (real and discrete) describing a model on a tree including the numerical parameters of each model regime, the integer ids of the splitting nodes defining the regimes on the tree and the integer ids of the model types associated with each regime.

Usage

```
PCMGetVecParamsRegimesAndModels(model, tree, ...)
```

Arguments

```
model a PCM model tree a phylo object with an edge.part member.
```

additional parameters passed to methods.

Details

This is an S3 generic. In the default implementation, the last entry in the returned vector is the number of numerical parameters. This is used to identify the starting positions in the vector of the first splitting node.

Value

a numeric vector concatenating the result

PCMInfo

Meta-information about a tree and trait data associated with a PCM

Description

This function pre-processes the given tree and data in order to create meta-information used during likelihood calculation.

36 PCMInfo

Usage

```
PCMInfo(
   X,
   tree,
   model,
   SE = matrix(0, PCMNumTraits(model), PCMTreeNumTips(tree)),
   verbose = FALSE,
   preorder = NULL,
   ...
)
```

Arguments

Χ

a k x N numerical matrix with possible NA and NaN entries. For $i=1, \ldots, N$, the column i of X contains the measured trait values for species i (the tip with integer identifier equal to i in tree). Missing values can be either not-available (NA) or not existing (NaN). These two values are treated differently when calculating likelihoods (see PCMPresentCoordinates).

tree

a phylo object with N tips.

mode1

an S3 object specifying both, the model type (class, e.g. "OU") as well as the concrete model parameter values at which the likelihood is to be calculated (see also Details).

SE

a k x N matrix specifying the standard error for each measurement in X. Alternatively, a k x k x N cube specifying an upper triangular k x k factor of the variance covariance matrix for the measurement error for each tip $i=1, \ldots, N$. When SE is a matrix, the k x k measurement error variance matrix for a tip i is calculated as VE[, , i] <- diag(SE[, i] * SE[, i], nrow = k). When SE is a cube, the way how the measurement variance matrix for a tip i is calculated depends on the runtime option PCMBase.Transpose.Sigma_x as follows:

```
\label{eq:continuous} \begin{split} &\textbf{if} \ \texttt{getOption("PCMBase.Transpose.Sigma\_x", FALSE)} == \texttt{FALSE} \ \textbf{(default):} \\ &VE[,\,,i] <- \ \text{SE}[,\,,i] \ \%*\% \ \textbf{t}(SE[,\,,i]) \\ &\textbf{if} \ \texttt{getOption("PCMBase.Transpose.Sigma\_x", FALSE)} == \texttt{TRUE:} \ VE[,\,,i] <- \ \textbf{t}(SE[,\,,i]) \ \%*\% \ SE[,\,,i] \end{split}
```

Note that the above behavior is consistent with the treatment of the model parameters Sigma_x, Sigmae_x and Sigmaj_x, which are also specified as upper triangular factors. Default: matrix(0.0, PCMNumTraits(model), PCMTreeNumTips(tree)).

verbose

logical indicating if some debug-messages should printed.

preorder

an integer vector of row-indices in tree\$edge matrix as returned by PCMTreeP-reorder. This can be given for performance speed-up when several operations needing preorder are executed on the tree. Default: NULL.

...

additional arguments used by implementing methods.

Value

a named list with the following elements:

PCMLik 37

Χ	k x N matrix denoting the trait data;
VE	$k \times k \times N$ array denoting the measurement error variance covariance matrix for each for each tip $i = 1,,N$. See the parameter SE in PCMLik.
М	total number of nodes in the tree;
N	number of tips;
k	number of traits;
RTree	number of parts on the tree (distinct elements of tree\$edge.part);
RModel	number of regimes in the model (elements of attr(model, regimes));
р	number of free parameters describing the model;
r	an integer vector corresponding to tree\$edge with the regime for each branch in tree;
хi	an integer vector of 0's and 1's corresponding to the rows in tree\$edge indicating the presence of a jump at the corresponding branch;
pc	a logical matrix of dimension k x M denoting the present coordinates for each node; in special cases this matrix can be edited by hand after calling PCMInfo and before passing the returned list to PCMLik. Otherwise, this matrix can be calculated in a custom way by specifying the option PCMBase.PCMPresentCoordinatesFun. See also PCMPresentCoordinates and PCMOptions.

This list is passed to PCMLik.

DOM: 11.	
PCMLik	Likelihood of a multivariate Gaussian phylogenetic comparative
	model with non-interacting lineages

Description

The likelihood of a PCM represents the probability density function of observed trait values (data) at the tips of a tree given the tree and the model parameters. Seen as a function of the model parameters, the likelihood is used to fit the model to the observed trait data and the phylogenetic tree (which is typically inferred from another sort of data, such as an alignment of genetic sequences for the species at the tips of the tree). The PCMLik function provides a common interface for calculating the (log-)likelihood of different PCMs. Below we denote by N the number of tips, by M the total number of nodes in the tree including tips, internal and root node, and by k - the number of traits.

```
PCMLik(
   X,
   tree,
   model,
   SE = matrix(0, PCMNumTraits(model), PCMTreeNumTips(tree)),
   metaI = PCMInfo(X = X, tree = tree, model = model, SE = SE, verbose = verbose),
   log = TRUE,
   verbose = FALSE
)
```

38 PCMLik

Arguments

Χ

a k x N numerical matrix with possible NA and NaN entries. For $i=1, \ldots, N$, the column i of X contains the measured trait values for species i (the tip with integer identifier equal to i in tree). Missing values can be either not-available (NA) or not existing (NaN). These two values are treated differently when calculating likelihoods (see PCMPresentCoordinates).

tree

a phylo object with N tips.

model

an S3 object specifying both, the model type (class, e.g. "OU") as well as the concrete model parameter values at which the likelihood is to be calculated (see also Details).

SE

a k x N matrix specifying the standard error for each measurement in X. Alternatively, a k x k x N cube specifying an upper triangular k x k factor of the variance covariance matrix for the measurement error for each tip $i=1, \ldots, N$. When SE is a matrix, the k x k measurement error variance matrix for a tip i is calculated as VE[, , i] <- diag(SE[, i] * SE[, i], nrow = k). When SE is a cube, the way how the measurement variance matrix for a tip i is calculated depends on the runtime option PCMBase.Transpose.Sigma_x as follows:

if getOption("PCMBase.Transpose.Sigma_x", FALSE) == FALSE (default): $VE[,\,,i] \leftarrow SE[,\,,i]~\%*\%~t(SE[,\,,i])$

if getOption("PCMBase.Transpose.Sigma_x", FALSE) == TRUE: VE[,,i] < t(SE[,,i]) %*% SE[,,i]

Note that the above behavior is consistent with the treatment of the model parameters Sigma_x, Sigmae_x and Sigmaj_x, which are also specified as upper triangular factors. Default: matrix(0.0, PCMNumTraits(model), PCMTreeNumTips(tree)).

metaI

a list returned from a call to PCMInfo(X, tree, model, SE), containing metadata such as N, M and k. Alternatively, this can be a character string naming a function or a function object that returns such a list, e.g. the functionPCMInfo or the function PCMInfoCpp from the PCMBaseCpp package.

log

logical indicating whether a log-likelehood should be calculated. Default is

TRUE.

verbose

logical indicating if some debug-messages should printed.

Details

For efficiency, the argument metaI can be provided explicitly, because this is not supposed to change during a model inference procedure such as likelihood maximization.

Value

a numerical value with named attributes as follows:

X0 A numerical vector of length k specifying the value at the root for which the likelihood value was calculated. If the model contains a member called X0, this vector is used; otherwise the value of X0 maximizing the likelihood for the given model parameters is calculated by maximizing the quadratic polynomial 'X0 * L_root * X0 + m_root * X0 + r_root';

PCMLikDmvNorm 39

error A character string with information if a numerical or other logical error occurred during likelihood calculation.

If an error occured during likelihood calculation, the default behavior is to return NA with a non-NULL error attribute. This behavior can be changed in using global options:

"PCMBase.Value.NA" Allows to specify a different NA value such as -Inf or -1e20 which can be used in combination with log = TRUE when using optim to maximize the log-likelihood;

"PCMBase.Errors.As.Warnings" Setting this option to FALSE will cause any error to result in calling the stop R-base function. If not caught in a tryCatch, this will cause the inference procedure to abort at the occurence of a numerical error. By default, this option is set to TRUE, which means that getOption("PCMBase.Value.NA", as.double(NA)) is returned with an error attribute and a warning is issued.

See Also

PCMInfo PCMAbCdEf PCMLmr PCMSim PCMCond

Examples

```
N <- 10
tr <- PCMTree(ape::rtree(N))
model <- PCMBaseTestObjects$model_MixedGaussian_ab

PCMTreeSetPartRegimes(tr, c(`11` = 'a'), setPartition = TRUE)
set.seed(1, kind = "Mersenne-Twister", normal.kind = "Inversion")
X <- PCMSim(tr, model, X0 = rep(0, 3))

PCMLik(X, tr, model)</pre>
```

PCMLikDmvNorm

Calculate the likelihood of a model using the standard formula for multivariate pdf

Description

Calculate the likelihood of a model using the standard formula for multivariate pdf

```
PCMLikDmvNorm(
   X,
   tree,
   model,
   SE = matrix(0, PCMNumTraits(model), PCMTreeNumTips(tree)),
   metaI = PCMInfo(X, tree, model, SE, verbose = verbose),
   log = TRUE,
   verbose = FALSE
)
```

40 PCMLikTrace

Arguments

Χ

a k x N numerical matrix with possible NA and NaN entries. For $i=1,\ldots,N$, the column i of X contains the measured trait values for species i (the tip with integer identifier equal to i in tree). Missing values can be either not-available (NA) or not existing (NaN). These two values are treated differently when calculating likelihoods (see PCMPresentCoordinates).

tree

a phylo object with N tips.

mode1

an S3 object specifying both, the model type (class, e.g. "OU") as well as the concrete model parameter values at which the likelihood is to be calculated (see also Details).

SE

a k x N matrix specifying the standard error for each measurement in X. Alternatively, a k x k x N cube specifying an upper triangular k x k factor of the variance covariance matrix for the measurement error for each tip $i=1, \ldots, N$. When SE is a matrix, the k x k measurement error variance matrix for a tip i is calculated as VE[, , i] <- diag(SE[, i] * SE[, i], nrow = k). When SE is a cube, the way how the measurement variance matrix for a tip i is calculated depends on the runtime option PCMBase.Transpose.Sigma_x as follows:

if getOption("PCMBase.Transpose.Sigma_x", FALSE) == FALSE (default): $VE[.,i] \leftarrow SE[.,i] \%*\% t(SE[.,i])$

if getOption("PCMBase.Transpose.Sigma_x", FALSE) == TRUE: VE[,,i] < t(SE[,,i]) %*% SE[,,i]

Note that the above behavior is consistent with the treatment of the model parameters Sigma_x, Sigmae_x and Sigmaj_x, which are also specified as upper triangular factors. Default: matrix(0.0, PCMNumTraits(model), PCMTreeNumTips(tree)).

metaI

a list returned from a call to PCMInfo(X, tree, model, SE), containing metadata such as N, M and k. Alternatively, this can be a character string naming a function or a function object that returns such a list, e.g. the functionPCMInfo or the function PCMInfoCpp from the PCMBaseCpp package.

log

logical indicating whether a log-likelehood should be calculated. Default is

TRUE.

verbose

logical indicating if some debug-messages should printed.

Value

a numerical value with named attributes as follows:

DOM	٠		
PCML	.1	ΚI	race

Tracing the log-likelihood calculation of a model over each node of the tree

Description

This is an S3 generic function providing tracing information for the likelihood calculation for a given tree, data and model parameters. Useful for illustration or for debugging purpose.

PCMLikTrace 41

Usage

```
PCMLikTrace(
   X,
   tree,
   model,
   SE = matrix(0, PCMNumTraits(model), PCMTreeNumTips(tree)),
   metaI = PCMInfo(X = X, tree = tree, model = model, SE = SE, verbose = verbose),
   log = TRUE,
   verbose = FALSE
)
```

Arguments

Χ

a k x N numerical matrix with possible NA and NaN entries. For $i=1,\ldots,N$, the column i of X contains the measured trait values for species i (the tip with integer identifier equal to i in tree). Missing values can be either not-available (NA) or not existing (NaN). These two values are treated differently when calculating likelihoods (see PCMPresentCoordinates).

tree

a phylo object with N tips.

mode1

an S3 object specifying both, the model type (class, e.g. "OU") as well as the concrete model parameter values at which the likelihood is to be calculated (see also Details).

SE

a k x N matrix specifying the standard error for each measurement in X. Alternatively, a k x k x N cube specifying an upper triangular k x k factor of the variance covariance matrix for the measurement error for each tip $i=1, \ldots, N$. When SE is a matrix, the k x k measurement error variance matrix for a tip i is calculated as VE[, , i] <- diag(SE[, i] * SE[, i], nrow = k). When SE is a cube, the way how the measurement variance matrix for a tip i is calculated depends on the runtime option PCMBase.Transpose.Sigma_x as follows:

```
\label{eq:continuous} \begin{split} &\textbf{if} \ \texttt{getOption("PCMBase.Transpose.Sigma\_x", FALSE)} == \texttt{FALSE} \ \textbf{(default):} \\ &VE[,\,,\,i] <- \mathtt{SE}[,\,,\,i] \ \%*\% \ \texttt{t}(\mathtt{SE}[,\,,\,i]) \end{split} \\ &\textbf{if} \ \texttt{getOption("PCMBase.Transpose.Sigma\_x", FALSE)} == \mathtt{TRUE:} \ VE[,\,,\,i] <- \texttt{t}(\mathtt{SE}[,\,,\,i]) \ \%*\% \ \mathtt{SE}[,\,,\,i] \end{split}
```

Note that the above behavior is consistent with the treatment of the model parameters Sigma_x, Sigmae_x and Sigmaj_x, which are also specified as upper triangular factors. Default: matrix(0.0, PCMNumTraits(model), PCMTreeNumTips(tree)).

metaI

a list returned from a call to PCMInfo(X, tree, model, SE), containing metadata such as N, M and k. Alternatively, this can be a character string naming a function or a function object that returns such a list, e.g. the functionPCMInfo or the function PCMInfoCpp from the PCMBaseCpp package.

log

logical indicating whether a log-likelehood should be calculated. Default is TRUE.

verbose

logical indicating if some debug-messages should printed.

42 PCMListMembers

Value

The returned object will, in general, depend on the type of model and the algorithm used for likelihood calculation. For a G_LInv model and pruning-wise likelihood calculation, the returned object will be a data.table with columns corresponding to the node-state variables, e.g. the quadratic polynomial coefficients associated with each node in the tree.

See Also

PCMInfo PCMAbCdEf PCMLmr PCMSim PCMCond PCMParseErrorMessage

PCMListMembers

A vector of access-code strings to all members of a named list

Description

A vector of access-code strings to all members of a named list

Usage

```
PCMListMembers(
    l,
    recursive = TRUE,
    format = c("$", "$'", "$\"", "$\"", "[['", "[[\"", "[[\"")])
```

Arguments

a named list object.

recursive logical indicating if list members should be gone through recursively. TRUE by

default.

format a character string indicating the format for accessing a member. Acceptable val-

ues are c("\$", "\$'", '\$"', "[['", '[["', '[["'] of which the first

one is taken as default.

Value

a vector of character strings denoting each named member of the list.

Examples

```
PCMListMembers(PCMBaseTestObjects$model_MixedGaussian_ab)
PCMListMembers(PCMBaseTestObjects$model_MixedGaussian_ab, format = '$\'')
PCMListMembers(PCMBaseTestObjects$tree.ab, format = '$\'')
```

PCMListParameterizations

PCMListParameterizations

Specify the parameterizations for each parameter of a model

43

Description

These are S3 generics. 'PCMListParameterizations' should return all possible parametrizations for the class of 'model'. 'PCMListDefaultParameterizations' is a handy way to specify a subset of all parametrizations. 'PCMListDefaultParameterizations' should be used to avoid generating too many model parametrizations which occupy space in the R-global environment while they are not used (see PCMGenerateParameterizations). It is mandatory to implement a specification for 'PCMListParameterizations' for each newly defined class of models. 'PCMListDefaultParameterizations' has a default implementation that calls 'PCMListParameterizations' and returns the first parametrization for each parameter. Hence, implementing a method for 'PCMListDefaultParameterizations' for a newly defined model type is optional.

Usage

```
PCMListParameterizations(model, ...)
PCMListDefaultParameterizations(model, ...)
```

Arguments

model a PCM.

. . . additional arguments used by implementing methods.

Value

a named list with list elements corresponding to each parameter in model. Each list element is a list of character vectors, specifying the possible S3 class attributes for the parameter in question. For an example, type 'PCMListParameterizations.BM' to see the possible parameterizations for the BM model.

See Also

PCMGenerateParameterizations

44 PCMLmr

PCMLmr

Quadratic polynomial parameters L, m, r

Description

Quadratic polynomial parameters L, m, r

Usage

```
PCMLmr(
    X,
    tree,
    model,
    SE = matrix(0, PCMNumTraits(model), PCMTreeNumTips(tree)),
    metaI = PCMInfo(X = X, tree = tree, model = model, SE = SE, verbose = verbose),
    root.only = TRUE,
    verbose = FALSE
)
```

Arguments

Χ

a k x N numerical matrix with possible NA and NaN entries. For $i=1,\ldots,N$, the column i of X contains the measured trait values for species i (the tip with integer identifier equal to i in tree). Missing values can be either not-available (NA) or not existing (NaN). These two values are treated differently when calculating likelihoods (see PCMPresentCoordinates).

tree

a phylo object with N tips.

model

an S3 object specifying both, the model type (class, e.g. "OU") as well as the concrete model parameter values at which the likelihood is to be calculated (see also Details).

SE

a k x N matrix specifying the standard error for each measurement in X. Alternatively, a k x k x N cube specifying an upper triangular k x k factor of the variance covariance matrix for the measurement error for each tip $i=1, \ldots, N$. When SE is a matrix, the k x k measurement error variance matrix for a tip i is calculated as VE[, , i] <- diag(SE[, i] * SE[, i], nrow = k). When SE is a cube, the way how the measurement variance matrix for a tip i is calculated depends on the runtime option PCMBase.Transpose.Sigma_x as follows:

```
\label{eq:continuous} \begin{split} &\textbf{if} \ \mathsf{getOption}(\text{"PCMBase.Transpose.Sigma}_x", \ \mathsf{FALSE}) == \mathsf{FALSE} \ (\textbf{default}) \text{:} \\ &VE[,\,,i] <- \mathrm{SE}[,\,,i] \ \%*\% \ \mathsf{t}(\mathrm{SE}[,\,,i]) \end{split} &\textbf{if} \ \mathsf{getOption}(\text{"PCMBase.Transpose.Sigma}_x", \ \mathsf{FALSE}) == \mathsf{TRUE:} \ VE[,\,,i] <- \mathsf{t}(\mathrm{SE}[,\,,i]) \ \%*\% \ \mathrm{SE}[,\,,i] \end{split}
```

Note that the above behavior is consistent with the treatment of the model parameters Sigma_x, Sigmae_x and Sigmaj_x, which are also specified as upper triangular factors. Default: matrix(0.0, PCMNumTraits(model), PCMTreeNumTips(tree)).

metaI a list returned from a call to PCMInfo(X, tree, model, SE), containing meta-

data such as N, M and k. Alternatively, this can be a character string naming a function or a function object that returns such a list, e.g. the functionPCMInfo or

the function PCMInfoCpp from the PCMBaseCpp package.

root.only logical indicating whether to return the calculated values of L,m,r only for the

root or for all nodes in the tree.

verbose logical indicating if some debug-messages should printed.

Value

A list with the members A,b,C,d,E,f,L,m,r for all nodes in the tree or only for the root if root.only=TRUE.

PCMMapModelTypesToRegimes

Integer vector giving the model type index for each regime

Description

Integer vector giving the model type index for each regime

Usage

```
PCMMapModelTypesToRegimes(model, tree, ...)
```

Arguments

model a PCM model

tree a phylo object with an edge.part member ... additional parameters passed to methods

Details

This is a generic S3 method. The default implementation for the basic class PCM returns a vector of 1's, because it assumes that a single model type is associated with each regime. The implementation for mixed Gaussian models returns the mapping attribute of the MixedGaussian object reordered to correspond to PCMTreeGetPartNames(tree).

Value

an integer vector with elements corresponding to the elements in PCMTreeGetPartNames(tree)

46 PCMMean

PCMMean	Expected mean vector at each tip conditioned on a trait-value vector at the root

Description

Expected mean vector at each tip conditioned on a trait-value vector at the root

Usage

```
PCMMean(
   tree,
   model,
   X0 = model$X0,
   metaI = PCMInfo(NULL, tree, model, verbose = verbose),
   internal = FALSE,
   verbose = FALSE
)
```

Arguments

tree	a phylo object with N tips.
------	-----------------------------

model an S3 object specifying both, the model type (class, e.g. "OU") as well as the

concrete model parameter values at which the likelihood is to be calculated (see

also Details).

X0 a k-vector denoting the root trait

metaI a list returned from a call to PCMInfo(X, tree, model, SE), containing meta-

data such as N, M and k. Alternatively, this can be a character string naming a function or a function object that returns such a list, e.g. the functionPCMInfo or

the function PCMInfoCpp from the PCMBaseCpp package.

internal a logical indicating ig the per-node mean vectors should be returned (see Value).

Default FALSE.

verbose logical indicating if some debug-messages should printed.

Value

If internal is FALSE (default), then a $k \times N$ matrix Mu, such that Mu[, i] equals the expected mean k-vector at tip i, conditioned on X0 and the tree. Otherwise, a $k \times M$ matrix Mu containing the mean vector for each node.

Examples

```
# a Brownian motion model with one regime
modelBM <- PCM(model = "BM", k = 2)
# print the model
modelBM</pre>
```

PCMMeanAtTime 47

```
# assign the model parameters at random: this will use uniform distribution
# with boundaries specified by PCMParamLowerLimit and PCMParamUpperLimit
# We do this in two steps:
# 1. First we generate a random vector. Note the length of the vector equals PCMParamCount(modelBM)
randomParams <- PCMParamRandomVecParams(modelBM, PCMNumTraits(modelBM), PCMNumRegimes(modelBM))
randomParams
# 2. Then we load this random vector into the model.
PCMParamLoadOrStore(modelBM, randomParams, 0, PCMNumTraits(modelBM), PCMNumRegimes(modelBM), TRUE)
# create a random tree of 10 tips
tree <- ape::rtree(10)
PCMMean(tree, modelBM)</pre>
```

PCMMeanAtTime

Calculate the mean at time t, given X0, under a PCM model

Description

Calculate the mean at time t, given X0, under a PCM model

Usage

```
PCMMeanAtTime(
   t,
   model,
   X0 = model$X0,
   regime = PCMRegimes(model)[1L],
   verbose = FALSE
)
```

Arguments

t positive numeric denoting time

model a PCM model object

X0 a numeric vector of length k, where k is the number of traits in the model (De-

faults to model\$X0).

regime an integer or a character denoting the regime in model for which to do the cal-

culation; Defaults to PCMRegimes(model)[1L], meaning the first regime in the

model.

verbose a logical indicating if (debug) messages should be written on the console (De-

faults to FALSE).

Value

A numeric vector of length k

48 PCMModels

Examples

```
# a Brownian motion model with one regime
modelBM <- PCM(model = "BM", k = 2)
# print the model
modelBM
# assign the model parameters at random: this will use uniform distribution
# with boundaries specified by PCMParamLowerLimit and PCMParamUpperLimit
# We do this in two steps:
# 1. First we generate a random vector. Note the length of the vector equals PCMParamCount(modelBM)
randomParams <- PCMParamRandomVecParams(modelBM, PCMNumTraits(modelBM), PCMNumRegimes(modelBM))
randomParams
# 2. Then we load this random vector into the model.
PCMParamLoadOrStore(modelBM, randomParams, 0, PCMNumTraits(modelBM), PCMNumRegimes(modelBM), TRUE)
# PCMMeanAtTime(1, modelBM)
# note that the variance at time 0 is not the 0 matrix because the model has a non-zero
# environmental deviation
PCMMeanAtTime(0, modelBM)</pre>
```

PCMModels

Get a list of PCM models currently implemented

Description

Get a list of PCM models currently implemented

Usage

```
PCMModels(pattern = NULL, parentClass = NULL, ...)
```

Arguments

pattern a character string specifying an optional for the model-names to search for.

parentClass a character string specifying an optional parent class of the models to look for.

additional arguments used by implementing methods.

Details

The function is using the S3 api function methods looking for all registered implementations of the function PCMSpecify.

Value

a character vector of the model classes found.

Examples

```
PCMModels()
PCMModels("^OU")
```

PCMModelTypes 49

PCMModelTypes

Get the model type(s) of a model

Description

For a regular PCM object, the model type is its S3 class. For a MixedGaussian each regime is mapped to one of several possible model types.

Usage

```
PCMModelTypes(obj)
```

Arguments

obj

a PCM object

Value

a character vector

 ${\tt PCMNumRegimes}$

Number of regimes in a obj

Description

Number of regimes in a obj

Usage

```
PCMNumRegimes(obj)
```

Arguments

obj

a PCM object

Value

an integer

50 PCMOptions

PCMNumTraits

Number of traits modeled by a PCM

Description

Number of traits modeled by a PCM

Usage

PCMNumTraits(model)

Arguments

model

a PCM object or an a parameter object (the name of this argument could be misleading, because both, model and parameter objects are supported).

Value

an integer

PCMOptions

Global options for the PCMBase package

Description

Global options for the PCMBase package

Usage

PCMOptions()

Value

a named list with the currently set values of the following global options:

PCMBase. Value. NA NA value for the likelihood; used in GaussianPCM to return this value in case of an error occurring during likelihood calculation. By default, this is set to as.double(NA).

PCMBase.Errors.As.Warnings a logical flag indicating if errors (occuring, e.g. during likelihood calculation) should be treated as warnings and added as an attribute "error" to attach to the likelihood values. Default TRUE.

PCMBase.Raise.Lik.Errors Should numerical and other sort of errors occurring during likelihood calculation be raised either as errors or as warnings, depending on the option PCMBase.Errors.As.Warnings. Default TRUE. This option can be useful if too frequent warnings get raised during a model fit procedure.

PCMBase.Threshold.Lambda_ij a 0-threshold for abs(Lambda_i + Lambda_j), where Lambda_i and Lambda_j are eigenvalues of the parameter matrix H of an OU or other model. Default 1e-8. See PCMPExpxMeanExp.

- PCMBase.Threshold.EV A 0-threshold for the eigenvalues of the matrix V for a given branch. The V matrix is considered singular if it has eigenvalues smaller than PCMBase.Threshold.EV or when the ratio min(svdV)/max(svdV) is below PCMBase.Threshold.SV. Default is 1e-5. Treatment of branches with singular V matrix is defined by the option PCMBase.Skip.Singular.
- PCMBase.Threshold.SV A 0-threshold for min(svdV)/max(svdV), where svdV is the vector of singular values of the matrix V for a given branch. The V matrix is considered singular if it has eigenvalues smaller than PCMBase.Threshold.EV or when the ratio min(svdV)/max(svdV) is below PCMBase.Threshold.SV. Default is 1e-6. Treatment of branches with singular V matrix is defined by the option PCMBase.Skip.Singular.
- PCMBase.Threshold.Skip.Singular A double indicating if an internal branch of shorter length with singular matrix V should be skipped during likelihood calculation. Setting this option to a higher value, together with a TRUE value for the option PCMBase.Skip.Singular will result in tolerating some parameter values resulting in singular variance covariance matrix of the transition distribution. Default 1e-4.
- PCMBase.Skip.Singular A logical value indicating whether internal branches with singular matrix V and shorter than getOption("PCMBase.Threshold.Skip.Singular") should be skipped during likelihood calculation, adding their children L,m,r values to their parent node. Default TRUE. Note, that setting this option to FALSE may cause some models to stop working, e.g. the White model. Setting this option to FALSE will also cause errors or NA likelihood values in the case of trees with very short or 0-length branches.
- PCMBase.Tolerance.Symmetric A double specifying the tolerance in tests for symmetric matrices. Default 1e-8; see also isSymmetric.
- PCMBase.Lmr.mode An integer code specifying the parallel likelihood calculation mode.
- PCMBase.ParamValue.LowerLimit Default lower limit value for parameters, default setting is -10.0.
- PCMBase.ParamValue.LowerLimit.NonNegative Numeric (default: 0.0) indication the lower limit for parameters inheriting from class '_NonNegative's
- PCMBase.ParamValue.LowerLimit.NonNegativeDiagonal Default lower limit value for parameters corresponding to non-negative diagonal elements of matrices, default setting is 0.0.
- PCMBase.ParamValue.UpperLimit Default upper limit value for parameters, default setting is 10.0.
- PCMBase.Transpose.Sigma_x Should upper diagonal factors for variance-covariance rate matrices be transposed, e.g. should Sigma = t(Sigma_x) Sigma_x or, rather Sigma = Sigma_x t(Sigma_x)? Note that the two variants are not equal. The default is FALSE, meaning Sigma = Sigma_x t(Sigma_x). In this case, Sigma_x is not the actual upper Cholesky factor of Sigma, i.e. chol(Sigma) != Sigma_x. See also chol and UpperTriFactor. This option applies to parameters Sigma_x, Sigmae_x, Sigmaj_x and the measurement errors SE[,,i] for each measurement i when the argument SE is specified as a cube.
- PCMBase.MaxLengthListCladePartitions Maximum number of tree partitions returned by PCMTreeListCladePartition. This option has the goal to interrupt the recursive search for new partitions in the case of calling PCMTreeListCladePartitions on a big tree with a small value of the maxCladeSize argument. By default this is set to Inf.

52 PCMPairSums

PCMBase.PCMPresentCoordinatesFun A function with the same synopsis as PCMPresentCoordinates that can be specified in case of custom setting for the present coordinates for specific nodes of the tree. See PCMPresentCoordinates, and PCMInfo.

- PCMBase.Use1DClasses Logical indicating if 1D arithmetic operations should be used instead of multi-dimensional ones. This can speed-up computations in the case of a single trait. Currently, this feature is implemented only in the PCMBaseCpp R-package and only for some model types, such as OU and BM. Default: FALSE
- PCMBase.PrintSubscript_u Logical indicating if a subscript 'u' should be printed instead of a subscript 'x'. Used in PCMTable. Default: FALSE.
- PCMBase.MaxNForGuessSigma_x A real fraction number in the interval (0, 1) or an integer bigger than 1 controlling the number of tips to use for analytical calculation of the evolutionary rate matrix under a BM assumption. This option is used in the suggested PCMFit R-package. Default: 0.25.
- PCMBase.UsePCMVarForVCV Logical (default: FALSE) indicating if the function PCMTreeVCV should use PCMVar instead of ape's function vcv to calculate the phylogenetic variance covariance matrix under BM assumption. Note that setting this option to TRUE would slow down the function PCMTreeVCV considerably but may be more stable, particularly in the case of very big and deep trees, where previous ape's versions of the vcv function have thrown stack-overflow errors.

Examples

PCMOptions()

PCMPairSums

Sums of pairs of elements in a vector

Description

Sums of pairs of elements in a vector

Usage

PCMPairSums(lambda)

Arguments

lambda

a numeric vector

Value

a squared symmetric matrix with elem_ij=lambda_i+lambda_j.

PCMParam 53

PCMParam

Module PCMParam

Description

Global and S3 generic functions for manipulating model parameters. The parameters in a PCM are named objects with a class attribute specifying the main type and optional properties (tags).

S3 generic functions:

PCMParamCount() Counting the number of actual numeric parameters (used, e.g. for calculating information scores, e.g. AIC);

PCMParamLoadOrStore(), **PCMParamLoadOrStore()** Storing/loading a parameter to/from a numerical vector;

PCMParamLowerLimit(),**PCMParamUpperLimit()** Specifying parameter upper and lower limits;

PCMParamRandomVecParams() Generating a random parameter vector;

For all the above properties, check-functions are defined, e.g. 'is.Local(o)', 'is.Global(o)', 'is.ScalarParameter(o)', 'is.VectorParameter', etc.

PCMParamBindRegimeParams

Bind named vectors or matrices into an array so that the names form the names of the last dimension.

Description

Bind named vectors or matrices into an array so that the names form the names of the last dimension.

Usage

PCMParamBindRegimeParams(...)

Arguments

Any number of named vectors, or matrices. The dimensions of all the arrays must match. The names will be used for the names of the regimes.

Value

an array with dim attribute one longer than the number of dimensions of each argument, i.e. if there are 5 vector arguments of length 2, the returned value will be an array with dim c(2,5); if there are 5 matrix arguments of dim 2 x 2, the returned value will be an array with dim c(2,2,5).

Examples

```
# regimes
# in regime 'a' the three traits evolve according to three independent OU processes
a.X0 < -c(5, 2, 1)
a.H <- rbind(
  c(0, 0, 0),
  c(0, 2, 0),
  c(0, 0, 3))
a. Theta <- c(10, 6, 2)
a.Sigma_x <- rbind(</pre>
  c(1.6, 0.0, 0.0),
  c(0.0, 2.4, 0.0),
  c(0.0, 0.0, 2.0)
a.Sigmae_x <- rbind(
  c(0.0, 0.0, 0.0),
  c(0.0, 0.0, 0.0),
  c(0.0, 0.0, 0.0)
a.h_drift<-c(0, 0, 0)
# in regime 'b' there is correlation between the traits
b.X0 < -c(12, 4, 3)
b.H <- rbind(</pre>
 c(2.0, 0.1, 0.2),
  c(0.1, 0.6, 0.2),
  c(0.2, 0.2, 0.3))
b. Theta <- c(10, 6, 2)
b.Sigma_x <- rbind(</pre>
  c(1.6, 0.3, 0.3),
  c(0.0, 0.3, 0.4),
  c(0.0, 0.0, 2.0)
b.Sigmae_x <- rbind(</pre>
  c(0.2, 0.0, 0.0),
  c(0.0, 0.3, 0.0),
  c(0.0, 0.0, 0.4))
b.h_drift<-c(1, 2, 3)
H <- PCMParamBindRegimeParams(a = a.H, b = b.H)</pre>
Theta <- PCMParamBindRegimeParams(a = a.Theta, b = b.Theta)
Sigma_x <- PCMParamBindRegimeParams(a = a.Sigma_x, b = b.Sigma_x)</pre>
Sigmae_x <- PCMParamBindRegimeParams(a = a.Sigmae_x, b = b.Sigmae_x)</pre>
h_drift <- PCMParamBindRegimeParams(a = a.h_drift, b = b.h_drift)</pre>
model.a.BM_drift.123 <- PCM("BM_drift", k = 3, regimes = "a",</pre>
params = list(
  X0 = a.X0,
  h_drift = h_drift[,'a',drop=FALSE],
  Sigma_x = Sigma_x[,,'a',drop=FALSE],
  Sigmae_x = Sigmae_x[,,'a',drop=FALSE]))
# regimes 'a' and 'b', traits 1, 2 and 3
model.ab.123 \leftarrow PCM("OU", k = 3, regimes = c("a", "b"),
```

PCMParamCount 55

```
params = list(
 X0 = a.X0,
 H = H[,,,drop=FALSE],
 Theta = Theta[,,drop=FALSE],
 Sigma_x = Sigma_x[,,,drop=FALSE],
 Sigmae_x = Sigmae_x[,,,drop=FALSE]))
```

PCMParamCount

Count the number of free parameters associated with a PCM or a PCM-parameter

Description

Count the number of free parameters associated with a PCM or a PCM-parameter

Usage

```
PCMParamCount(
  countRegimeChanges = FALSE,
  countModelTypes = FALSE,
  offset = 0L,
  k = 1L
 R = 1L
 parentModel = NULL
)
```

Arguments

a PCM model object or a parameter of a PCM object

countRegimeChanges

logical indicating if regime changes should be counted. If TRUE, the default implementation would add PCMNumRegimes(model) - 1. Default FALSE.

countModelTypes

logical indicating whether the model type should be counted. If TRUE the default implementation will add +1 only if there are more than one modelTypes (length(attr(model, "modelTypes", exact = TRUE)) > 1), assuming that allregimes are regimes of the same model type (e.g. OU). The implementation for MRG models will add +1 for every regime if there are more than one model-Types. Default FALSE.

offset an integer denoting an offset count from which to start counting (internally

used). Default: 0.

an integer denoting the number of modeled traits. Default: 1. k

R an integer denoting the number of regimes in the model. Default: 1.

NULL or a PCM object. Default: NULL. parentModel

56 PCMParamLoadOrStore

Value

an integer

PCMParamGetShortVector

Get a vector of the variable numeric parameters in a model

Description

The short vector of the model parameters does not include the nodes in the tree where a regime change occurs, nor the the model types associated with each regime.

Usage

```
PCMParamGetShortVector(o, k = 1L, R = 1L, ...)
```

Arguments

o a PCM model object or a parameter of a PCM object

k an integer denoting the number of modeled traits. Default: 1.

R an integer denoting the number of regimes in the model. Default: 1.

... other arguments that could be used by implementing methods.

Value

a numeric vector of length equal to 'PCMParamCount(o, FALSE, FALSE, 0L, k, R)'.

PCMParamLoadOrStore Load (or store) a PCM parameter from (or to) a vector of the variable parameters in a model.

Description

Load (or store) a PCM parameter from (or to) a vector of the variable parameters in a model.

```
PCMParamLoadOrStore(o, vecParams, offset, k, R, load, parentModel = NULL)
```

Arguments

o a PCM model object or a parameter of a PCM object

vecParams a numeric vector.

offset an integer denoting an offset count from which to start counting (internally

used). Default: 0.

k an integer denoting the number of modeled traits. Default: 1.

R an integer denoting the number of regimes in the model. Default: 1.

load logical indicating if parameters should be loaded from vecParams into o (TRUE)

or stored to vecParams from o (FALSE).

parentModel NULL or a PCM object. Default: NULL.

Details

This S3 generic function has both, a returned value and side effects.

Value

an integer equaling the number of elements read from vecParams. In the case of type=="custom", the number of indices bigger than offset returned by the function indices(offset, k).

PCMParamLocateInShortVector

Locate a named parameter in the short vector representation of a

model

Description

Locate a named parameter in the short vector representation of a model

Usage

PCMParamLocateInShortVector(o, accessExpr, enclos = "?")

Arguments

o a PCM model object.

accessExpr a character string used to access the parameter, e.g. "\$Theta[,,1]" or "[['Theta']][,,1]".

enclos a character string containing the symbol '?', e.g. 'diag(?)'. The meaning

of this symbol is to be replaced by the matching accessExpr (see examples).

Default value: '?'.

Value

an integer vector of length PCMParamCount(o) with NAs everywhere except at the coordinates corresponding to the parameter in question.

Examples

```
model <- PCM(PCMDefaultModelTypes()["D"], k = 3, regimes = c("a", "b"))
# The parameter H is a diagonal 3x3 matrix. If this matrix is considered as
# a vector the indices of its diagonal elements are 1, 5 and 9. These indices
# are indicated as the non-NA entries in the returned vector.

PCMParamLocateInShortVector(model, "$H[,,1]")
PCMParamLocateInShortVector(model, "$H[,,'a']")
PCMParamLocateInShortVector(model, "$H[,,'b']")
PCMParamLocateInShortVector(model, "$Sigma_x[,,'b']", enclos = 'diag(?)')
PCMParamLocateInShortVector(model, "$Sigma_x[,,'b']", enclos = '?[upper.tri(?)]')</pre>
```

PCMParamLowerLimit

The lower limit for a given model or parameter type

Description

This is an S3 generic function.

Usage

```
PCMParamLowerLimit(o, k, R, ...)
```

Arguments

- o an object such as a VectorParameter a MatrixParameter or a PCM.
 k integer denoting the number of traits
- R integer denoting the number of regimes in the model in which o belongs to.
- . . . additional arguments (optional or future use).

Value

an object of the same S3 class as o representing a lower limit for the class.

PCMParamRandomVecParams

Generate a random parameter vector for a model using uniform distribution between its lower and upper bounds.

Description

Generate a random parameter vector for a model using uniform distribution between its lower and upper bounds.

Usage

```
PCMParamRandomVecParams(
   o,
   k,
   R,
   n = 1L,
   argsPCMParamLowerLimit = NULL,
   argsPCMParamUpperLimit = NULL
)
```

Arguments

```
o a PCM model object or a parameter k integer denoting the number of traits.

R integer denoting the number of regimes.

n an integer specifying the number of random vectors to generate argsPCMParamLowerLimit, argsPCMParamUpperLimit named lists of arguments passed to PCMParamLowerLimit and PCMParamUpperLimit.
```

Value

a numeric matrix of dimension n x PCMParamCount(o).

See Also

PCMParamLimits PCMParamGetShortVector

PCMParamSetByName

Set model parameters from a named list

Description

Set model parameters from a named list

```
PCMParamSetByName(
  model,
  params,
  inplace = TRUE,
  replaceWholeParameters = FALSE,
  deepCopySubPCMs = FALSE,
  failIfNamesInParamsDontExist = TRUE,
  ...
)
```

60 PCMParamType

Arguments

model a PCM model object

params a named list with elements among the names found in model

inplace logical indicating if the parameters should be set "inplace" for the model object

in the calling environment or a new model object with the parameters set as

specified should be returned. Defaults to TRUE.

replaceWholeParameters

logical, by default set to FALSE. If TRUE, the parameters will be completely replaced, meaning that their attributes (e.g. S3 class) will be replaced as well (dangerous).

deepCopySubPCMs

a logical indicating whether nested PCMs should be 'deep'-copied, meaning element by element, eventually preserving the attributes as in model. By default this is set to FALSE, meaning that sub-PCMs found in params will completely overwrite the sub-PCMs with the same name in model.

failIfNamesInParamsDontExist

logical indicating if an error should be raised if params contains elements not existing in model. Default: TRUE.

... other arguments that can be used by implementing methods.

Value

If inplace is TRUE, the function only has a side effect of setting the parameters of the model object in the calling environment; otherwise the function returns a modified copy of the model object.

PCMParamType Parameter types

Description

The parameter types are divided in the following categories:

Main type These are the "ScalarParameter", "VectorParameter" and "MatrixParameter" classes. Each model parameter must have a main type.

Scope/Omission These are the "_Global" and "_Omitted" classes. Every parameter can be global for all regimes or local for a single regime. If not specified, local scope is assumed. In some special cases a parameter (e.g. Sigmae can be omitted from a model. This is done by adding " Omitted" to its class attribute.

Constancy (optional) These are the "_Fixed", "_Ones", "_Identity" and "_Zeros" classes.

Transformation (optional) These are the "_Transformable", "_CholeskyFactor" and "_Schur" classes.

Other properties (optional) These are the "_NonNegative", "_WithNonNegativeDiagonal", "_LowerTriangular", "_AllEqual", "_ScalarDiagonal", "_Symmetric", "_UpperTriangular", "_LowerTriangularWithDiagonal" and "_UpperTriangularWithDiagonal" classes.

PCMParamType 61

```
is.Local(o)
is.Global(o)
is.ScalarParameter(o)
is.VectorParameter(o)
is.MatrixParameter(o)
is.WithCustomVecParams(o)
is.Fixed(o)
is.Zeros(o)
is.Ones(o)
is.Identity(o)
is.AllEqual(o)
is.NonNegative(o)
is.Diagonal(o)
is.ScalarDiagonal(o)
is.Symmetric(o)
is.UpperTriangular(o)
is.UpperTriangularWithDiagonal(o)
is.WithNonNegativeDiagonal(o)
is.LowerTriangular(o)
is.LowerTriangularWithDiagonal(o)
is.Omitted(o)
is.CholeskyFactor(o)
is.Schur(o)
is.Transformable(o)
```

62 PCMParamType

```
is.Transformed(o)
is.SemiPositiveDefinite(o)
```

Arguments

o an object, i.e. a PCM or a parameter object.

Value

logical indicating if the object passed is from the type appearing in the function-name.

Functions

- is.Local:
- is.Global:
- is.ScalarParameter:
- is.VectorParameter:
- is.MatrixParameter:
- is.WithCustomVecParams:
- is.Fixed:
- is.Zeros:
- is.Ones:
- is.Identity:
- is.AllEqual:
- is.NonNegative:
- is.Diagonal:
- is.ScalarDiagonal:
- is.Symmetric:
- is.UpperTriangular:
- is.UpperTriangularWithDiagonal:
- is.WithNonNegativeDiagonal:
- is.LowerTriangular:
- is.LowerTriangularWithDiagonal:
- is.Omitted:
- is.CholeskyFactor:
- is.Schur:
- is.Transformable:
- is.Transformed:
- is.SemiPositiveDefinite:

PCMParamUpperLimit

The upper limit for a given model or parameter type

Description

This is an S3 generic function.

Usage

```
PCMParamUpperLimit(o, k, R, ...)
```

Arguments

o an object such as a VectorParameter a MatrixParameter or a PCM.

k integer denoting the number of traits

R integer denoting the number of regimes in the model in which o belongs to.

... additional arguments (optional or future use).

Value

an object of the same S3 class as o representing an upper limit for the class.

PCMParentClasses

Parent S3 classes for a model class

Description

Parent S3 classes for a model class

Usage

PCMParentClasses(model)

Arguments

model

an S3 object.

Details

This S3 generic function is intended to be specified for user models. This function is called by the 'PCM.character' method to determine the parent classes for a given model class.

Value

a vector of character string denoting the names of the parent classes

PCMPExpxMeanExp

PCMParseErrorMessage Extract error information from a formatted error message.

Description

Extract error information from a formatted error message.

Usage

```
PCMParseErrorMessage(x)
```

Arguments

Х

character string representing the error message.

Value

Currently the function returns x unchanged.

PCMPExpxMeanExp

Create a function of time that calculates $(1 - exp(-lambda_ij * time))/lambda_ij$ for every element $lambda_ij$ of the input matrix $Lambda_ij$.

Description

Create a function of time that calculates $(1-exp(-lambda_ij*time))/lambda_ij$ for every element $lambda_ij$ of the input matrix $Lambda_ij$.

Usage

```
PCMPExpxMeanExp(
  Lambda_ij,
  threshold.Lambda_ij = getOption("PCMBase.Threshold.Lambda_ij", 1e-08)
)
```

Arguments

```
Lambda_ij a squared numerical matrix of dimension k x k threshold.Lambda_ij
```

a 0-threshold for abs(Lambda_i + Lambda_j), where Lambda_i and Lambda_j are eigenvalues of the parameter matrix H. This threshold-value is used as a condition to take the limit time of the expression '(1-exp(-Lambda_ij*time))/Lambda_ij' as '(Lambda_i+Lambda_j) -> 0'. You can control this value by the global option "PCMBase.Threshold.Lambda_ij". The default value (1e-8) is suitable for branch lengths bigger than 1e-6. For smaller branch lengths, you may want to increase the threshold value using, e.g. 'options(PCMBase.Threshold.Lambda_ij=1e-6)'.

PCMPLambdaP_1 65

Details

the function $(1 - exp(-lambda_ij * time))/lambda_ij$ corresponds to the product of the CDF of an exponential distribution with rate $Lambda_ij$ multiplied by its mean value (mean waiting time).

Value

a function of time returning a matrix with entries formed from the above function or the limit, time, if $|Lambda_{ij}| \le trehshold0$.

PCMPLambdaP_1

Eigen-decomposition of a matrix H

Description

Eigen-decomposition of a matrix H

Usage

```
PCMPLambdaP_1(H)
```

Arguments

Н

a numeric matrix

Details

The function fails with an error message if H is defective, that is, if its matrix of eigenvectors is computationally singular. The test for singularity is based on the roond function.

Value

a list with elements as follows:

lambda a vector of the eigenvalues of H

P a squared matrix with column vectors, the eigenvectors of H corresponding to

the eigenvalues in lambda

P_1 the inverse matrix of P

.

PCMPlotGaussianDensityGrid2D

A 2D Gaussian distribution density grid in the form of a ggplot object

Description

A 2D Gaussian distribution density grid in the form of a ggplot object

Usage

```
PCMPlotGaussianDensityGrid2D(
   mu,
   Sigma,
   xlim,
   ylim,
   xNumPoints = 100,
   yNumPoints = 100,
   ...
)
```

Arguments

```
mu numerical mean vector of length 2

Sigma numerical 2 x 2 covariance matrix

xlim, ylim numerical vectors of length 2

xNumPoints, yNumPoints
 integers denoting how many points should the grid contain for each axis.

... additional arguments passed to ggplot
```

Value

```
a ggplot object
```

PCMPlotGaussianSample2D

A 2D sample from Gaussian distribution

Description

A 2D sample from Gaussian distribution

```
PCMPlotGaussianSample2D(mu, Sigma, numPoints = 1000, ...)
```

PCMPlotMath 67

Arguments

mu numerical mean vector of length 2 Sigma numerical 2 x 2 covariance matrix

numPoints an integer denoting how many points should be randomly sampled (see details).

... additional arguments passed to ggplot.

Details

This function generates a random sample of numPoints 2d points using the function rmvnorm from the mvtnorm R-package. Then it produces a ggplot on the generated points.

Value

a ggplot object

PCMPlotMath

Beautiful model description based on plotmath

Description

This is an S3 generic that produces a plotmath expression for its argument.

Usage

```
PCMPlotMath(o, roundDigits = 2, transformSigma_x = FALSE)
```

Arguments

o a PCM or a parameter object.

roundDigits an integer, default: 2.

transformSigma_x

a logical indicating if Cholesky transformation should be applied to Cholesky-

factor parameters prior to generating the plotmath expression.

Value

a character string.

68 PCMPlotTraitData2D

PCMPlotTraitData2D

Scatter plot of 2-dimensional data

Description

Scatter plot of 2-dimensional data

Usage

```
PCMPlotTraitData2D(
   X,
   tree,
   sizePoints = 2,
   alphaPoints = 1,
   labeledTips = NULL,
   sizeLabels = 8,
   nudgeLabels = c(0, 0),
   palette = PCMColorPalette(PCMNumRegimes(tree), PCMRegimes(tree)),
   scaleSizeWithTime = !is.ultrametric(tree),
   numTimeFacets = if (is.ultrametric(tree) || scaleSizeWithTime) 1L else 3L,
   nrowTimeFacets = 1L,
   ncolTimeFacets = numTimeFacets
)
```

Arguments

X a k x N matrix tree a phylo object sizePoints, alphaPoints

numeric parameters passed as arguments size and alpha to geom_point. Default:

sizePoints = 2, alphaPoints = 1.

labeledTips a vector of tip-numbers to label (NULL by default)

sizeLabels passed to geom_text to specify the size of tip-labels for the trait-points.

nudgeLabels a numeric vector of two elements (default: c(0,0)), passed as arguments nudge_x

and nudge_y of geom_text.

palette a named vector of colors

scaleSizeWithTime

logical indicating if the size and the transparency of the points should reflect the distance from the present (points that are farther away in time with respect to the present moment, i.e. closer to the root of the tree, are displayed smaller and

more transparent.). By default this is set to !is.ultrametric(tree).

numTimeFacets

a number or a numeric vector controlling the creation of different facets corresponding to different time intervals when the tree is non-ultrametric. If a single number, it will be interpreted as an integer specifying the number of facets, each facets corresponding to an equal interval of time. If a numeric vector, it will be

PCMPresentCoordinates 69

```
used to specify the cut-points for each interval. Default: if(is.ultrametric(tree) || scaleSizeWithTime) 1L else 3.
```

nrowTimeFacets, ncolTimeFacets

integers specifying how the time facets should be layed out. Default: nrowTimeFacets = 1L, ncolTimeFacets = numTimeFacets.

Value

a ggplot object

PCMPresentCoordinates Determine which traits are present (active) on each node of the tree

Description

For every node (root, internal or tip) in tree, build a logical vector of length k with TRUE values for every present coordinate. Non-present coordinates arize from NA-values in the trait data. These can occur in two cases:

Missing measurements for some traits at some tips: the present coordinates are FALSE for the corresponding tip and trait, but are full for all traits at all internal and root nodes.

non-existent traits for some species: the FALSE present coordinates propagate towards the parent nodes - an internal or root node will have a present coordinate set to FALSE for a given trait, if all of its descendants have this coordinate set to FALSE.

These two cases have different effect on the likelihood calculation: missing measurements (NA) are integrated out at the parent nodes; while non-existent traits (NaN) are treated as reduced dimensionality of the vector at the parent node.

Usage

PCMPresentCoordinates(X, tree, metaI)

Arguments

X numeric k x N matrix of observed values, with possible NA entries. The columns

in X are in the order of tree\$tip.label

tree a phylo object

metaI The result of calling PCMInfo.

Value

a k x M logical matrix. The function fails in case when all traits are NAs for some of the tips. In that case an error message is issued "PCMPresentCoordinates:: Some tips have 0 present coordinates. Consider removing these tips.".

See Also

PCMLik

70 PCMSetAttribute

PCMRegimes

Get the regimes (aka colors) of a PCM or of a PCMTree object

Description

Get the regimes (aka colors) of a PCM or of a PCMTree object

Usage

```
PCMRegimes(obj)
```

Arguments

obj

a PCM or a PCMTree object

Value

a character or an integer vector giving the regime names in the obj

 ${\sf PCMSetAttribute}$

Set an attribute of a named member in a PCM or other named list object

Description

Set an attribute of a named member in a PCM or other named list object

```
PCMSetAttribute(
  name,
  value,
  object,
  member = "",
  spec = TRUE,
  inplace = TRUE,
  ...
)
```

PCMSim 71

Arguments

name	a character string denoting the attribute name.
value	the value for the attribute.
object	a PCM or a list object.
member	a member expression. Member expressions are character strings denoting named elements in a list object (see examples). Default: "".
spec	a logical (TRUE by default) indicating if the attribute should also be set in the corresponding member of the spec attribute (this is for PCM objects only).
inplace	logical (TRUE by default) indicating if the attribute should be set to the object in the current environment, or a modified object should be returned.
	additional arguments passed to MatchListMembers.

Details

Calling this function can affect the attributes of multiple members matched by the member argument.

Value

if inplace is TRUE (default) nothing is returned. Otherwise, a modified version of object is returned.

Examples

```
model <- PCMBaseTestObjects$model_MixedGaussian_ab
PCMSetAttribute("class", c("MatrixParameter", "_Fixed"), model, "H")</pre>
```

PCMSim

Simulation of a phylogenetic comparative model on a tree

Description

Generate trait data on a tree according to a multivariate stochastic model with one or several regimes

```
PCMSim(
   tree,
   model,
   X0,
   SE = matrix(0, PCMNumTraits(model), PCMTreeNumTips(tree)),
   metaI = PCMInfo(X = NULL, tree = tree, model = model, SE = SE, verbose = verbose),
   verbose = FALSE
)
```

72 PCMSim

Arguments

tree	a phylo object specifying a rooted tree.
model	an S3 object specifying the model (see Details).
X0	a numeric vector of length \boldsymbol{k} (the number of traits) specifying the trait values at the root of the tree.
SE	a k x N matrix specifying the standard error for each measurement in X. Alternatively, a k x k x N cube specifying an upper triangular k x k factor of the variance covariance matrix for the measurement error for each node i=1,, N. Default: $matrix(0.0, PCMNumTraits(model), PCMTreeNumTips(tree))$.
metaI	a named list containing meta-information about the data and the model.
verbose	a logical indicating if informative messages should be written during execution.

Details

Internally, this function uses the PCMCond implementation for the given model class.

Value

numeric M x k matrix of values at all nodes of the tree, i.e. root, internal and tip, where M is the number of nodes: $M=\dim(\text{tree}\ensuremath{\$}\text{edge})[1]+1$, with indices from 1 to $N=\operatorname{length}(\text{tree}\ensuremath{\$}\text{tip.label})$ corresponding to tips, N+1 corresponding to the root and bigger than N+1 corresponding to internal nodes. The function will fail in case that the length of the argument vector X0 differs from the number of traits specified in $metal\ensuremath{\$}$ k. Error message: "PCMSim:: X0 must be of length ...".

See Also

PCMLik PCMInfo PCMCond

Examples

```
N <- 10
L <- 100.0
tr <- ape::stree(N)
tr$edge.length <- rep(L, N)
for(epoch in seq(1, L, by = 1.0)) {
   tr <- PCMTreeInsertSingletonsAtEpoch(tr, epoch)
}
model <- PCMBaseTestObjects$model_MixedGaussian_ab

PCMTreeSetPartRegimes(tr, c(`11` = 'a'), setPartition = TRUE)

set.seed(1, kind = "Mersenne-Twister", normal.kind = "Inversion")
X <- PCMSim(tr, model, X0 = rep(0, 3))</pre>
```

PCMSpecify 73

PCMSpecify

Parameter specification of PCM model

Description

The parameter specification of a PCM model represents a named list with an entry for each parameter of the model. Each entry in the list is a structure defining the S3 class of the parameter and its verbal description. This is an S3 generic. See 'PCMSpecify.OU' for an example method.

Usage

```
PCMSpecify(model, ...)
```

Arguments

model a PCM model object.

... additional arguments used by implementing methods.

Value

a list specifying the parameters of a PCM.

PCMTable

A data.table representation of a PCM object

Description

A data.table representation of a PCM object

Usage

```
PCMTable(
  model,
  skipGlobalRegime = FALSE,
  addTransformed = TRUE,
  removeUntransformed = TRUE)
```

Arguments

```
model a PCM object. skipGlobalRegime
```

logical indicating whether a raw in the returned table for the global-scope parameters should be omitted (this is mostly for internal use). Default (FALSE).

addTransformed logical. If TRUE (the default), columns for the transformed version of the transformable parameters will be added.

removeUntransformed

logical If TRUE (default), columns for the untransformed version of the transformable parameters will be omitted.

Details

This is an S3 generic.

Value

an object of S3 class PCMTable

PCMTableParameterizations

Cartesian product of possible parameterizations for the different parameters of a model

Description

This function generates a data.table in which each column corresponds to one parameter of model and each row corresponds to one combination of parameterizations for the model parameters, such that the whole table corresponds to the Cartesian product of the lists found in 'listParameterizations'. Usually, subsets of this table should be passed to 'PCMGenerateParameterizations'

Usage

```
PCMTableParameterizations(
  model,
  listParameterizations = PCMListParameterizations(model, ...),
  ...
)
```

Arguments

```
model a PCM object.

listParameterizations

a list returned by a method for 'PCMListParameterizations'. Default: 'PCM-ListParameterizations(model, ...)'.

additional arguments passed to 'PCMListParameterizations(model, ...)'.
```

Value

a data.table object.

PCMTrajectory 75

PCMTrajectory

Generate a trajectory for the mean in one regime of a PCM

Description

Generate a trajectory for the mean in one regime of a PCM

Usage

```
PCMTrajectory(
  model,
  regime = PCMRegimes(model)[1],
  X0 = rep(0, PCMNumTraits(model)),
  W0 = matrix(0, nrow = PCMNumTraits(model), ncol = PCMNumTraits(model)),
  tX = seq(0, 100, by = 1),
  tVar = tX[seq(0, length(tX), length.out = 4)],
  dims = seq_len(PCMNumTraits(model)),
  sizeSamp = 100,
  doPlot2D = FALSE,
  plot = NULL
)
```

Arguments

model	a PCM object.
regime	a regime in 'model'. Default is PCMRegimes(model)[1].
X0	a numeric vector specifying an initial point in the trait space. Default is rep(0, PCMNumTraits(model))
WØ	a numeric $k \times k$ symmetric positive definite matrix or 0 matrix, specifying the initial variance covariance matrix at t0. By default, this is a $k \times k$ 0 matrix.
tX, tVar	numeric vectors of positive points in time sorted in increasing order. tX specifies the points in time at which to calculate the mean (conditional on x 0). t Var specifies a subset of the points in t X at which to generate random samples from the t 4-variate Gaussian distribution with mean equal to the mean value at the corresponding time conditional on t 40 and variance equal to the variance at this time, conditional on t 40. Default settings are ' t 40, t 40, by = 1)' and ' t 40 are t 40, length(t 40), length(t 40), length(t 40).
dims	an integer vector specifying the traits for which samples at tVar should be generated (see tX,tVar above). Default: seq_len(PCMNumTraits(model)).
sizeSamp	an integer specifying the number points in the random samples (see tX and tVar above). Default 100.
doPlot2D	Should a ggplot object be produced and returned. This is possible only for two of the traits specified in dims. Default: FALSE.
plot	a ggplot object. This can be specified when doPlot2D is TRUE and allows to add the plot of this trajectory as a layer in an existing ggplot. Default: NULL

76 PCMTrajectory

Value

if doPlot2D is TRUE, returns a ggplot. Otherwise a named list of two elements:

dt a data.table with columns 'regime', 't', 'X', 'V' and 'samp'. For each row corresponding to time in tVar, the column samp represents a list of sizeSamp k-vectors.

dtPlot a data.table with the same data as in dt, but with converted columns X and samp into 2 x k columns denoted xi, i=1,...,k and xsi (i=1...k) This is suitable for plotting with ggplot.

```
set.seed(1, kind = "Mersenne-Twister", normal.kind = "Inversion")
# a Brownian motion model with one regime
modelOU <- PCM(model = PCMDefaultModelTypes()['F'], k = 2)</pre>
# assign the model parameters at random: this will use uniform distribution
# with boundaries specified by PCMParamLowerLimit and PCMParamUpperLimit
# We do this in two steps:
# 1. First we generate a random vector. Note the length of the vector equals
# PCMParamCount(modelBM).
randomParams <- PCMParamRandomVecParams(</pre>
  modelOU, PCMNumTraits(modelOU), PCMNumRegimes(modelOU))
# 2. Then we load this random vector into the model.
PCMParamLoadOrStore(
  modelOU,
  randomParams,
  0, PCMNumTraits(modelBM), PCMNumRegimes(modelBM), load = TRUE)
# let's plot the trajectory of the model starting from X0 = c(0,0)
PCMTrajectory(
  model = modelOU,
  X0 = c(0, 0),
  doPlot2D = TRUE)
# A faceted grid of plots for the two regimes in a mixed model:
pla <- PCMTrajectory(</pre>
  model = PCMBaseTestObjects$model_MixedGaussian_ab, regime = "a",
  X0 = c(0, 0, 0),
  doPlot2D = TRUE) +
  ggplot2::scale_y\_continuous(limits = c(0, 10)) +
  ggplot2::facet_grid(.~regime)
plb <- PCMTrajectory(</pre>
  model = PCMBaseTestObjects$model_MixedGaussian_ab, regime = "b",
  X0 = c(0, 0, 0),
  doPlot2D = TRUE) +
  ggplot2::scale_y_continuous(limits = c(0, 10)) +
  ggplot2::facet_grid(.~regime) +
  ggplot2::theme(
    axis.title.y = ggplot2::element_blank(),
```

PCMTree 77

```
axis.text.y = ggplot2::element_blank(),
axis.ticks.y = ggplot2::element_blank())
plot(pla)
plot(plb)
```

PCMTree

Create a PCMTree object from a phylo object

Description

PCMTree is class that inherits from the class 'phylo' in the R-package 'ape'. Thus, all the functions working on a phylo object would work in the same way if they receive as argument an object of class 'PCMTree'. A PCMTree object has the following members in addition to the regular members ('tip.label', 'node.label', 'edge', 'edge.length') found in a regular phylo object:

edge.part a character vector having as many elements as there are branches in the tree (corresponding to the rows in 'tree\$edge'). Each element denotes the name of the part to which the corresponding branch belongs. A part in the tree represents a connected subset of its nodes and the branches leading to these nodes. A partition of the tree represents the splitting of the tree into a number of parts. Visually, a partition can be represented as a coloring of the tree, in which no color is assigned to more than one part. In other words, if two branches in the tree are connected by the same color, they either share a node, or all the branches on the path in the tree connecting these two branches have the same color. Formally, we define a partition of the tree as any set of nodes in the tree that includes the root. Each node in this set defines a part as the set of its descendant nodes that can be reached without traversing another partition node. We name each part by the label of its most ancestral node, that is, the node in it, which is closest to the root fo the tree. The value of edge.part for an edge in the tree is the name of the part that contains the node to which the edge is pointing.

part.regime a named vector of size the number of parts in the tree. The names correspond to part-names whereas the values denote the ids or character names of regimes in a PCM object.

The constructor PCMTree() returns an object of call

Usage

```
PCMTree(tree)
```

Arguments

tree

a phylo object. If this is already a PCMTree object, a copy of this object will be returned.

Value

an object of class PCMTree. This is a copy of the passed phylo object which is guaranteed to have node.label, edge.part and a part.regime entries set.

78 PCMTree

```
tree <- ape::rtree(8)</pre>
# the following four are NULLs
tree$node.label
tree$edge.part
tree$part.regime
tree$edge.regime
# In previous version regimes were assigned directly to the edges via
# tree$edge.regime. This is supported but not recommended anymore:
tree$edge.regime <- sample(</pre>
  letters[1:3], size = PCMTreeNumNodes(tree) - 1, replace = TRUE)
tree.a <- PCMTree(tree)</pre>
PCMTreeGetLabels(tree.a)
tree.a$node.label
tree.a$edge.part
tree.a$part.regime
# this is set to NULL - starting from PCMBase 1.2.9 all of the information
# for the regimes is stored in tree$edge.part and tree$part.regime.
tree.a$edge.regime
PCMTreeGetPartition(tree.a)
PCMTreeGetPartNames(tree.a)
PCMTreeGetPartRegimes(tree.a)
# let's see how the tree looks like
if(requireNamespace("ggtree"))
PCMTreePlot(tree.a) + ggtree::geom_nodelab() + ggtree::geom_tiplab()
# This is the recommended way to set a partition on the tree
PCMTreeSetPartition(tree.a, c(10, 12))
PCMTreeGetPartition(tree.a)
PCMTreeGetPartNames(tree.a)
PCMTreeGetPartRegimes(tree.a)
if(requireNamespace("ggtree"))
PCMTreePlot(tree.a) + ggtree::geom_nodelab() + ggtree::geom_tiplab()
PCMTreeGetPartsForNodes(tree.a, c(11, 15, 12))
PCMTreeGetPartsForNodes(tree.a, c("11", "15", "12"))
PCMTreeSetPartRegimes(tree.a, c('9' = 'a', '10' = 'b', '12' = 'c'))
PCMTreeGetPartition(tree.a)
PCMTreeGetPartNames(tree.a)
```

PCMTreeBackbonePartition 79

```
PCMTreeGetPartRegimes(tree.a)

if(requireNamespace("ggtree"))
PCMTreePlot(tree.a) + ggtree::geom_nodelab() + ggtree::geom_tiplab()
```

PCMTreeBackbonePartition

Prune the tree leaving one tip for each or some of its parts

Description

Prune the tree leaving one tip for each or some of its parts

Usage

```
PCMTreeBackbonePartition(tree, partsToKeep = PCMTreeGetPartNames(tree))
```

Arguments

tree a PCMTree or a phylo object.

partsToKeep a character vector denoting part names in the tree to be kept. Defaults to 'PCMTreeGet-

PartNames(tree)'.

Value

a PCMTree object representing a pruned version of tree.

See Also

PCMTreeSetPartition

PCMTree

```
set.seed(1, kind = "Mersenne-Twister", normal.kind = "Inversion")
tree <- PCMTree(ape::rtree(25))

if(requireNamespace("ggtree"))
PCMTreePlot(tree) + ggtree::geom_nodelab(angle = 45) +
    ggtree::geom_tiplab(angle = 45)

backb <- PCMTreeBackbonePartition(tree)

if(requireNamespace("ggtree"))
PCMTreePlot(backb) + ggtree::geom_nodelab(angle = 45) +
    ggtree::geom_tiplab(angle = 45)</pre>
tree2 <- PCMTreeSetPartRegimes(
```

```
tree, c(^26) = ^a", ^28) = ^b"), setPartition = TRUE,
  inplace = FALSE)
if(requireNamespace("ggtree"))
PCMTreePlot(tree2) + ggtree::geom_nodelab(angle = 45) +
  ggtree::geom_tiplab(angle = 45)
backb <- PCMTreeBackbonePartition(tree2)</pre>
if(requireNamespace("ggtree"))
PCMTreePlot(backb) + ggtree::geom_nodelab(angle = 45) +
  ggtree::geom_tiplab(angle = 45)
tree3 <- PCMTreeSetPartRegimes(</pre>
  tree, c(^26) = ^a", ^28) = ^b", ^41) = ^c", setPartition = TRUE,
  inplace = FALSE)
if(requireNamespace("ggtree"))
PCMTreePlot(tree3) + ggtree::geom_nodelab(angle = 45) +
  ggtree::geom_tiplab(angle = 45)
backb <- PCMTreeBackbonePartition(tree3)</pre>
if(requireNamespace("ggtree"))
PCMTreePlot(backb) + ggtree::geom_nodelab(angle = 45) +
  ggtree::geom_tiplab(angle = 45)
backb41 <- PCMTreeBackbonePartition(tree3, partsToKeep = "41")</pre>
if(requireNamespace("ggtree"))
PCMTreePlot(backb41) + ggtree::geom_nodelab(angle = 45) +
  ggtree::geom_tiplab(angle = 45)
backbMoreNodes <- PCMTreeInsertSingletonsAtEpoch(</pre>
   backb, epoch = 3.7, minLength = 0.001)
PCMTreeGetPartRegimes(backbMoreNodes)
if(requireNamespace("ggtree"))
PCMTreePlot(backbMoreNodes) + ggtree::geom_nodelab(angle=45) +
  ggtree::geom_tiplab(angle=45)
backbMoreNodes <- PCMTreeInsertSingletonsAtEpoch(</pre>
   backbMoreNodes, epoch = 0.2, minLength = 0.001)
PCMTreeGetPartRegimes(backbMoreNodes)
if(requireNamespace("ggtree"))
PCMTreePlot(backbMoreNodes) + ggtree::geom_nodelab(angle=45) +
  ggtree::geom_tiplab(angle=45)
backbMoreNodes <- PCMTreeInsertSingletonsAtEpoch(</pre>
   backbMoreNodes, epoch = 1.2, minLength = 0.001)
PCMTreeGetPartRegimes(backbMoreNodes)
```

PCMTreeDropClade 81

```
if(requireNamespace("ggtree"))
PCMTreePlot(backbMoreNodes) + ggtree::geom_nodelab(angle=45) +
    ggtree::geom_tiplab(angle=45)
```

PCMTreeDropClade

Drop a clade from a phylogenetic tree

Description

Drop a clade from a phylogenetic tree

Usage

```
PCMTreeDropClade(
    tree,
    cladeRootNode,
    tableAncestors = NULL,
    X = NULL,
    returnList = !is.null(X),
    errorOnMissing = FALSE
)
```

Arguments

tree a phylo object

cladeRootNode a character string denoting the label or an integer denoting a node in the tree

tableAncestors an integer matrix returned by a previous call to PCMTreeTableAncestors(tree)

or NULL.

X an optional k x N matrix with trait value vectors for each tip in tree.

returnList logical indicating if a list of the phylo object associated with the tree after drop-

ping the clade and the corresponding entries in X should be returned. Defaults

to !is.null(X)

errorOnMissing logical indicating if an error should be raised if cladeRootNode is not among the

nodes in tree. Default FALSE, meaning that if cladeRootNode is not a node in

tree the tree (and X if returnList is TRUE) is/are returned unchanged.

Value

If returnList is FALSE, a phylo object associated with the remaining tree after dropping the clade, otherise, a list with two named members :

tree the phylo object associated with the remaining tree after dropping the clade

X the submatrix of X with columns corresponding to the tips in the remaining tree

82 PCMTreeDtNodes

See Also

PCMTreeSpliAtNode PCMTreeExtractClade

Examples

```
set.seed(1, kind = "Mersenne-Twister", normal.kind = "Inversion")
tree <- PCMTree(ape::rtree(25))</pre>
PCMTreeSetPartRegimes(
  tree, c('26'="a", '28'="b", '45'="c"), setPartition = TRUE)
if(requireNamespace("ggtree"))
PCMTreePlot(tree, palette=c(a = "red", b = "green", c = "blue")) +
  ggtree::geom_nodelab(angle = 45) + ggtree::geom_tiplab(angle = 45)
redGreenTree <- PCMTreeDropClade(tree, 45)</pre>
PCMTreeGetPartRegimes(redGreenTree)
if(requireNamespace("ggtree"))
PCMTreePlot(redGreenTree, palette=c(a = "red", b = "green", c = "blue")) +
  ggtree::geom_nodelab(angle = 45) + ggtree::geom_tiplab(angle = 45)
# we need to use the label here, because the node 29 in tree is not the same
# id in redGreenTree:
redGreenTree2 <- PCMTreeDropClade(redGreenTree, "29")</pre>
if(requireNamespace("ggtree"))
PCMTreePlot(redGreenTree2, palette=c(a = "red", b = "green", c = "blue")) +
  ggtree::geom_nodelab(angle = 45) + ggtree::geom_tiplab(angle = 45)
```

PCMTreeDtNodes

A data.table with time, part and regime information for the nodes in a tree

Description

A data.table with time, part and regime information for the nodes in a tree

Usage

```
PCMTreeDtNodes(tree)
```

Arguments

tree

a phylo object with node-labels and parts

PCMTreeEdgeTimes 83

Value

a data.table with a row for each node in tree and columns as follows:

startNode the starting node of each edge or NA_integer_ for the root

endNode the end node of each edge or the root id for the root

startNodeLab the character label for the startNode

endNodeLab the character label for endNode

startTime the time (distance from the root node) for the startNode or NA_real_ for the root node

endTime the time (distance from the root node) for the endNode or NA_real_ for the root node

part the part to which the edge belongs, i.e. the part of the endNode

regime the regime to which the edge belongs, i.e. the regime of the part of the endNode

Examples

PCMTreeDtNodes(PCMBaseTestObjects\$tree.ab)

PCMTreeEdgeTimes

A matrix with the begin and end time from the root for each edge in tree

Description

A matrix with the begin and end time from the root for each edge in tree

Usage

PCMTreeEdgeTimes(tree)

Arguments

tree

a phylo

PCMTreeEvalNestedEDxOnTree

Perfrom nested extractions or drops of clades from a tree

Description

Perfrorm nested extractions or drops of clades from a tree

Usage

```
PCMTreeEvalNestedEDxOnTree(expr, tree)
```

Arguments

expr a character string representing an R expression of nested calls of functions E(x,node) denoting extracting the clade rooted at node from the tree x, or D(x,node), denoting dropping the clade rooted at node from the tree x. These calls can be nested, i.e. x can be either the symbol x (corresponding to the original tree passed as argument) or a nested call to d or e.

tree a phylo object with named tips and internal nodes

Value

the resulting phylo object from evaluating expr on tree.

```
set.seed(1, kind = "Mersenne-Twister", normal.kind = "Inversion")
tree <- PCMTree(ape::rtree(25))</pre>
PCMTreeSetPartRegimes(
  tree, c('26'="a", '28'="b", '45'="c", '47'="d"), setPartition = TRUE)
if(requireNamespace("ggtree"))
PCMTreePlot(
  tree, palette=c(a = "red", b = "green", c = "blue", d = "magenta")) +
  ggtree::geom_nodelab(angle = 45) + ggtree::geom_tiplab(angle = 45)
bluePart <- PCMTreeEvalNestedEDxOnTree("D(E(tree, 45), 47)", tree)</pre>
PCMTreeGetPartRegimes(bluePart)
if(requireNamespace("ggtree"))
PCMTreePlot(
  bluePart, palette=c(a = "red", b = "green", c = "blue", d = "magenta")) +
  ggtree::geom_nodelab(angle = 45) + ggtree::geom_tiplab(angle = 45)
# Swapping the D and E calls has the same result:
bluePart2 <- PCMTreeEvalNestedEDxOnTree("E(D(tree, 47), 45)", tree)</pre>
PCMTreeGetPartRegimes(bluePart2)
```

PCMTreeExtractClade 85

```
if(requireNamespace("ggtree"))
PCMTreePlot(
 bluePart2, palette=c(a = "red", b = "green", c = "blue", d = "magenta")) +
 ggtree::geom_nodelab(angle = 45) + ggtree::geom_tiplab(angle = 45)
greenPart <- PCMTreeEvalNestedEDxOnTree("E(tree,28)", tree)</pre>
bgParts <- bluePart+greenPart
if(requireNamespace("ggtree")) {
PCMTreePlot(
 greenPart, palette=c(a = "red", b = "green", c = "blue", d = "magenta")) +
 ggtree::geom_nodelab(angle = 45) + ggtree::geom_tiplab(angle = 45)
PCMTreePlot(
 bluePart + greenPart, palette=c(a = "red", b = "green", c = "blue", d = "magenta")) +
 ggtree::geom_nodelab(angle = 45) + ggtree::geom_tiplab(angle = 45)
 greenPart + bluePart, palette=c(a = "red", b = "green", c = "blue", d = "magenta")) +
 ggtree::geom_nodelab(angle = 45) + ggtree::geom_tiplab(angle = 45)
PCMTreePlot(
 bgParts, palette=c(a = "red", b = "green", c = "blue", d = "magenta")) +
 ggtree::geom_nodelab(angle = 45) + ggtree::geom_tiplab(angle = 45)
}
```

PCMTreeExtractClade

Extract a clade from phylogenetic tree

Description

Extract a clade from phylogenetic tree

Usage

```
PCMTreeExtractClade(
   tree,
   cladeRootNode,
   tableAncestors = NULL,
   X = NULL,
   returnList = !is.null(X)
)
```

Arguments

```
tree a PCMTree object.

cladeRootNode a character string denoting the label or an integer denoting a node in the tree.

tableAncestors an integer matrix returned by a previous call to PCMTreeTableAncestors(tree)
```

or NULL.

X an optional k x N matrix with trait value vectors for each tip in tree.

returnList logical indicating if only the phylo object associated with the clade should be

returned. Defaults to !is.null(X)

Value

If returnList is FALSE, a phylo object associated with the clade, otherwise, a list with two named members:

tree the phylo object associated with the clade

X the submatrix of X with columns corresponding to the tips in the clade

See Also

PCMTreeSpliAtNode PCMTreeDropClade

Examples

```
set.seed(1, kind = "Mersenne-Twister", normal.kind = "Inversion")
tree <- PCMTree(ape::rtree(25))</pre>
PCMTreeSetPartRegimes(
  tree, c('26'="a", '28'="b", '45'="c"), setPartition = TRUE)
if(requireNamespace("ggtree"))
PCMTreePlot(tree, palette=c(a = "red", b = "green", c = "blue")) +
  ggtree::geom_nodelab(angle = 45) + ggtree::geom_tiplab(angle = 45)
blueTree <- PCMTreeExtractClade(tree, 45)</pre>
PCMTreeGetPartRegimes(blueTree)
if(requireNamespace("ggtree"))
PCMTreePlot(blueTree, palette=c(a = "red", b = "green", c = "blue")) +
  ggtree::geom_nodelab(angle = 45) + ggtree::geom_tiplab(angle = 45)
# we need to use the label here, because the node 29 in tree is not the same
# id in redGreenTree:
blueTree2 <- PCMTreeDropClade(blueTree, "48")</pre>
if(requireNamespace("ggtree"))
PCMTreePlot(blueTree2, palette=c(a = "red", b = "green", c = "blue")) +
  ggtree::geom_nodelab(angle = 45) + ggtree::geom_tiplab(angle = 45)
```

 ${\tt PCMTreeGetBranchLength}$

The length of the branch leading to a node

Description

The length of the branch leading to a node

PCMTreeGetDaughters 87

Usage

PCMTreeGetBranchLength(tree, daughterId)

Arguments

tree a phylo object.

daughterId an integer denoting the id of a daughter node

Value

a double denoting the length of the branch leading to daughterId

PCMTreeGetDaughters

A vector of the daughter nodes for a given parent node id in a tree

Description

A vector of the daughter nodes for a given parent node id in a tree

Usage

PCMTreeGetDaughters(tree, parentId)

Arguments

tree a phylo object.

parentId an integer denoting the id of the parent node

Value

an integer vector of the direct descendants of parentId

PCMTreeGetLabels

Node labels of a tree

Description

Get the character labels of the tips, root and internal nodes in the tree (see Functions below).

Usage

```
PCMTreeGetLabels(tree)
```

PCMTreeGetRootLabel(tree)

PCMTreeGetNodeLabels(tree)

PCMTreeGetTipLabels(tree)

88 PCMTreeGetParent

Arguments

tree a phylo object

Value

a character vector

Functions

• PCMTreeGetLabels: Get all labels in the order (tips,root,internal).

• PCMTreeGetRootLabel: Get the root label

• PCMTreeGetNodeLabels: Get the internal node labels

• PCMTreeGetTipLabels: Get the tip labels

PCMTreeGetParent

The parent node id of a daughter node in a tree

Description

The parent node id of a daughter node in a tree

Usage

PCMTreeGetParent(tree, daughterId)

Arguments

tree a phylo object.

daughterId an integer denoting the id of the daughter node

Value

an integer denoting the parent of daughterId

PCMTreeGetPartition 89

PCMTreeGetPartition Get the starting branch' nodes for each part on a tree

Description

Get the starting branch' nodes for each part on a tree

Usage

```
PCMTreeGetPartition(tree)
```

Arguments

tree

a phylo object with an edge.part member denoting parts. The function assumes that each part covers a linked set of branches on the tree.

Details

We call a starting branch the first branch from the root to the tips of a given part. A starting node is the node at which a starting branch ends.

Value

a named integer vector with elements equal to the starting nodes for each part in tree and names equal to the labels of these nodes.

See Also

```
PCMTreeSetPartition
```

Examples

```
set.seed(1, kind = "Mersenne-Twister", normal.kind = "Inversion")
PCMTreeGetPartition(PCMTree(ape::rtree(20)))
```

 ${\tt PCMTreeGetPartNames}$

Unique parts on a tree in the order of occurrence from the root to the tips (preorder)

Description

Unique parts on a tree in the order of occurrence from the root to the tips (preorder)

Usage

```
PCMTreeGetPartNames(tree)
```

Arguments

tree a phylo object with an additional member edge.part which should be a character

or an integer vector of length equal to the number of branches.

Value

a character vector.

PCMTreeGetPartRegimes Regime mapping for the parts in a tree

Description

Regime mapping for the parts in a tree

Usage

PCMTreeGetPartRegimes(tree)

Arguments

tree a PCMTree or a phylo object.

Value

a named vector with names corresponding to the part names in tree and values corresponding to regime names or ids.

PCMTreeGetPartsForNodes

Get the parts of the branches leading to a set of nodes or tips

Description

Get the parts of the branches leading to a set of nodes or tips

Usage

PCMTreeGetPartsForNodes(tree, nodes = seq_len(PCMTreeNumNodes(tree)))

Arguments

tree a phylo object with an edge.part member denoting parts.

nodes an integer vector denoting the nodes. Default is seq_len(PCMTreeNumNodes(tree).

Value

a character vector denoting the parts of the branches leading to the nodes, according to tree\$edge.part.

 ${\tt PCMTreeGetRegimesForEdges}$

Model regimes (i.e. colors) associated with the branches in a tree

Description

Model regimes (i.e. colors) associated with the branches in a tree

Usage

PCMTreeGetRegimesForEdges(tree)

Arguments

tree

a PCMTree or a phylo object.

Value

a vector with entries corresponding to the rows in tree\$edge denoting the regime associated with each branch in the tree. The type of the vector element is defined by the type of tree\$part.regime.

 ${\tt PCMTreeGetRegimesForNodes}$

Get the regimes of the branches leading to a set of nodes or tips

Description

Get the regimes of the branches leading to a set of nodes or tips

Usage

```
PCMTreeGetRegimesForNodes(tree, nodes = seq_len(PCMTreeNumNodes(tree)))
```

Arguments

tree a phylo object with an edge.part member denoting parts.

nodes an integer vector denoting the nodes. Default is seq_len(PCMTreeNumNodes(tree).

Value

a character vector denoting the parts of the branches leading to the nodes, according to tree\$edge.part.

PCMTreeGetTipsInPart Get the tips belonging to a part in a tree

Description

Get the tips belonging to a part in a tree

Usage

```
PCMTreeGetTipsInPart(tree, part)
```

Arguments

tree a phylo object with an edge.regime member or a PCMTree object

part a character or integer denoting a part name in the tree.

Value

an integer vector with the ids of the tips belonging to part

See Also

PCMTreeGetTipsInRegime, PCMTreeGetPartNames, PCMRegimes, PCMTreeGetPartRegimes, PCMTreeSet-PartRegimes

```
set.seed(1, kind = "Mersenne-Twister", normal.kind = "Inversion")
tree <- ape::rtree(10)
regimes <- sample(letters[1:3], nrow(tree$edge), replace = TRUE)
PCMTreeSetRegimesForEdges(tree, regimes)

if(requireNamespace("ggtree"))
PCMTreePlot(tree) + ggtree::geom_nodelab() + ggtree::geom_tiplab()

part <- PCMTreeGetPartNames(tree)[1]
PCMTreeGetTipsInPart(tree, part)
print(part)</pre>
```

PCMTreeGetTipsInRegime

Get the tips belonging to a regime in a tree

Description

Get the tips belonging to a regime in a tree

Usage

```
PCMTreeGetTipsInRegime(tree, regime)
```

Arguments

tree a phylo object with an edge.regime member or a PCMTree object

regime a character or integer denoting a regime in the tree.

Value

an integer vector with the ids of the tips belonging to regime.

See Also

PCMTreeGetTipsInPart, PCMTreeGetPartNames, PCMRegimes, PCMTreeGetPartRegimes, PCMTreeSetPartRegimes, PCMTreeGetPartition

```
set.seed(1, kind = "Mersenne-Twister", normal.kind = "Inversion")
tree <- ape::rtree(10)
regimes <- sample(letters[1:3], nrow(tree$edge), replace = TRUE)
PCMTreeSetRegimesForEdges(tree, regimes)

if(requireNamespace("ggtree"))
PCMTreePlot(tree) + ggtree::geom_nodelab() + ggtree::geom_tiplab()

regime <- PCMRegimes(tree)[1]
PCMTreeGetTipsInRegime(tree, regime)
print(regime)</pre>
```

PCMTreeInsertSingletons

Insert tips or singleton nodes on chosen edges

Description

Insert tips or singleton nodes on chosen edges

Usage

```
PCMTreeInsertSingletons(tree, nodes, positions)

PCMTreeInsertSingletonsAtEpoch(tree, epoch, minLength = 0.1)

PCMTreeInsertTipsOrSingletons(
    tree,
    nodes,
    positions = rep(0, length(nodes)),
    singleton = FALSE,
    tipBranchLengths = 0.01,
    nodeLabels = NULL,
    tipLabels = NULL
)
```

Arguments

tree	a	phy	vlo.	obi	iect

nodes an integer vector denoting the terminating nodes of the edges on which a sin-

gleton node is to be inserted. This vector should not have duplicated nodes - if there is a need to insert two or more singleton nodes at distinct positions of the same edge, this should be done by calling the function several times with the

longest position first and so on.

positions a positive numeric vector of the same length as nodes denoting the root-ward

distances from nodes at which the singleton nodes should be inserted. For PCMTreeInsertTipsOrSingletons this can contains 0's and is set by default to

rep(0, length(nodes)).

epoch a numeric indicating a distance from the root at which a singleton node should

be inserted in all lineages that are alive at that time.

minLength a numeric indicating the minimum allowed branch-length after dividing a branch

by insertion of a singleton nodes. No singleton node is inserted if this would result in a branch shorter than 'minLength'. Note that this condition is checked

only in 'PCMTreeInsertSingletonsAtEpoch'.

singleton (PCMTreeInsertTipsOrSingletons only) a logical indicating if a singleton node

should be inserted and no tip node should be inserted.

tipBranchLengths

(PCMTreeInsertTipsOrSingletons only) positive numeric vector of the length of nodes, denoting the lengths of the new edges leading to tips.

nodeLabels

(PCMTreeInsertSingletons and PCMTreeInsertTipsOrSingletons) a character vector of the same length as nodes, indicating the names of the newly inserted nodes. These names are ignored where positions is 0. This argument is optional and default node labels will be assigned if this is not specified or set to NULL. If specified, then it should not contain node-labels already present in the tree.

tipLabels

(PCMTreeInsertTipsOrSingletons only) a character vector of the same length as nodes of the new tip-labels. This argument is optional and default tip labels will be assigned if this is not specified or set to NULL. If specified, then it should not contain tip-labels already present in the tree.

Value

a modified copy of tree.

Functions

- PCMTreeInsertSingletonsAtEpoch:
- PCMTreeInsertTipsOrSingletons:

See Also

PCMTreeEdgeTimes PCMTreeLocateEpochOnBranches PCMTreeLocateMidpointsOnBranches

```
set.seed(1, kind = "Mersenne-Twister", normal.kind = "Inversion")
tree <- PCMTree(ape::rtree(25))</pre>
PCMTreeSetPartRegimes(
  tree, c('26'="a", '28'="b", '45'="c", '47'="d"), setPartition = TRUE)
if(requireNamespace("ggtree"))
PCMTreePlot(
  tree.
  palette=c(a = "red", b = "green", c = "blue", d = "magenta")) +
  ggtree::geom_nodelab(angle = 45) + ggtree::geom_tiplab(angle = 45)
cbind(tree$edge, PCMTreeEdgeTimes(tree))
id47 <- PCMTreeMatchLabels(tree, "47")</pre>
length47 <- PCMTreeGetBranchLength(tree, id47)</pre>
# insert a singleton at 0.55 (root-ward) from node 47
tree <- PCMTreeInsertSingletons(tree, nodes = "47", positions = (length47/2))
if(requireNamespace("ggtree"))
PCMTreePlot(
```

96 PCMTreeJumps

```
palette=c(a = "red", b = "green", c = "blue", d = "magenta")) +
  ggtree::geom_nodelab(angle = 45) + ggtree::geom_tiplab(angle = 45)
# this fails, because the branch leading to node "47" is shorter now (0.55).
ggplot2::should_stop(
  tree <- PCMTreeInsertSingletons(</pre>
    tree, nodes = "47", positions= 2* length47 / 3))
# the tree is the same
if(requireNamespace("ggtree"))
PCMTreePlot(
  tree, palette=c(a = "red", b = "green", c = "blue", d = "magenta")) +
  ggtree::geom_nodelab(angle = 45) + ggtree::geom_tiplab(angle = 45)
# we can insert at a position within the edge:
tree <- PCMTreeInsertSingletons(tree, nodes = "47", positions = length47/3)</pre>
if(requireNamespace("ggtree"))
PCMTreePlot(
  tree, palette=c(a = "red", b = "green", c = "blue", d = "magenta")) +
  ggtree::geom_nodelab(angle = 45) + ggtree::geom_tiplab(angle = 45)
# Insert singletons at all branches crossing a given epoch. This will skip
# inserting singleton nodes where the resulting branches would be shorter
tree <- PCMTreeInsertSingletonsAtEpoch(tree, 2.3)</pre>
if(requireNamespace("ggtree"))
PCMTreePlot(
  tree, palette=c(a = "red", b = "green", c = "blue", d = "magenta")) +
  ggtree::geom_nodelab(angle = 45) + ggtree::geom_tiplab(angle = 45)
# Insert singletons at all branches crossing a given epoch
tree <- PCMTreeInsertSingletonsAtEpoch(tree, 2.3, minLength = 0.001)</pre>
if(requireNamespace("ggtree"))
PCMTreePlot(
  palette=c(a = "red", b = "green", c = "blue", d = "magenta")) +
  ggtree::geom_nodelab(angle = 45) + ggtree::geom_tiplab(angle = 45)
```

PCMTreeJumps

Jumps in modeled traits associated with branches in a tree

Description

Jumps in modeled traits associated with branches in a tree

PCMTreeListAllPartitions 97

Usage

```
PCMTreeJumps(tree)
```

Arguments

tree a phylo object

Value

an integer vector of 0's and 1's with entries corresponding to the denoting if a jump took place at the beginning of a branch.

PCMTreeListAllPartitions

A list of all possible (including recursive) partitions of a tree

Description

A list of all possible (including recursive) partitions of a tree

Usage

```
PCMTreeListAllPartitions(
   tree,
   minCladeSize,
   skipNodes = character(),
   tableAncestors = NULL,
   verbose = FALSE
)
```

Arguments

tree a phylo object with set labels for the internal nodes

minCladeSize integer indicating the minimum number of tips allowed in one part.

skipNodes an integer or character vector indicating the ids or labels of nodes that should

not be used as partition nodes. By default, this is an empty character vector.

tableAncestors NULL (default) or an integer matrix returned by a previous call to PCMTreeTableAncestors(tree).

verbose a logical indicating if informative messages should be printed to the console.

Value

a list of integer vectors.

Examples

```
set.seed(1, kind = "Mersenne-Twister", normal.kind = "Inversion")
tree <- PCMTree(ape::rtree(10))

if(requireNamespace("ggtree"))
PCMTreePlot(tree) + ggtree::geom_nodelab() + ggtree::geom_tiplab()

# list of all partitions into parts of at least 4 tips
PCMTreeListAllPartitions(tree, 4)

# list of all partitions into parts of at least 3 tips
PCMTreeListAllPartitions(tree, 3)

# list all partitions into parts of at least 3 tips, excluding the partitions
# where node 16 is one of the partition nodes:
PCMTreeListAllPartitions(tree, minCladeSize = 3, skipNodes = "16")</pre>
```

PCMTreeListCladePartitions

A list of all possible clade partitions of a tree with a number of splitting nodes

Description

Each subset of nNodes distinct internal or tip nodes defines a partition of the branches of the tree into nNodes+1 blocks called parts. This function generates partitions where each part has nNodes splitting nodes and contains at least minCladeSize tips.

Usage

```
PCMTreeListCladePartitions(
    tree,
    nNodes,
    minCladeSize = 0,
    skipNodes = character(0),
    tableAncestors = NULL,
    countOnly = FALSE,
    verbose = FALSE
)
```

Arguments

tree a phylo object

nNodes an integer giving the number of partitioning nodes. There would be nNodes+1

blocks in each partition (see details).

minCladeSize integer indicating the minimum number of tips allowed in a clade.

PCMTreeListDescendants 99

skipNodes an integer or character vector indicating the ids or labels of nodes that should

not be used as partition nodes. By default, this is an empty character vector.

tableAncestors NULL (default) or an integer matrix returned by a previous call to PCMTreeTableAncestors(tree).

countOnly logical indicating if the only the number of partitions should be returned.

verbose a logical indicating if informative messages should be printed to the console.

Value

a list of integer nNodes-vectors. By default a full traversal of all partitions is done. It is possible to truncate the search to a limited number of partitions by setting the option PCMBase.MaxLengthListCladePartitions to a finite positive integer.

See Also

PCMOptions

PCMTreeListDescendants

A list of the descendants for each node in a tree

Description

A list of the descendants for each node in a tree

Usage

PCMTreeListDescendants(tree, tableAncestors = PCMTreeTableAncestors(tree))

Arguments

tree a phylo object

tableAncestors an integer matrix resulting from a call to PCMTreeTableAncestors(tree).

Details

This function has time and memory complexity O(M^2), where M is the number of nodes in the tree. It can take several minutes and gigabytes of memory on trees of more than 10000 tips.

Value

a list with unnamed elements in the order of nodes in the tree. Each element is an integer vector containing the descendant nodes (in increasing order) of the node identified by its index-number in the list.

PCMTreeListRootPaths A list of the path to the root from each node in a tree

Description

A list of the path to the root from each node in a tree

Usage

```
PCMTreeListRootPaths(tree, tableAncestors = PCMTreeTableAncestors(tree))
```

Arguments

tree a phylo object

tableAncestors an integer matrix resulting from a call to PCMTreeTableAncestors(tree).

Details

This function has time and memory complexity O(M^2), where M is the number of nodes in the tree. It can take several minutes and gigabytes of memory on trees of more than 10000 tips.

Value

a list with unnamed elements in the order of nodes in the tree. Each element is an integer vector containing the ancestors nodes on the path from the node (i) to the root of the tree in that order (the first element in the vector is the parent node of i and so on).

PCMTreeLocateEpochOnBranches

Find the crossing points of an epoch-time with each lineage of a tree

Description

Find the crossing points of an epoch-time with each lineage of a tree

Usage

PCMTreeLocateEpochOnBranches(tree, epoch)

Arguments

tree a phylo

epoch a positive numeric indicating tip-ward distance from the root

Value

a named list with an integer vector element "nodes" denoting the ending nodes for each branch crossing epoch and numeric vector element "positions" denoting the root-ward offset from each node in nodes.

PCMTreeLocateMidpointsOnBranches

Find the middle point of each branch longer than a threshold

Description

Find the middle point of each branch longer than a threshold

Usage

PCMTreeLocateMidpointsOnBranches(tree, threshold = 0)

Arguments

tree a phylo

threshold a positive numeric; only branches longer than threshold will be returned; Default

0.

Value

a named list with an integer vector element "nodes" denoting the ending nodes for each branch crossing epoch and numeric vector element "positions" denoting the root-ward offset from each node in nodes.

PCMTreeMatchLabels

Get the node numbers associated with tip- or node-labels in a tree

Description

Get the node numbers associated with tip- or node-labels in a tree

Usage

```
PCMTreeMatchLabels(tree, labels, stopIfNotFound = TRUE)
```

Arguments

tree a phylo object

labels a character vector with valid tip or node labels from tree

stopIfNotFound logical indicating if an error should be raised in case a label has not been found

in the tree labels. Default: TRUE

Value

an integer vector giving the tip- or node- integer indices corresponding to labels. If stopIfNotFound is set to FALSE, this vector may contain NAs for the labels that were not found.

Examples

```
set.seed(1, kind = "Mersenne-Twister", normal.kind = "Inversion")
PCMTreeMatchLabels(PCMTree(ape::rtree(20)), c("t1", "t15", "21", "39"))
PCMTreeMatchLabels(PCMTree(ape::rtree(20)), c("t1", "45"), stopIfNotFound = FALSE)
```

PCMTreeMatrixNodesInSamePart

Which couples from a given set of nodes in a tree belong to the same part?

Description

Which couples from a given set of nodes in a tree belong to the same part?

Which couples from a given set of nodes in a tree belong to the same regime?

Usage

```
PCMTreeMatrixNodesInSamePart(
    tree,
    nodes = seq_len(PCMTreeNumNodes(tree)),
    upperTriangle = TRUE,
    returnVector = TRUE
)

PCMTreeMatrixNodesInSameRegime(
    tree,
    nodes = seq_len(PCMTreeNumNodes(tree)),
    upperTriangle = TRUE,
    returnVector = TRUE
)
```

Arguments

tree a PCMTree object or a phylo object.

nodes an integer vector of length $L \ge 2$ denoting a set of nodes in the tree.

upperTriangle logical indicating if all duplicated entries and diagonal entries should be set to

NA (by default TRUE).

returnVector logical indicating if a vector instead of a matrix should be returned (correspond-

ing to calling as vector on the resulting matrix and removing NAs). Default:

TRUE

Value

- a L x L logical matrix with TRUE on the diagonal and for each couple of tips that belong to the same part or regime. If returnVector is TRUE (default) only a vector of the non-NA entries will be returned.
- a L x L logical matrix with TRUE on the diagonal and for each couple of tips that belong to the same part or regime. If returnVector is TRUE (default) only a vector of the non-NA entries will be returned.

Examples

```
set.seed(1, kind = "Mersenne-Twister", normal.kind = "Inversion")
tree <- PCMTree(ape::rtree(8))</pre>
PCMTreeMatrixNodesInSamePart(tree, returnVector = FALSE)
PCMTreeSetPartition(tree, c(10, 12))
PCMTreeMatrixNodesInSamePart(tree, returnVector = FALSE)
PCMTreeMatrixNodesInSamePart(tree)
PCMTreeMatrixNodesInSamePart(tree, seq_len(PCMTreeNumTips(tree)))
PCMTreeMatrixNodesInSamePart(
  tree, seq_len(PCMTreeNumTips(tree)), returnVector = FALSE)
set.seed(1, kind = "Mersenne-Twister", normal.kind = "Inversion")
tree <- PCMTree(ape::rtree(8))</pre>
PCMTreeMatrixNodesInSamePart(tree, returnVector = FALSE)
PCMTreeSetPartition(tree, c(10, 12))
PCMTreeMatrixNodesInSamePart(tree, returnVector = FALSE)
PCMTreeMatrixNodesInSamePart(tree)
PCMTreeMatrixNodesInSamePart(tree, seq_len(PCMTreeNumTips(tree)))
PCMTreeMatrixNodesInSamePart(
  tree, seq_len(PCMTreeNumTips(tree)), returnVector = FALSE)
```

PCMTreeNearestNodesToEpoch

Find the nearest node to a given time from the root (epoch) on each lineage crossing this epoch

Description

Find the nearest node to a given time from the root (epoch) on each lineage crossing this epoch

Usage

PCMTreeNearestNodesToEpoch(tree, epoch)

104 PCMTreeNumNodes

Arguments

tree a phylo

epoch a non-negative numeric

Value

an integer vector

PCMTreeNodeTimes

Calculate the time from the root to each node of the tree

Description

Calculate the time from the root to each node of the tree

Usage

```
PCMTreeNodeTimes(tree, tipsOnly = FALSE)
```

Arguments

tree an object of class phylo

tipsOnly Logical indicating whether the returned results should be truncated only to the

tips of the tree.

Value

A vector of size the number of nodes in the tree (tips, root, internal) containing the time from the root to the corresponding node in the tree.

PCMTreeNumNodes

Number of all nodes in a tree

Description

Number of all nodes in a tree

Usage

PCMTreeNumNodes(tree)

Arguments

tree a phylo object

PCMTreeNumParts 105

Details

Wrapper for nrow(tree\$edge) + 1

Value

the number of nodes in tree including root, internal and tips.

PCMTreeNumParts

Number of unique parts on a tree

Description

Number of unique parts on a tree

Usage

PCMTreeNumParts(tree)

Arguments

tree

a phylo object

Value

the number of different parts encountered on the tree branches

PCMTreeNumTips

Wrapper for length(tree\$tip.label)

Description

Wrapper for length(tree\$tip.label)

Usage

PCMTreeNumTips(tree)

Arguments

tree

a phylo object

Value

the number of tips in tree

106 PCMTreePostorder

PCMTreePlot

Plot a tree with parts and regimes assigned to these parts

Description

Plot a tree with parts and regimes assigned to these parts

Usage

```
PCMTreePlot(
   tree,
   palette = PCMColorPalette(PCMNumRegimes(tree), PCMRegimes(tree)),
   ...
)
```

Arguments

tree a PCMTree or a phylo object.

palette a named vector of colors corresponding to the regimes in tree

... Arguments passed to ggtree, e.g. layout = 'fan', open.angle = 8, size=.25.

Note

This function requires that the ggtree package is installed. At the time of releasing this version the ggtree package is not available on CRAN. Check the ggtree homepage for instruction on how to install this package: .

PCMTreePostorder

Post-order tree traversal

Description

Post-order tree traversal

Usage

```
PCMTreePostorder(tree)
```

Arguments

tree

a phylo object with possible singleton nodes (i.e. internal nodes with one daughter node)

Value

a vector of indices of edges in tree\$edge in post-order.

PCMTreePreorder 107

ı		мт	re	۵D	ra	۸r	٨	۵.	r
	ᆫ	וויו	1 4	eг	1 0	10	(1)	-1	1

Pre-order tree traversal

Description

Pre-order tree traversal

Usage

```
PCMTreePreorder(tree)
```

Arguments

tree

a phylo object with possible singleton nodes (i.e. internal nodes with one daughter node)

Value

a vector of indices of edges in tree\$edge in pre-order.

PCMTreeSetLabels

Set tip and internal node labels in a tree

Description

Set tip and internal node labels in a tree

Usage

```
PCMTreeSetLabels(
   tree,
   labels = as.character(1:PCMTreeNumNodes(tree)),
   inplace = TRUE
)
```

Arguments

tree a phylo object or a PCMTree object. If this is a PCMTree object, the internal

edge.part and part.regime members will be updated accordingly.

labels a character vector in the order 1:PCMTreeNumNodes(tree) as denoted in the

tree\$edge matrix.

inplace a logical indicating if the change should be done in place on the object in the

calling environment (in this case tree must not be a temporary object, e.g. re-

turned by another function call). Default is TRUE.

108 PCMTreeSetPartition

Value

if inplace is FALSE, a copy of tree with set or modified tree\$tip.label and tree\$node.label. If the original tree has a member edge.part, the returned tree has tree\$edge.part and tree\$part.regime updated. If inplace is TRUE (the default), nothing is returned and the above changes are made directly on the input tree.

See Also

PCMTree

Examples

```
tree <- ape::rtree(5)</pre>
tree$tip.label
# the following three are NULLs
tree$node.label
tree$edge.part
tree$part.regime
tree <- PCMTree(tree)</pre>
PCMTreeSetPartition(tree, c(6, 8))
tree$tip.label
tree$node.label
tree$edge.part
tree$part.regime
PCMTreeSetLabels(
  tree, labels = paste0(c(rep("t", 5), rep("n", 4)), PCMTreeGetLabels(tree)))
PCMTreeGetLabels(tree)
tree$tip.label
tree$node.label
tree$edge.part
tree$part.regime
```

PCMTreeSetPartition Set a partition of a tree by specifying the partition nodes

Description

Set a partition of a tree by specifying the partition nodes

Usage

```
PCMTreeSetPartition(tree, nodes = c(PCMTreeNumTips(tree) + 1L), inplace = TRUE)
```

PCMTreeSetPartition 109

Arguments

tree a PCMTree object.

nodes a character vector containing tip or node labels or an integer vector denoting tip

or internal nodes in tree - the parts change at the start of the branches leading to

these nodes. Default: c(PCMTreeNumTips(tree) + 1L).

inplace a logical indicating if the change should be done to the tree in the calling en-

vironment (TRUE) or a copy of the tree with set edge.part member should be

returned (FALSE). Default is TRUE.

Value

If inplace is TRUE nothing, otherwise a copy of the tree with set edge.part member.

See Also

```
PCMTreeGetPartition PCMTree
```

```
set.seed(1, kind = "Mersenne-Twister", normal.kind = "Inversion")
tree <- PCMTree(ape::rtree(8))</pre>
PCMTreeSetLabels(tree, paste0("x", PCMTreeGetLabels(tree)))
PCMTreeGetPartition(tree)
PCMTreeGetPartNames(tree)
PCMTreeGetPartRegimes(tree)
if(requireNamespace("ggtree"))
PCMTreePlot(tree) + ggtree::geom_nodelab() + ggtree::geom_tiplab()
tree <- PCMTreeSetPartition(tree, c(12, 14), inplace = FALSE)</pre>
PCMTreeGetPartition(tree)
PCMTreeGetPartNames(tree)
PCMTreeGetPartRegimes(tree)
if(requireNamespace("ggtree"))
PCMTreePlot(tree) + ggtree::geom_nodelab() + ggtree::geom_tiplab()
# reset the partition to a default one, where there is only one part:
PCMTreeSetPartition(tree)
PCMTreeGetPartition(tree)
PCMTreeGetPartNames(tree)
PCMTreeGetPartRegimes(tree)
if(requireNamespace("ggtree"))
PCMTreePlot(tree) + ggtree::geom_nodelab() + ggtree::geom_tiplab()
# reset the labels to the default labels which are character representations
# of the node ids
```

PCMTreeSetLabels(tree)
PCMTreeGetPartition(tree)
PCMTreeGetPartNames(tree)
PCMTreeGetPartRegimes(tree)

PCMTreeSetPartRegimes Set regimes for the parts in a tree

Description

Set regimes for the parts in a tree

Usage

PCMTreeSetPartRegimes(tree, part.regime, setPartition = FALSE, inplace = TRUE)

Arguments

tree a PCMTree object.

part.regime a named vector containing regimes to be assigned to some of or to each of the

parts in the tree.

setPartition a logical indicating if the partition of the tree should be set as well. If this argu-

ment is set to TRUE, the names of part.regime are passed as the nodes argument

in a call to ${\tt PCMTreeSetPartition}.$ Default: FALSE.

inplace a logical indicating if the change should be done to the tree in the calling en-

vironment (TRUE) or a copy of the tree with set edge.part member should be

returned (FALSE). Default is TRUE.

Value

If inplace is TRUE nothing, otherwise a copy of the tree with set edge.part and part.regime members.

See Also

PCMTree

```
tree <- PCMTree(ape::rtree(25))
PCMTreeGetPartition(tree)
PCMTreeGetPartRegimes(tree)
PCMTreeGetPartNames(tree)

PCMTreeSetPartRegimes(tree, c(`26` = 2))
PCMTreeGetPartition(tree)
PCMTreeGetPartRegimes(tree)
PCMTreeGetPartNames(tree)</pre>
```

```
PCMTreeSetPartRegimes(tree, c('26' = "global-regime"))
PCMTreeGetPartition(tree)
PCMTreeGetPartRegimes(tree)
PCMTreeGetPartNames(tree)
# This should fail because no partition with nodes 26, 28 and 41 has been
ggplot2::should_stop(
  PCMTreeSetPartRegimes(tree, c('26' = "a", '28' = "b", '41' = "c")))
# This should succeed and change the partition as well as regime assignment
PCMTreeSetPartRegimes(
  tree, c('26' = "a", '28' = "b", '41' = "c"), setPartition = TRUE)
PCMTreeGetPartition(tree)
PCMTreeGetPartRegimes(tree)
PCMTreeGetPartNames(tree)
set.seed(1, kind = "Mersenne-Twister", normal.kind = "Inversion")
# number of tips
N <- 40
# tree with one regime
tree.a <- ape::rtree(N)</pre>
tree.a <- PCMTree(tree.a)</pre>
PCMTreeSetPartRegimes(
  tree.a.
  part.regime = structure("a", names = as.character(N+1L)),
  setPartition = TRUE,
  inplace = TRUE)
if(requireNamespace("ggtree"))
PCMTreePlot(tree.a) + ggtree::geom_nodelab() + ggtree::geom_tiplab()
tree.ab <- tree.a
PCMTreeSetPartRegimes(
  tree.ab,
  part.regime = structure(c("a", "b"), names = as.character(c(N+1L, N+31L))),
  setPartition = TRUE,
  inplace = TRUE)
if(requireNamespace("ggtree"))
PCMTreePlot(tree.ab) + ggtree::geom_nodelab() + ggtree::geom_tiplab()
```

PCMTreeSetRegimesForEdges

Set the regime for each individual edge in a tree explicitly

Description

Set the regime for each individual edge in a tree explicitly

Usage

```
PCMTreeSetRegimesForEdges(tree, regimes, inplace = TRUE)
```

Arguments

tree a PCMTree or a phylo object.

regimes a vector of the length equal to 'nrow(tree\$edge)'.

inplace a logical indicating if the change should be done within the tree in the calling

environment or a copy of the tree with modified regime assignment should be

returned.

Value

if inplace is TRUE, nothing, otherwise a modified copy of tree.

Note

Calling this function overwrites the current partitioning of the tree.

```
set.seed(1, kind = "Mersenne-Twister", normal.kind = "Inversion")
tree <- ape::rtree(10)
regimes <- sample(letters[1:3], nrow(tree$edge), replace = TRUE)
PCMTreeSetRegimesForEdges(tree, regimes)

if(requireNamespace("ggtree"))
PCMTreePlot(tree)</pre>
```

PCMTreeSplitAtNode 113

PCMTreeSplitAtNode	Slit a tree at a given internal node into a clade rooted at this node and
	the remaining tree after dropping this clade

Description

Slit a tree at a given internal node into a clade rooted at this node and the remaining tree after dropping this clade

Usage

```
PCMTreeSplitAtNode(
   tree,
   node,
   tableAncestors = PCMTreeTableAncestors(tree),
   X = NULL
)
```

Arguments

```
tree a PCMTree object.

node an integer or character indicating a root, internal or tip node

tableAncestors an integer matrix returned by a previous call to PCMTreeTableAncestors(tree) or NULL.

X an optional k \times N matrix with trait value vectors for each tip in tree.
```

Details

In the current implementation, the edge.jump and edge.part members of the tree will be discarded and not present in the clade.

Value

A list containing two named phylo objects:

```
clade The subtree (clade) starting at node.
```

Xclade The portion of X attributable to the tips in clade; NULL if X is NULL.

rest The tree resulting after dropping all tips in the clade.

Xrest The portion of X attributable to the tips in rest; NULL if X is NULL.

114 PCMTreeTableAncestors

Examples

```
set.seed(1, kind = "Mersenne-Twister", normal.kind = "Inversion")
tree <- PCMTree(ape::rtree(25))

if(requireNamespace("ggtree"))
PCMTreePlot(tree) + ggtree::geom_nodelab(angle = 45) +
    ggtree::geom_tiplab(angle = 45)

spl <- PCMTreeSplitAtNode(tree, 28)

if(requireNamespace("ggtree"))
PCMTreePlot(PCMTree(spl$clade)) + ggtree::geom_nodelab(angle = 45) +
    ggtree::geom_tiplab(angle = 45)

if(requireNamespace("ggtree"))
PCMTreePlot(PCMTree(spl$rest)) + ggtree::geom_nodelab(angle = 45) +
    ggtree::geom_tiplab(angle = 45)</pre>
```

PCMTreeTableAncestors A matrix (table) of ancestors/descendants for each node in a tree

Description

A matrix (table) of ancestors/descendants for each node in a tree

Usage

```
PCMTreeTableAncestors(tree, preorder = PCMTreePreorder(tree))
```

Arguments

tree a phylo object

preorder an integer vector returned by a previous call to PCMTreePreorder(tree). De-

fault PCMTreePreorder(tree).

Details

This function has time and memory complexity O(M^2), where M is the number of nodes in the tree. It can take several minutes and gigabytes of memory on trees of more than 10000 tips.

Value

an integer square matrix of size $M \times M$ where M is the number of nodes in the tree. Element j on row i is 0 if j is not an ancestor of i or a positive integer equal to the position of j on the path from the root to i if j is an ancestor of i.

PCMTreeToString 115

PCMTreeToString

A character representation of a phylo object.

Description

A character representation of a phylo object.

Usage

```
PCMTreeToString(tree, includeLengths = FALSE, includePartition = FALSE)
```

Arguments

tree a phylo object.

includeLengths logical. Default: FALSE.
includePartition logical. Default: FALSE.

Value

a character string.

PCMTreeVCV

Phylogenetic Variance-covariance matrix

Description

This is a simplified wrapper for ape's vcv function. Setting the runtime option PCMBase.UsePCMVarForVCV to TRUE will switch to a computation of the matrix using the function PCMVar.

Usage

```
PCMTreeVCV(tree)
```

Arguments

tree

a phylo object

Value

a N x N matrix. Assuming a BM model of evolution, this is a matrix in which element (i,j) is equal to the shared root-distance of the nodes i and j.

See Also

vcv PCMVar PCMOptions

PCMVar

PCMUnfixParameter

Unfix a parameter in a PCM model

Description

Unfix a parameter in a PCM model

Usage

```
PCMUnfixParameter(model, name)
```

Arguments

model a PCM object
name a character string

Value

a copy of the model with removed class '_Fixed' from the class of the parameter name

PCMVar

Expected variance-covariance matrix for each couple of tips (i,j)

Description

Expected variance-covariance matrix for each couple of tips (i,j)

Usage

```
PCMVar(
    tree,
    model,
    W0 = matrix(0, PCMNumTraits(model), PCMNumTraits(model)),
    SE = matrix(0, PCMNumTraits(model), PCMTreeNumTips(tree)),
    metaI = PCMInfo(NULL, tree, model, verbose = verbose),
    internal = FALSE,
    diagOnly = FALSE,
    verbose = FALSE
)
```

PCMVar 117

Arguments

tree	a phylo object with N tips.
model	an S3 object specifying both, the model type (class, e.g. "OU") as well as the concrete model parameter values at which the likelihood is to be calculated (see also Details).
W0	a numeric matrix denoting the initial $k \times k$ variance covariance matrix at the root (default is the $k \times k$ zero matrix).
SE	a k x N matrix specifying the standard error for each measurement in X. Alternatively, a k x k x N cube specifying an upper triangular k x k factor of the variance covariance matrix for the measurement error for each tip i=1,, N. When SE is a matrix, the k x k measurement error variance matrix for a tip i is calculated as VE[, , i] <- diag(SE[, i] * SE[, i], nrow = k). When SE is a cube, the way how the measurement variance matrix for a tip i is calculated depends on the runtime option PCMBase.Transpose.Sigma_x as follows:
	$\label{eq:continuous_sigma_x} \begin{split} \textbf{if} \ & \text{getOption("PCMBase.Transpose.Sigma_x", FALSE)} == \text{FALSE} \ (\textbf{default):} \\ & \text{VE}[,,i] <- \text{SE}[,,i] \ \%*\% \ t(\text{SE}[,,i]) \\ \textbf{if} \ & \text{getOption("PCMBase.Transpose.Sigma_x", FALSE)} == \text{TRUE:} \ \text{VE}[,,i] <- \\ & \text{t(SE}[,,i]) \ \%*\% \ \text{SE}[,,i] \end{split}$
	Note that the above behavior is consistent with the treatment of the model parameters Sigma_x, Sigmae_x and Sigmaj_x, which are also specified as upper triangular factors. Default: matrix(0.0, PCMNumTraits(model), PCMTreeNumTips(tree)).
metaI	a list returned from a call to PCMInfo(X, tree, model, SE), containing metadata such as N, M and k. Alternatively, this can be a character string naming a function or a function object that returns such a list, e.g. the functionPCMInfo or the function PCMInfoCpp from the PCMBaseCpp package.
internal	a logical indicating if the per-node variance-covariances matrices for the internal

internal

a logical indicating if the per-node variance-covariances matrices for the internal

nodes should be returned (see Value). Default FALSE.

diagOnly

a logical indicating if only the variance blocks for the nodes should be calculated. By default this is set to FALSE, meaning that the co-variances are calcu-

lated for all couples of nodes.

verbose

logical indicating if some debug-messages should printed.

Value

If internal is FALSE, a (k x N) x (k x N) matrix W, such that k x k block W[((i-1)*k)+(1:k), ((j-1)*k)+(1:k)] equals the expected covariance matrix between tips i and j. Otherwise, a list with an element 'W' as described above and a k x M matrix element 'Wii' containing the per-node variance covariance matrix for each node: The k x k block Wii[, (i-1)*k + (1:k)] represents the variance covariance matrix for node i.

```
# a Brownian motion model with one regime
modelBM \leftarrow PCM(model = "BM", k = 2)
# print the model
mode1BM
```

118 PCMVarAtTime

```
# assign the model parameters at random: this will use uniform distribution
# with boundaries specified by PCMParamLowerLimit and PCMParamUpperLimit
# We do this in two steps:
# 1. First we generate a random vector. Note the length of the vector equals PCMParamCount(modelBM)
randomParams <- PCMParamRandomVecParams(modelBM, PCMNumTraits(modelBM), PCMNumRegimes(modelBM))
randomParams
# 2. Then we load this random vector into the model.
PCMParamLoadOrStore(modelBM, randomParams, 0, PCMNumTraits(modelBM), PCMNumRegimes(modelBM), TRUE)
# create a random tree of 10 tips
tree <- ape::rtree(10)
covMat <- PCMVar(tree, modelBM)</pre>
```

PCMVarAtTime

Calculate the variance covariance $k \ x \ k$ matrix at time t, under a PCM model

Description

Calculate the variance covariance k x k matrix at time t, under a PCM model

Usage

```
PCMVarAtTime(
   t,
   model,
   W0 = matrix(0, PCMNumTraits(model), PCMNumTraits(model)),
   SE = matrix(0, PCMNumTraits(model), PCMNumTraits(model)),
   regime = PCMRegimes(model)[1L],
   verbose = FALSE
)
```

Arguments

t	positive numeric denoting time
model	a PCM model object
W0	a numeric matrix denoting the initial $k\ x\ k$ variance covariance matrix at the root (default is the $k\ x\ k$ zero matrix).
SE	a k x k matrix specifying the upper triangular factor of the measurement error variance-covariance matrix. The product SE Default: $SE = matrix(0.0, PCM-NumTraits(model), PCMNumTraits(model))$.
regime	an integer or a character denoting the regime in model for which to do the calculation; Defaults to PCMRegimes(model)[1L], meaning the first regime in the model.
verbose	a logical indicating if (debug) messages should be written on the console (Defaults to FALSE).

Value

A numeric k x k matrix

Examples

```
# a Brownian motion model with one regime
modelBM \leftarrow PCM(model = "BM", k = 2)
# print the model
mode1BM
# assign the model parameters at random: this will use uniform distribution
\# with boundaries specified by PCMParamLowerLimit and PCMParamUpperLimit
# We do this in two steps:
# 1. First we generate a random vector. Note the length of the vector equals PCMParamCount(modelBM)
randomParams <- PCMParamRandomVecParams(modelBM, PCMNumTraits(modelBM), PCMNumRegimes(modelBM))</pre>
randomParams
# 2. Then we load this random vector into the model.
PCMParamLoadOrStore(modelBM, randomParams, 0, PCMNumTraits(modelBM), PCMNumRegimes(modelBM), TRUE)
# PCMVarAtTime(1, modelBM)
# note that the variance at time 0 is not the 0 matrix because the model has a non-zero
# environmental deviation
PCMVarAtTime(0, modelBM)
```

 ${\tt Require Suggested Packages}$

Check if all packages listed in Suggests are available

Description

Check if all packages listed in Suggests are available

Usage

RequireSuggestedPackages()

Value

logical TRUE if suggested packages are installed and can be loaded; FALSE otherwise

120 UpperTriFactor

TruePositiveRate

True positive rate of a set of binary predictions against their trues

Description

Let the set of predictions be described by a logical vector 'pred', and let the corresponding trues by described in a logical vector 'true' of the same length. Then, the true positive rate is given by the expression: sum(pred & true)/sum(true). The false positive rate is given by the expression: sum(pred & !true)/sum(!true). If these expressions do not give a finite number, NA_real_ is returned.

Usage

```
TruePositiveRate(pred, true)
FalsePositiveRate(pred, true)
```

Arguments

pred, true

vectors of the same positive length that can be converted to logical.

Value

a double between 0 and 1 or NA_real_ if the result is not a finite number.

Examples

UpperTriFactor

Upper triangular factor of a symmetric positive definite matrix

Description

This function is an analog to the Cholesky decomposition.

Usage

```
UpperTriFactor(Sigma)
```

White 121

Arguments

Sigma

A symmetric positive definite $k \times k$ matrix that can be passed as argument to chol.

Value

```
an upper triangular matrix Sigma_x, such that Sigma = Sigma_x %*% t(Sigma_x)
```

See Also

```
chol;
```

the option PCMBase.Transpose.Sigma_x in PCMOptions.

Examples

```
# S is a symmetric positive definite matrix
M<-matrix(rexp(9),3,3); S <- M %*% t(M)

# This should return a zero matrix:
UpperTriFactor(S) %*% t(UpperTriFactor(S)) - S

# This should return a zero matrix too:
t(chol(S)) %*% chol(S) - S

# Unless S is diagonal, in the general case, this will return a
# non-zero matrix:
chol(S) %*% t(chol(S)) - S</pre>
```

White

White Gaussian PCM ignoring phylogenetic history

Description

White model ignoring phylogenetic history, treating trait values as independent samples from a k-variate Gaussian.

Details

Calculating likelihoods for this model does not work if the global option PCMBase.Singular.Skip is set to FALSE.

Index

* datasets	is.ScalarParameter (PCMParamType), 60	
dataFig3,8	is.Schur(PCMParamType), 60	
PCMBaseTestObjects, 20	is.SemiPositiveDefinite(PCMParamType)	
Args_MixedGaussian_MGPMDefaultModelTypes, 5	is.Symmetric (PCMParamType), 60 is.Transformable, 20	
Args_MixedGaussian_MGPMScalarOUType, 6	is.Transformable(PCMParamType), 60	
Args_MixedGaussian_MGPMSurfaceOUType,	is.Transformed (PCMParamType), 60 is.UpperTriangular (PCMParamType), 60	
as.MixedGaussian, 7, 14	is.UpperTriangularWithDiagonal (PCMParamType), 60	
chol, 51, 121	is.VectorParameter(PCMParamType), 60	
dataFig3, 8	is.WithCustomVecParams(PCMParamType), 60	
FalsePositiveRate (TruePositiveRate), 120	is.WithNonNegativeDiagonal (PCMParamType), 60	
FormatCellAsLatex, 8	is.Zeros(PCMParamType), 60	
FormatTableAsLatex, 9	isSymmetric, 51	
grep, <i>11</i>	MatchListMembers, 11, <i>19</i> , <i>34</i> , <i>71</i> methods, <i>48</i>	
is.AllEqual (PCMParamType), 60	MGPMDefaultModelTypes	
is.CholeskyFactor(PCMParamType), 60	(PCMDefaultModelTypes), 27	
is.Diagonal (PCMParamType), 60	MGPMScalarOUType, 12	
is.Fixed (PCMParamType), 60	MGPMSurfaceOUType, 12	
is.GaussianPCM, 9	MixedGaussian, 13, 15, 16	
is.Global (PCMParamType), 60	MixedGaussianTemplate, 14	
is.Identity(PCMParamType), 60	•	
is.Local (PCMParamType), 60	PCM, 15	
is.LowerTriangular (PCMParamType), 60	PCMAbCdEf, 17, 39, 42	
is.LowerTriangularWithDiagonal	PCMAddToListAttribute, 18	
(PCMParamType), 60	PCMApplyTransformation, 19	
is.MatrixParameter (PCMParamType), 60	PCMBaseIsADevRelease, 20	
is.MixedGaussian, 10	PCMBaseTestObjects, 20	
is.NonNegative (PCMParamType), 60	PCMColorPalette, 22	
is.Omitted (PCMParamType), 60	PCMCombineListAttribute, 22	
is.Ones (PCMParamType), 60	PCMCond, 23, 39, 42, 72	
is.PCM, 10	PCMCond.GaussianPCM, 24	
is.PCMTree, 11	PCMCondV0U, 25	
is ScalarDiagonal (PCMParamType) 60	PCMCreatelikelihood 26	

INDEX 123

PCMDefaultModelTypes, 27	PCMPlotTraitData2D,68
PCMDefaultObject, 28	PCMPresentCoordinates, 26, 36–38, 40, 41,
PCMDescribe, 29	44, 52, 69
PCMDescribeParameters, 29	PCMRegimes, 70, 92, 93
PCMExtractDimensions, 30	PCMSetAttribute, 70
PCMExtractRegimes, 30	PCMSim, 39, 42, 71
PCMFindMethod, 31	PCMSpecify, 16, 48, 73
PCMFixParameter, 32	PCMTable, 73
PCMGenerateModelTypes, 32	PCMTableParameterizations, 74
PCMGenerateParameterizations, 33, 43	PCMTrajectory, 75
PCMGetAttribute, 34	PCMTree, 77, 108-110
PCMGetVecParamsRegimesAndModels, 35	PCMTreeBackbonePartition, 79
PCMInfo, 27, 35, 39, 42, 52, 72	PCMTreeDropClade, 81
PCMLik, 17, 37, 37, 69, 72	PCMTreeDtNodes, 82
PCMLikDmvNorm, 39	PCMTreeEdgeTimes, 83, 95
PCMLikTrace, 40	PCMTreeEvalNestedEDxOnTree, 84
PCMListDefaultParameterizations	PCMTreeExtractClade, 85
(PCMListParameterizations), 43	PCMTreeGetBranchLength, 86
PCMListMembers, 12, 42	PCMTreeGetDaughters, 87
PCMListParameterizations, 43	PCMTreeGetLabels, 87
PCMLmr, 39, 42, 44	PCMTreeGetNodeLabels
PCMMapModelTypesToRegimes, 45	(PCMTreeGetLabels), 87
PCMMean, 46	PCMTreeGetParent, 88
PCMMeanAtTime, 47	PCMTreeGetPartition, 89, 93, 109
PCMModels, <i>14</i> , 48	PCMTreeGetPartNames, 14, 89, 92, 93
PCMModelTypes, 49	PCMTreeGetPartRegimes, 90, 92, 93
PCMNumRegimes, 49	PCMTreeGetPartsForNodes, 90
PCMNumTraits, 50	PCMTreeGetRegimesForEdges, 91
PCMOptions, 37, 50, 99, 115, 121	PCMTreeGetRegimesForNodes, 91
PCMPairSums, 52	PCMTreeGetRootLabel (PCMTreeGetLabels)
PCMParam, 53	87
PCMParamBindRegimeParams, 53	PCMTreeGetTipLabels (PCMTreeGetLabels)
PCMParamCount, 55	87
PCMParamGetShortVector, 56	PCMTreeGetTipsInPart, 92, 93
PCMParamLoadOrStore, 56	PCMTreeGetTipsInRegime, 92, 93
PCMParamLocateInShortVector, 57	PCMTreeInsertSingletons, 94
PCMParamLowerLimit, 58	PCMTreeInsertSingletonsAtEpoch
PCMParamRandomVecParams, 58	(PCMTreeInsertSingletons), 94
PCMParamSetByName, 59	PCMTreeInsertTipsOrSingletons
PCMParamType, 60	(PCMTreeInsertSingletons), 94
PCMParamUpperLimit, 63	PCMTreeJumps, 96
PCMParentClasses, 63	PCMTreeListAllPartitions, 97
PCMParseErrorMessage, 42,64	PCMTreeListCladePartitions, 51 , 98
PCMPExpxMeanExp, 51, 64	PCMTreeListDescendants, 99
PCMPLambdaP_1, 65	PCMTreeListRootPaths, 100
PCMPlotGaussianDensityGrid2D, 66	PCMTreeLocateEpochOnBranches, 95, 100
PCMPlotGaussianSample2D, 66	${\tt PCMTreeLocateMidpointsOnBranches}, {\tt 95},$
PCMPlotMath, 67	101

124 INDEX

```
PCMTreeMatchLabels, 101
PCMTreeMatrixNodesInSamePart, 102
PCMTreeMatrixNodesInSameRegime
        (PCMTreeMatrixNodesInSamePart),
        102
PCMTreeNearestNodesToEpoch, 103
PCMTreeNodeTimes, 104
PCMTreeNumNodes, 104
PCMTreeNumParts, 105
PCMTreeNumTips, 105
PCMTreePlot, 106
PCMTreePostorder, 106
PCMTreePreorder, 107
PCMTreeSetLabels, 107
PCMTreeSetPartition, 89, 108
PCMTreeSetPartRegimes, 92, 93, 110
PCMTreeSetRegimesForEdges, 111
PCMTreeSplitAtNode, 113
PCMTreeTableAncestors, 114
PCMTreeToString, 115
PCMTreeVCV, 52, 115
PCMUnfixParameter, 116
PCMVar, 52, 115, 116
PCMVarAtTime, 118
rcond, 65
RequireSuggestedPackages, 119
stop, 39
{\it True Positive Rate}, 120
tryCatch, 39
UpperTriFactor, 51, 120
vcv, 52, 115
White, 121
```