Package 'AzureVM'

October 12, 2022

Title Virtual Machines in 'Azure'

Version 2.2.2

Description

Functionality for working with virtual machines (VMs) in Microsoft's 'Azure' cloud: https://azure.microsoft.com/en-us/services/virtual-machines/. Includes facilities to deploy, startup, shutdown, and cleanly delete VMs and VM clusters. Deployment configurations can be highly customised, and can make use of existing resources as well as creating new ones. A selection of predefined configurations is provided to allow easy deployment of commonly used Linux and Windows images, including Data Science Virtual Machines. With a running VM, execute scripts and install optional extensions. Part of the 'AzureR' family of packages.

URL https://github.com/Azure/AzureVM https://github.com/Azure/AzureR

BugReports https://github.com/Azure/AzureVM/issues

License MIT + file LICENSE

VignetteBuilder knitr

Depends R (>= 3.3)

Imports R6 (>= 2.4.1), AzureRMR (>= 2.3.0), jsonlite

Suggests knitr, rmarkdown, testthat, parallel, AzureKeyVault, AzureVMmetadata

RoxygenNote 7.1.1

NeedsCompilation no

Author Hong Ooi [aut, cre], Microsoft [cph]

Maintainer Hong Ooi <hongooi73@gmail.com>

Repository CRAN

Date/Publication 2020-10-14 23:50:07 UTC

2 autoscaler_config

R topics documented:

	autoscaler_config	2
	az_vmss_resource	3
	az_vmss_template	5
	az_vm_resource	8
	az_vm_template	9
	build_template_definition.vm_config	11
	centos_7.5	13
	centos_7.5_ss	18
	create_vm	24
	defunct	28
	delete_vm	28
	get_vm	29
	ip_config	31
	is_vm	31
	lb_config	32
	lb_rule_ssh	33
	list_vm_sizes	35
	nic_config	36
	nsg_config	37
	nsg_rule_allow_ssh	38
	scaleset_options	39
	user_config	40
	vnet_config	42
Index		43

autoscaler_config

Autoscaler configuration

Description

Autoscaler configuration

```
autoscaler_config(profiles = list(autoscaler_profile()), ...)
autoscaler_profile(name = "Profile", minsize = 1, maxsize = NA,
  default = NA, scale_out = 0.75, scale_in = 0.25, interval = "PT1M",
  window = "PT5M")
```

az_vmss_resource 3

Arguments

profiles A list of autoscaling profiles, each obtained via a call to autoscaler_profile.

Other named arguments that will be treated as resource properties.

name For autoscaler_profile, a name for the profile.

minsize, maxsize, default

For autoscaler_profile, the minimum, maximum and default number of in-

stances.

scale_out, scale_in

For autoscaler_profile, the CPU usage (a fraction between 0 and 1) at which

to scale out and in, respectively.

interval For autoscaler_profile, The interval between samples, in ISO 8601 format.

The default is 1 minute.

window For autoscaler_profile, the window width over which to compute the per-

centage CPU. The default is 5 minutes.

See Also

```
create_vm_scaleset, vmss_config
```

Examples

```
autoscaler_config()
autoscaler_config(list(
    autoscaler_profile(minsize=2, maxsize=50, scale_out=0.9, scale_in=0.1)
))
```

az_vmss_resource

Virtual machine scaleset resource class

Description

Class representing a virtual machine scaleset resource. In general, the methods in this class should not be called directly, nor should objects be directly instantiated from it. Use the az_vmss_template class for interacting with scalesets instead.

Format

An R6 object of class az_vmss_resource, inheriting from AzureRMR::az_resource.

Details

A single virtual machine scaleset in Azure is actually a collection of resources, including any and all of the following.

- Network security group (Azure resource type Microsoft.Network/networkSecurityGroups)
- Virtual network (Azure resource type Microsoft.Network/virtualNetworks)

4 az_vmss_resource

- Load balancer (Azure resource type Microsoft.Network/loadBalancers)
- Public IP address (Azure resource type Microsoft.Network/publicIPAddresses)
- Autoscaler (Azure resource type Microsoft. Insights/autoscaleSettings)
- The scaleset itself (Azure resource type Microsoft.Compute/virtualMachineScaleSets)

By wrapping the deployment template used to create these resources, the az_vmss_template class allows managing them all as a single entity.

Methods

The following methods are available, in addition to those provided by the AzureRMR::az_template class.

- sync_vmss_status: Check the status of the scaleset.
- list_instances(): Return a list of az_vm_resource objects, one for each VM instance in the scaleset. Note that if the scaleset has a load balancer attached, the number of instances will vary depending on the load.
- get_instance(id): Return a specific VM instance in the scaleset.
- start(id=NULL, wait=FALSE): Start the scaleset. In this and the other methods listed here, id can be an optional character vector of instance IDs; if supplied, only carry out the operation for those instances.
- restart(id=NULL, wait=FALSE): Restart the scaleset.
- stop(deallocate=TRUE, id=NULL, wait=FALSE): Stop the scaleset.
- get_public_ip_address(): Get the public IP address of the scaleset (technically, of the load balancer). If the scaleset doesn't have a load balancer attached, returns NA.
- get_vm_public_ip_addresses(id=NULL, nic=1, config=1): Get the public IP addresses for the instances in the scaleset. Returns NA for the instances that are stopped or not publicly accessible.
- get_vm_private_ip_addresses(id=NULL, nic=1, config=1): Get the private IP addresses for the instances in the scaleset.
- get_vnet(nic=1, config=1): Get the scaleset's virtual network resource.
- get_nsg(nic=1, config=1): Get the scaleset's network security group resource.
- run_deployed_command(command, parameters=NULL, script=NULL, id=NULL): Run a PowerShell command on the instances in the scaleset.
- run_script(script, parameters=NULL, id=NULL): Run a script on the VM. For a Linux VM, this will be a shell script; for a Windows VM, a PowerShell script. Pass the script as a character vector.
- reimage(id=NULL, datadisks=FALSE): Reimage the instances in the scaleset. If datadisks is TRUE, reimage any attached data disks as well.
- redeploy(id=NULL): Redeploy the instances in the scaleset.
- mapped_vm_operation(..., id=NULL): Carry out an arbitrary operation on the instances in the scaleset. See the do_operation method of the AzureRMR::az_resource class for more details.

az_vmss_template 5

• add_extension(publisher, type, version, settings=list(), protected_settings=list(), key_vault_settings=list()): Add an extension to the scaleset.

• do_vmss_operation(...) Carry out an arbitrary operation on the scaleset resource (as opposed to the instances in the scaleset).

Instance operations

AzureVM has the ability to parallelise scaleset instance operations using a background process pool provided by AzureRMR. This can lead to significant speedups when working with scalesets with high instance counts. The pool is created automatically the first time that it is required, and remains persistent for the session. You can control the size of the process pool with the azure_vm_minpoolsize and azure_vm_maxpoolsize options, which have default values 2 and 10 respectively.

The id argument lets you specify a subset of instances on which to carry out an operation. This can be a character vector of instance IDs; a list of instance objects such as returned by list_instances; or a single instance object. The default (NULL) is to carry out the operation on all instances.

See Also

AzureRMR::az_resource, get_vm_scaleset_resource, az_vmss_template, AzureRMR::init_pool VM scaleset API reference

az_vmss_template

Virtual machine scaleset (cluster) template class

Description

Class representing a virtual machine scaleset deployment template. This class keeps track of all resources that are created as part of deploying a scaleset, and exposes methods for managing them.

Format

An R6 object of class az_vmss_template, inheriting from AzureRMR::az_template.

Details

A virtual machine scaleset in Azure is actually a collection of resources, including any and all of the following.

- Network security group (Azure resource type Microsoft . Network/networkSecurityGroups)
- Virtual network (Azure resource type Microsoft.Network/virtualNetworks)
- Load balancer (Azure resource type Microsoft.Network/loadBalancers)
- Public IP address (Azure resource type Microsoft.Network/publicIPAddresses)
- Autoscaler (Azure resource type Microsoft.Insights/autoscaleSettings)
- The scaleset itself (Azure resource type Microsoft.Compute/virtualMachineScaleSets)

By wrapping the deployment template used to create these resources, the az_vmss_template class allows managing them all as a single entity.

6 az_vmss_template

Fields

The following fields are exposed, in addition to those provided by the AzureRMR::az_template class.

- dns_name: The DNS name for the scaleset (technically, the name for its load balancer). Will be NULL if the scaleset is not publicly visible, or doesn't have a load balancer attached.
- identity: The managed identity details for the scaleset. Will be NULL if the scaleset doesn't have an identity assigned.

Methods

The following methods are available, in addition to those provided by the AzureRMR::az_template class.

- sync_vmss_status: Check the status of the scaleset.
- list_instances(): Return a list of az_vm_resource objects, one for each VM instance in the scaleset. Note that if the scaleset has an autoscaler attached, the number of instances will vary depending on the load.
- get_instance(id): Return a specific VM instance in the scaleset.
- start(id=NULL, wait=FALSE): Start the scaleset. In this and the other methods listed here, id can be an optional character vector of instance IDs; if supplied, only carry out the operation for those instances.
- restart(id=NULL, wait=FALSE): Restart the scaleset.
- stop(deallocate=TRUE, id=NULL, wait=FALSE): Stop the scaleset.
- get_public_ip_address(): Get the public IP address of the scaleset (technically, of the load balancer). If the scaleset doesn't have a load balancer attached, returns NA.
- get_vm_public_ip_addresses(id=NULL, nic=1, config=1): Get the public IP addresses for the instances in the scaleset. Returns NA for the instances that are stopped or not publicly accessible.
- get_vm_private_ip_addresses(id=NULL, nic=1, config=1): Get the private IP addresses for the instances in the scaleset.
- get_public_ip_resource(): Get the Azure resource for the load balancer's public IP address.
- get_vnet(nic=1, config=1): Get the scaleset's virtual network resource.
- get_nsg(nic=1, config=1): Get the scaleset's network security group resource.
- get_load_balancer(): Get the scaleset's load balancer resource.
- get_autoscaler(): Get the scaleset's autoscaler resource.
- run_deployed_command(command, parameters=NULL, script=NULL, id=NULL): Run a PowerShell command on the instances in the scaleset.
- run_script(script, parameters=NULL, id=NULL): Run a script on the VM. For a Linux VM, this will be a shell script; for a Windows VM, a PowerShell script. Pass the script as a character vector.
- reimage(id=NULL, datadisks=FALSE): Reimage the instances in the scaleset. If datadisks is TRUE, reimage any attached data disks as well.

az_vmss_template 7

- redeploy(id=NULL): Redeploy the instances in the scaleset.
- mapped_vm_operation(..., id=NULL): Carry out an arbitrary operation on the instances in the scaleset. See the do_operation method of the AzureRMR::az_resource class for more details.
- add_extension(publisher, type, version, settings=list(), protected_settings=list(), key_vault_settings=list()): Add an extension to the scaleset.
- do_vmss_operation(...) Carry out an arbitrary operation on the scaleset resource (as opposed to the instances in the scaleset).

Many of these methods are actually provided by the az_vmss_resource class, and propagated to the template as active bindings.

Instance operations

AzureVM has the ability to parallelise scaleset instance operations using a background process pool provided by AzureRMR. This can lead to significant speedups when working with scalesets with high instance counts. The pool is created automatically the first time that it is required, and remains persistent for the session. You can control the size of the process pool with the azure_vm_minpoolsize and azure_vm_maxpoolsize options, which have default values 2 and 10 respectively.

The id argument lets you specify a subset of instances on which to carry out an operation. This can be a character vector of instance IDs; a list of instance objects such as returned by list_instances; or a single instance object. The default (NULL) is to carry out the operation on all instances.

See Also

AzureRMR::az_template, create_vm_scaleset, get_vm_scaleset, delete_vm_scaleset, AzureRMR::init_pool VM scaleset API reference

Examples

```
## Not run:
sub <- AzureRMR::get_azure_login()$
    get_subscription("subscription_id")

vmss <- sub$get_vm_scaleset("myscaleset")

vmss$identity

vmss$get_public_ip_address() # NA if the scaleset doesn't have a load balancer

vmss$start()
vmss$get_vm_private_ip_addresses()
vmss$get_vm_public_ip_addresses() # NA if scaleset nodes are not publicly visible

instances <- vmss$list_instances()
first <- instances[1]
vmss$run_script("echo hello world! > /tmp/hello.txt", id=first)
vmss$stop(id=first)
```

8 az_vm_resource

```
vmss$reimage(id=first)
vmss$sync_vmss_status()
## End(Not run)
```

az_vm_resource

Virtual machine resource class

Description

Class representing a virtual machine resource. In general, the methods in this class should not be called directly, nor should objects be directly instantiated from it. Use the az_vm_template class for interacting with VMs instead.

Format

An R6 object of class az_vm_resource, inheriting from AzureRMR::az_resource.

Methods

The following methods are available, in addition to those provided by the AzureRMR::az_resource class:

- start(wait=TRUE): Start the VM. By default, wait until the startup process is complete.
- stop(deallocate=TRUE, wait=FALSE): Stop the VM. By default, deallocate it as well.
- restart(wait=TRUE): Restart the VM.
- run_deployed_command(command, parameters, script): Run a PowerShell command on the VM.
- run_script(script, parameters): Run a script on the VM. For a Linux VM, this will be a shell script; for a Windows VM, a PowerShell script. Pass the script as a character vector.
- sync_vm_status(): Check the status of the VM.
- resize(size, deallocate=FALSE, wait=FALSE): Resize the VM. Optionally stop and deallocate it first (may sometimes be necessary).
- redeploy(): Redeploy the VM.
- reimage(): Reimage the VM.
- get_public_ip_address(nic=1, config=1): Get the public IP address of the VM. Returns NA if the VM is shut down, or is not publicly accessible.
- get_private_ip_address(nic=1, config=1): Get the private IP address of the VM.
- get_public_ip_resource(nic=1, config=1): Get the Azure resource for the VM's public IP address.
- get_nic(nic=1): Get the VM's network interface resource.
- get_vnet(nic=1, config=1): Get the VM's virtual network resource.

az_vm_template 9

• get_nsg(nic=1, config=1): Get the VM's network security group resource. Note that an NSG can be attached to either the VM's network interface or to its virtual network subnet; if there is an NSG attached to both, this method returns a list containing the two NSG resource objects.

- get_disk(disk="os"): Get a managed disk resource attached to the VM. The disk argument can be "os" for the OS disk, or a number indicating the LUN of a data disk. AzureVM only supports managed disks.
- add_extension(publisher, type, version, settings=list(), protected_settings=list(), key_vault_settings=list()): Add an extension to the VM.
- do_vm_operation(...): Carry out an arbitrary operation on the VM resource. See the do_operation method of the AzureRMR::az_resource class for more details.

See Also

AzureRMR::az_resource, get_vm_resource, az_vm_template
VM API reference

az_vm_template

Virtual machine template class

Description

Class representing a virtual machine deployment template. This class keeps track of all resources that are created as part of deploying a VM, and exposes methods for managing them.

Format

An R6 object of class az_vm_template, inheriting from AzureRMR::az_template.

Details

A single virtual machine in Azure is actually a collection of resources, including any and all of the following.

- Network interface (Azure resource type Microsoft.Network/networkInterfaces)
- Network security group (Azure resource type Microsoft.Network/networkSecurityGroups)
- Virtual network (Azure resource type Microsoft.Network/virtualNetworks)
- Public IP address (Azure resource type Microsoft.Network/publicIPAddresses)
- The VM itself (Azure resource type Microsoft.Compute/virtualMachines)

By wrapping the deployment template used to create these resources, the az_vm_template class allows managing them all as a single entity.

10 az_vm_template

Fields

The following fields are exposed, in addition to those provided by the AzureRMR::az_template class.

- dns_name: The DNS name for the VM. Will be NULL if the VM is not publicly visible, or doesn't have a domain name assigned to its public IP address.
- identity: The managed identity details for the VM. Will be NULL if the VM doesn't have an identity assigned.

Methods

The following methods are available, in addition to those provided by the AzureRMR::az_template class.

- start(wait=TRUE): Start the VM. By default, wait until the startup process is complete.
- stop(deallocate=TRUE, wait=FALSE): Stop the VM. By default, deallocate it as well.
- restart(wait=TRUE): Restart the VM.
- run_deployed_command(command, parameters, script): Run a PowerShell command on the VM.
- run_script(script, parameters): Run a script on the VM. For a Linux VM, this will be a shell script; for a Windows VM, a PowerShell script. Pass the script as a character vector.
- sync_vm_status(): Check the status of the VM.
- resize(size, deallocate=FALSE, wait=FALSE): Resize the VM. Optionally stop and deallocate it first (may sometimes be necessary).
- redeploy(): Redeploy the VM.
- reimage(): Reimage the VM.
- get_public_ip_address(nic=1, config=1): Get the public IP address of the VM. Returns NA if the VM is stopped, or is not publicly accessible.
- get_private_ip_address(nic=1, config=1): Get the private IP address of the VM.
- get_public_ip_resource(nic=1, config=1): Get the Azure resource for the VM's public IP address.
- get_nic(nic=1): Get the VM's network interface resource.
- get_vnet(nic=1, config=1): Get the VM's virtual network resource.
- get_nsg(nic=1, config=1): Get the VM's network security group resource. Note that an NSG can be attached to either the VM's network interface or to its virtual network subnet; if there is an NSG attached to both, this method returns a list containing the two NSG resource objects.
- get_disk(disk="os"): Get a managed disk resource attached to the VM. The disk argument can be "os" for the OS disk, or a number indicating the LUN of a data disk. AzureVM only supports managed disks.
- add_extension(publisher, type, version, settings=list(), protected_settings=list(), key_vault_settings=list()): Add an extension to the VM.
- do_vm_operation(...): Carries out an arbitrary operation on the VM resource. See the do_operation method of the AzureRMR::az_resource class for more details.

Many of these methods are actually provided by the az_vm_resource class, and propagated to the template as active bindings.

See Also

```
AzureRMR::az_template, create_vm, get_vm, delete_vm
VM API reference
```

Examples

```
## Not run:
sub <- AzureRMR::get_azure_login()$
    get_subscription("subscription_id")

vm <- sub$get_vm("myvm")

vm$start()
vm$get_private_ip_address()
vm$get_public_ip_address()
vm$run_script("echo hello world! > /tmp/hello.txt")

vm$stop()
vm$get_private_ip_address()
vm$get_private_ip_address()
vm$get_private_ip_address()
vm$get_private_ip_address()
vm$get_public_ip_address() # NA, assuming VM has a dynamic IP address

vm$resize("Standard_DS13_v2")
vm$sync_vm_status()

## End(Not run)
```

Description

Build template definition and parameters

```
## S3 method for class 'vm_config'
build_template_definition(config, ...)
## S3 method for class 'vmss_config'
build_template_definition(config, ...)
## S3 method for class 'vm_config'
```

```
build_template_parameters(config, name, login_user, size, ...)
## S3 method for class 'vmss_config'
build_template_parameters(config, name, login_user, size, instances, ...)
```

Arguments

config	An object of class vm_config or vmss_config representing a virtual machine or scaleset deployment.
	Unused.
name	The VM or scaleset name. Will also be used for the domain name label, if a public IP address is included in the deployment.
login_user	An object of class $user_config$ representing the login details for the admin user account on the VM.
size	The VM (instance) size.
instances	For vmss_config, the number of (initial) instances in the VM scaleset.

Details

These are methods for the generics defined in the AzureRMR package.

Value

Objects of class json, which are JSON character strings representing the deployment template and its parameters.

See Also

```
create_vm, vm_config, vmss_config
```

Examples

centos_7.5

VM configuration functions

Description

VM configuration functions

```
centos_7.5(keylogin = TRUE, managed_identity = TRUE,
  datadisks = numeric(0), nsg = nsg_config(list(nsg_rule_allow_ssh)), ...)
centos_7.6(keylogin = TRUE, managed_identity = TRUE,
  datadisks = numeric(0), nsg = nsg_config(list(nsg_rule_allow_ssh)), ...)
centos_8.1(keylogin = TRUE, managed_identity = TRUE,
  datadisks = numeric(0), nsg = nsg_config(list(nsg_rule_allow_ssh)), ...)
debian_8_backports(keylogin = TRUE, managed_identity = TRUE,
  datadisks = numeric(0), nsg = nsg_config(list(nsg_rule_allow_ssh)), ...)
debian_9_backports(keylogin = TRUE, managed_identity = TRUE,
  datadisks = numeric(0), nsg = nsg_config(list(nsg_rule_allow_ssh)), ...)
debian_10_backports(keylogin = TRUE, managed_identity = TRUE,
  datadisks = numeric(0), nsg = nsg_config(list(nsg_rule_allow_ssh)), ...)
debian_10_backports_gen2(keylogin = TRUE, managed_identity = TRUE,
  datadisks = numeric(0), nsg = nsg_config(list(nsg_rule_allow_ssh)), ...)
ubuntu_dsvm(keylogin = TRUE, managed_identity = TRUE,
 datadisks = numeric(0), nsg = nsg_config(list(nsg_rule_allow_ssh,
  nsg_rule_allow_jupyter, nsg_rule_allow_rstudio)), ...)
ubuntu_dsvm_gen2(keylogin = TRUE, managed_identity = TRUE,
  datadisks = numeric(0), nsg = nsg_config(list(nsg_rule_allow_ssh,
  nsg_rule_allow_jupyter, nsg_rule_allow_rstudio)), ...)
windows_dsvm(keylogin = FALSE, managed_identity = TRUE,
  datadisks = numeric(0), nsg = nsg_config(list(nsg_rule_allow_rdp)), ...)
rhel_7.6(keylogin = TRUE, managed_identity = TRUE,
  datadisks = numeric(0), nsg = nsg_config(list(nsg_rule_allow_ssh)), ...)
rhel_8(keylogin = TRUE, managed_identity = TRUE, datadisks = numeric(0),
  nsg = nsg_config(list(nsg_rule_allow_ssh)), ...)
```

```
rhel_8.1(keylogin = TRUE, managed_identity = TRUE,
 datadisks = numeric(0), nsg = nsg_config(list(nsg_rule_allow_ssh)), ...)
rhel_8.1_gen2(keylogin = TRUE, managed_identity = TRUE,
  datadisks = numeric(0), nsg = nsg_config(list(nsg_rule_allow_ssh)), ...)
rhel_8.2(keylogin = TRUE, managed_identity = TRUE,
  datadisks = numeric(0), nsg = nsg_config(list(nsg_rule_allow_ssh)), ...)
rhel_8.2_gen2(keylogin = TRUE, managed_identity = TRUE,
  datadisks = numeric(0), nsg = nsg_config(list(nsg_rule_allow_ssh)), ...)
ubuntu_16.04(keylogin = TRUE, managed_identity = TRUE,
  datadisks = numeric(0), nsg = nsg_config(list(nsg_rule_allow_ssh)), ...)
ubuntu_18.04(keylogin = TRUE, managed_identity = TRUE,
  datadisks = numeric(0), nsg = nsg_config(list(nsg_rule_allow_ssh)), ...)
ubuntu_20.04(keylogin = TRUE, managed_identity = TRUE,
  datadisks = numeric(0), nsg = nsg_config(list(nsg_rule_allow_ssh)), ...)
ubuntu_20.04_gen2(keylogin = TRUE, managed_identity = TRUE,
  datadisks = numeric(0), nsg = nsg_config(list(nsg_rule_allow_ssh)), ...)
windows_2016(keylogin = FALSE, managed_identity = TRUE,
  datadisks = numeric(0), nsg = nsg_config(list(nsg_rule_allow_rdp)), ...)
windows_2019(keylogin = FALSE, managed_identity = TRUE,
  datadisks = numeric(0), nsg = nsg_config(list(nsg_rule_allow_rdp)), ...)
windows_2019_gen2(keylogin = FALSE, managed_identity = TRUE,
  datadisks = numeric(0), nsg = nsg_config(list(nsg_rule_allow_rdp)), ...)
vm_config(image, keylogin, managed_identity = TRUE,
 os\_disk\_type = c("Premium\_LRS", "StandardSSD\_LRS", "Standard\_LRS"),\\
 datadisks = numeric(0), nsg = nsg_config(), ip = ip_config(),
  vnet = vnet_config(), nic = nic_config(), other_resources = list(),
  variables = list(), ...)
```

Arguments

keylogin Whether to use an SSH public key to login (TRUE) or a password (FALSE).

Note that Windows does not support SSH key logins.

managed_identity

Whether to provide a managed system identity for the VM.

datadisks The data disks to attach to the VM. Specify this as either a vector of numeric disk sizes in GB, or a list of datadisk_config objects for more control over the specification.

The network security group for the VM. Can be a call to nsg_config to create a new NSG; an AzureRMR resource object or resource ID to reuse an existing NSG; or NULL to not use an NSG (not recommended).

For the specific VM configurations, other customisation arguments to be passed to vm_config. For vm_config, named arguments that will be folded into the VM resource definition in the template. In particular use properties=list(*) to set additional properties for the VM, beyond those set by the various config-

uration functions.

image For vm_config, the VM image to deploy. This should be an object of class

image_config, created by the function of the same name.

os_disk_type The type of primary disk for the VM. Can be "Premium_LRS" (the default),

"StandardSSD_LRS", or "Standard_LRS". Of these, "Standard_LRS" uses hard disks and the others use SSDs as the underlying hardware. Change this to "StandardSSD_LRS" or "Standard_LRS" if the VM size doesn't support premium

storage.

ip The public IP address for the VM. Can be a call to ip_config to create a new

IP address; an AzureRMR resource object or resource ID to reuse an existing address resource; or NULL if the VM should not be accessible from outside its

subnet.

vnet The virtual network for the VM. Can be a call to vnet_config to create a new

virtual network, or an AzureRMR resource object or resource ID to reuse an existing virtual network. Note that by default, AzureVM will associate the NSG

with the virtual network/subnet, not with the VM's network interface.

nic The network interface for the VM. Can be a call to nic_config to create a new

interface, or an AzureRMR resource object or resource ID to reuse an existing

interface.

other_resources

An optional list of other resources to include in the deployment.

variables An optional named list of variables to add to the template.

Details

These functions are for specifying the details of a new virtual machine deployment: the VM image and related options, along with the Azure resources that the VM may need. These include the datadisks, network security group, public IP address (if the VM is to be accessible from outside its subnet), virtual network, and network interface. vm_config is the base configuration function, and the others call it to create VMs with specific operating systems and other image details.

- ubuntu_dsvm: Data Science Virtual Machine, based on Ubuntu 18.04
- windows_dsvm: Data Science Virtual Machine, based on Windows Server 2019
- ubuntu_16.04, ubuntu_18.04, ubuntu_20.04, ubuntu_20.04_gen2: Ubuntu LTS
- windows_2016, windows_2019: Windows Server Datacenter edition
- rhel_7.6, rhel_8, rhel_8.1, rhel_8.1_gen2, rhel_8.2, "rhel_8.2_gen2: Red Hat Enterprise Linux
- centos_7.5, centos_7.6, centos_8.1: CentOS

 debian_8_backports, debian_9_backports, debian_10_backports, debian_10_backports_gen2: Debian with backports

The VM configurations with gen2 in the name are generation 2 VMs, which feature several technical improvements over the earlier generation 1. Consider using these for greater efficiency, however note that gen2 VMs are only available for select images and do not support all possible VM sizes.

Each resource can be specified in a number of ways:

- To create a new resource as part of the deployment, call the corresponding *_config function.
- To use an existing resource, supply either an AzureRMR::az_resource object (recommended) or a string containing the resource ID.
- If the resource is not needed, specify it as NULL.
- For the other_resources argument, supply a list of resources, each of which should be a list of resource fields (name, type, properties, sku, etc).

A VM configuration defines the following template variables by default, depending on its resources. If a particular resource is created, the corresponding *Name, *Id and *Ref variables will be available. If a resource is referred to but not created, the *Name* and *Id variables will be available. Other variables can be defined via the variables argument.

Variable name	Contents	Descript
location	[resourceGroup().location]	Region to
vmId	<pre>[resourceId('Microsoft.Compute/virtualMachines', parameters('vmName'))]</pre>	VM resor
vmRef	<pre>[concat('Microsoft.Compute/virtualMachines/', parameters('vmName'))]</pre>	VM temp
nsgName	<pre>[concat(parameters('vmName'), '-nsg')]</pre>	Network
nsgId	<pre>[resourceId('Microsoft.Network/networkSecurityGroups', variables('nsgName'))]</pre>	NSG reso
nsgRef	<pre>[concat('Microsoft.Network/networkSecurityGroups/', variables('nsgName'))]</pre>	NSG tem
ipName	<pre>[concat(parameters('vmName'), '-ip')]</pre>	Public IP
ipId	<pre>[resourceId('Microsoft.Network/publicIPAddresses', variables('ipName'))]</pre>	IP resour
ipRef	<pre>[concat('Microsoft.Network/publicIPAddresses/', variables('ipName'))]</pre>	IP templa
vnetName	<pre>[concat(parameters('vmName'), '-vnet')]</pre>	Virtual no
vnetId	<pre>[resourceId('Microsoft.Network/virtualNetworks', variables('vnetName'))]</pre>	Vnet reso
vnetRef	<pre>[concat('Microsoft.Network/virtualNetworks/', variables('vnetName'))]</pre>	Vnet tem
subnet	subnet	Subnet na
subnetId	<pre>[concat(variables('vnetId'), '/subnets/', variables('subnet'))]</pre>	Subnet re
nicName	<pre>[concat(parameters('vmName'), '-nic')]</pre>	Network
nicId	<pre>[resourceId('Microsoft.Network/networkInterfaces', variables('nicName'))]</pre>	NIC reso
nicRef	<pre>[concat('Microsoft.Network/networkInterfaces/', variables('nicName'))]</pre>	NIC temp

Thus, for example, if you are creating a VM named "myvm" along with all its associated resources, the NSG is named "myvm-nsg", the public IP address is "myvm-ip", the virtual network is "myvmvnet", and the network interface is "myvm-nic".

Value

An object of S3 class vm_config, that can be used by the create_vm method.

See Also

```
image_config, user_config, datadisk_config for options relating to the VM resource itself nsg_config, ip_config, vnet_config, nic_config for other resource configs build_template for template builder methods vmss_config for configuring a virtual machine scaleset create_vm
```

Examples

```
# basic Linux (Ubuntu) and Windows configs
ubuntu_18.04()
windows_2019()
# Windows DSVM with 500GB data disk, no public IP address
windows_dsvm(datadisks=500, ip=NULL)
# RHEL VM exposing ports 80 (HTTP) and 443 (HTTPS)
rhel_8(nsg=nsg_config(nsg_rule_allow_http, nsg_rule_allow_https))
# exposing no ports externally, spot (low) priority
rhel_8(nsg=nsg_config(list()), properties=list(priority="spot"))
# deploying an extra resource: storage account
ubuntu_18.04(
    variables=list(storName="[concat(parameters('vmName'), 'stor')]"),
    other_resources=list(
        list(
            type="Microsoft.Storage/storageAccounts",
            name="[variables('storName')]",
            apiVersion="2018-07-01",
            location="[variables('location')]",
            properties=list(supportsHttpsTrafficOnly=TRUE),
            sku=list(name="Standard_LRS"),
            kind="Storage"
        )
   )
)
## custom VM configuration: Windows 10 Pro 1903 with data disks
## this assumes you have a valid Win10 desktop license
user <- user_config("myname", password="Use-strong-passwords!")</pre>
image <- image_config(</pre>
     publisher="MicrosoftWindowsDesktop",
     offer="Windows-10",
     sku="19h1-pro"
datadisks <- list(</pre>
    datadisk_config(250, type="Premium_LRS"),
    datadisk_config(1000, type="Standard_LRS")
```

```
nsg <- nsg_config(</pre>
    list(nsg_rule_allow_rdp)
)
vm_config(
    image=image,
    keylogin=FALSE,
    datadisks=datadisks,
    nsg=nsg,
    properties=list(licenseType="Windows_Client")
)
## Not run:
# reusing existing resources: placing multiple VMs in one vnet/subnet
rg <- AzureRMR::get_azure_login()$</pre>
    get_subscription("sub_id")$
    get_resource_group("rgname")
vnet <- rg$get_resource(type="Microsoft.Network/virtualNetworks", name="myvnet")</pre>
# by default, the NSG is associated with the subnet, so we don't need a new NSG either
vmconfig1 <- ubuntu_18.04(vnet=vnet, nsg=NULL)</pre>
vmconfig2 <- debian_9_backports(vnet=vnet, nsg=NULL)</pre>
vmconfig3 <- windows_2019(vnet=vnet, nsg=NULL)</pre>
## End(Not run)
```

centos_7.5_ss

Virtual machine scaleset configuration functions

Description

Virtual machine scaleset configuration functions

```
centos_7.5_ss(datadisks = numeric(0),
   nsg = nsg_config(list(nsg_rule_allow_ssh)),
   load_balancer = lb_config(rules = list(lb_rule_ssh), probes =
   list(lb_probe_ssh)), ...)

centos_7.6_ss(datadisks = numeric(0),
   nsg = nsg_config(list(nsg_rule_allow_ssh)),
   load_balancer = lb_config(rules = list(lb_rule_ssh), probes =
   list(lb_probe_ssh)), ...)
```

```
centos_8.1_ss(datadisks = numeric(0),
  nsg = nsg_config(list(nsg_rule_allow_ssh)),
  load_balancer = lb_config(rules = list(lb_rule_ssh), probes =
  list(lb_probe_ssh)), ...)
debian_8_backports_ss(datadisks = numeric(0),
  nsg = nsg_config(list(nsg_rule_allow_ssh)),
  load_balancer = lb_config(rules = list(lb_rule_ssh), probes =
  list(lb_probe_ssh)), ...)
debian_9_backports_ss(datadisks = numeric(0),
  nsg = nsg_config(list(nsg_rule_allow_ssh)),
  load_balancer = lb_config(rules = list(lb_rule_ssh), probes =
  list(lb_probe_ssh)), ...)
debian_10_backports_ss(datadisks = numeric(0),
  nsg = nsg_config(list(nsg_rule_allow_ssh)),
  load_balancer = lb_config(rules = list(lb_rule_ssh), probes =
  list(lb_probe_ssh)), ...)
debian_10_backports_gen2_ss(datadisks = numeric(0),
  nsg = nsg_config(list(nsg_rule_allow_ssh)),
 load_balancer = lb_config(rules = list(lb_rule_ssh), probes =
  list(lb_probe_ssh)), ...)
ubuntu_dsvm_ss(datadisks = numeric(0),
  nsg = nsg_config(list(nsg_rule_allow_ssh, nsg_rule_allow_jupyter,
  nsg_rule_allow_rstudio)), load_balancer = lb_config(rules =
  list(lb_rule_ssh, lb_rule_jupyter, lb_rule_rstudio), probes =
  list(lb_probe_ssh, lb_probe_jupyter, lb_probe_rstudio)), ...)
ubuntu_dsvm_gen2_ss(datadisks = numeric(0),
  nsg = nsg_config(list(nsg_rule_allow_ssh, nsg_rule_allow_jupyter,
  nsg_rule_allow_rstudio)), load_balancer = lb_config(rules =
  list(lb_rule_ssh, lb_rule_jupyter, lb_rule_rstudio), probes =
  list(lb_probe_ssh, lb_probe_jupyter, lb_probe_rstudio)), ...)
windows_dsvm_ss(datadisks = numeric(0),
  nsg = nsg_config(list(nsg_rule_allow_rdp)),
  load_balancer = lb_config(rules = list(lb_rule_rdp), probes =
  list(lb_probe_rdp)), options = scaleset_options(keylogin = FALSE), ...)
rhel_7.6_ss(datadisks = numeric(0),
  nsg = nsg_config(list(nsg_rule_allow_ssh)),
  load_balancer = lb_config(rules = list(lb_rule_ssh), probes =
  list(lb_probe_ssh)), ...)
rhel_8_ss(datadisks = numeric(0),
```

```
nsg = nsg_config(list(nsg_rule_allow_ssh)),
  load_balancer = lb_config(rules = list(lb_rule_ssh), probes =
  list(lb_probe_ssh)), ...)
rhel_8.1_ss(datadisks = numeric(0),
  nsg = nsg_config(list(nsg_rule_allow_ssh)),
  load_balancer = lb_config(rules = list(lb_rule_ssh), probes =
  list(lb_probe_ssh)), ...)
rhel_8.1_gen2_ss(datadisks = numeric(0),
  nsg = nsg_config(list(nsg_rule_allow_ssh)),
  load_balancer = lb_config(rules = list(lb_rule_ssh), probes =
  list(lb_probe_ssh)), ...)
rhel_8.2_ss(datadisks = numeric(0),
  nsg = nsg_config(list(nsg_rule_allow_ssh)),
  load_balancer = lb_config(rules = list(lb_rule_ssh), probes =
  list(lb_probe_ssh)), ...)
rhel_8.2_gen2_ss(datadisks = numeric(0),
  nsg = nsg_config(list(nsg_rule_allow_ssh)),
  load_balancer = lb_config(rules = list(lb_rule_ssh), probes =
  list(lb_probe_ssh)), ...)
ubuntu_16.04_ss(datadisks = numeric(0),
  nsg = nsg_config(list(nsg_rule_allow_ssh)),
 load_balancer = lb_config(rules = list(lb_rule_ssh), probes =
  list(lb_probe_ssh)), ...)
ubuntu_18.04_ss(datadisks = numeric(0),
  nsg = nsg_config(list(nsg_rule_allow_ssh)),
  load_balancer = lb_config(rules = list(lb_rule_ssh), probes =
  list(lb_probe_ssh)), ...)
ubuntu_20.04_ss(datadisks = numeric(0),
  nsg = nsg_config(list(nsg_rule_allow_ssh)),
  load_balancer = lb_config(rules = list(lb_rule_ssh), probes =
  list(lb_probe_ssh)), ...)
ubuntu_20.04_gen2_ss(datadisks = numeric(0),
  nsg = nsg_config(list(nsg_rule_allow_ssh)),
  load_balancer = lb_config(rules = list(lb_rule_ssh), probes =
  list(lb_probe_ssh)), ...)
windows_2016_ss(datadisks = numeric(0),
  nsg = nsg_config(list(nsg_rule_allow_rdp)),
  load_balancer = lb_config(rules = list(lb_rule_rdp), probes =
  list(lb_probe_rdp)), options = scaleset_options(keylogin = FALSE), ...)
```

```
windows_2019_ss(datadisks = numeric(0),
   nsg = nsg_config(list(nsg_rule_allow_rdp)),
   load_balancer = lb_config(rules = list(lb_rule_rdp), probes =
   list(lb_probe_rdp)), options = scaleset_options(keylogin = FALSE), ...)

windows_2019_gen2_ss(datadisks = numeric(0),
   nsg = nsg_config(list(nsg_rule_allow_rdp)),
   load_balancer = lb_config(rules = list(lb_rule_rdp), probes =
   list(lb_probe_rdp)), options = scaleset_options(keylogin = FALSE), ...)

vmss_config(image, options = scaleset_options(), datadisks = numeric(0),
   nsg = nsg_config(), vnet = vnet_config(), load_balancer = lb_config(),
   load_balancer_address = ip_config(), autoscaler = autoscaler_config(),
   other_resources = list(), variables = list(), ...)
```

Arguments

datadisks The data disks to attach to the VM. Specify this as either a vector of numeric

disk sizes in GB, or a list of datadisk_config objects for more control over the

specification.

nsg The network security group for the scaleset. Can be a call to nsg_config to

create a new NSG; an AzureRMR resource object or resource ID to reuse an

existing NSG; or NULL to not use an NSG (not recommended).

load_balancer The load balancer for the scaleset. Can be a call to lb_config to create a new

load balancer; an AzureRMR resource object or resource ID to reuse an existing

load balancer; or NULL if load balancing is not required.

.. For the specific VM configurations, other customisation arguments to be passed

to vm_config. For vmss_config, named arguments that will be folded into the

scaleset resource definition in the template.

options Scaleset options, as obtained via a call to scaleset_options.

image For vmss_config, the VM image to deploy. This should be an object of class

image_config, created by the function of the same name.

vnet The virtual network for the scaleset. Can be a call to vnet_config to create a

new virtual network, or an AzureRMR resource object or resource ID to reuse an existing virtual network. Note that by default, AzureVM will associate the

NSG with the virtual network/subnet, not with the VM's network interface.

load_balancer_address

The public IP address for the load balancer. Can be a call to ip_config to create a new IP address, or an AzureRMR resource object or resource ID to reuse an

existing address resource. Ignored if load_balancer is NULL.

autoscaler The autoscaler for the scaleset. Can be a call to autoscaler_config to create

a new autoscaler; an AzureRMR resource object or resource ID to reuse an

existing autoscaler; or NULL if autoscaling is not required.

other_resources

An optional list of other resources to include in the deployment.

variables An optional named list of variables to add to the template.

Details

These functions are for specifying the details of a new virtual machine scaleset deployment: the base VM image and related options, along with the Azure resources that the scaleset may need. These include the network security group, virtual network, load balancer and associated public IP address, and autoscaler.

Each resource can be specified in a number of ways:

- To *create* a new resource as part of the deployment, call the corresponding *_config function.
- To use an *existing* resource, supply either an AzureRMR::az_resource object (recommended) or a string containing the resource ID.
- If the resource is not needed, specify it as NULL.
- For the other_resources argument, supply a list of resources, each of which should be a list of resource fields (name, type, properties, sku, etc).

The vmss_config function is the base configuration function, and the others call it to create VM scalesets with specific operating systems and other image details.

- ubuntu_dsvm_ss: Data Science Virtual Machine, based on Ubuntu 18.04
- windows_dsvm_ss: Data Science Virtual Machine, based on Windows Server 2019
- ubuntu_16.04_ss, ubuntu_18.04_ss, ubuntu_20.04_ss, ubuntu_20.04_gen2_ss: Ubuntu LTS
- windows_2016_ss, windows_2019_ss: Windows Server Datacenter edition
- rhel_7.6_ss, rhel_8_ss, rhel_8.1_ss, rhel_8.1_gen2_ss, rhel_8.2_ss, rhel_8.2_gen2_ss: Red Hat Enterprise Linux
- centos_7.5_ss, centos_7.6_ss, centos_8.1_ss: CentOS
- debian_8_backports_ss, debian_9_backports_ss, debian_10_backports_ss, debian_10_backports_gen2_ss:
 Debian with backports

The VM scaleset configurations with gen2 in the name use generation 2 VMs, which feature several technical improvements over the earlier generation 1. Consider using these for greater efficiency, however note that gen2 VMs are only available for select images and do not support all possible VM sizes.

A VM scaleset configuration defines the following template variables by default, depending on its resources. If a particular resource is created, the corresponding *Name, *Id and *Ref variables will be available. If a resource is referred to but not created, the *Name* and *Id variables will be available. Other variables can be defined via the variables argument.

Variable name	Contents
location	[resourceGroup().location]
vmId	<pre>[resourceId('Microsoft.Compute/virtualMachines', parameters('vmName'))]</pre>
vmRef	<pre>[concat('Microsoft.Compute/virtualMachines/', parameters('vmName'))]</pre>
nsgName	<pre>[concat(parameters('vmName'), '-nsg')]</pre>
nsgId	<pre>[resourceId('Microsoft.Network/networkSecurityGroups', variables('nsgName'))]</pre>
nsgRef	<pre>[concat('Microsoft.Network/networkSecurityGroups/', variables('nsgName'))]</pre>
vnetName	<pre>[concat(parameters('vmName'), '-vnet')]</pre>
vnetId	<pre>[resourceId('Microsoft.Network/virtualNetworks', variables('vnetName'))]</pre>

```
vnetRef
                [concat('Microsoft.Network/virtualNetworks/', variables('vnetName'))]
subnet
                subnet
subnetId
                [concat(variables('vnetId'), '/subnets/', variables('subnet'))]
1bName
                [concat(parameters('vmName'), '-lb')]
lbId
                [resourceId('Microsoft.Network/loadBalancers', variables('lbName'))]
1bRef
                [concat('Microsoft.Network/loadBalancers/', variables('lbName'))]
1bFrontendName
                frontend
1bBackendName
                backend
1bFrontendId
                [concat(variables('lbId'), '/frontendIPConfigurations/', variables('lbFrontendName'))
lbBackendId
                [concat(variables('lbId'), '/backendAddressPools/', variables('lbBackendName'))]
ipName
                [concat(parameters('vmName'), '-ip')]
                [resourceId('Microsoft.Network/publicIPAddresses', variables('ipName'))]
ipId
ipRef
                [concat('Microsoft.Network/publicIPAddresses/', variables('ipName'))]
                [concat(parameters('vmName'), '-as')]
asName
asId
                [resourceId('Microsoft.Insights/autoscaleSettings', variables('asName'))]
asRef
                [concat('Microsoft.Insights/autoscaleSettings/', variables('asName'))]
                [mul(int(parameters('instanceCount')), 10)]
asMaxCapacity
```

Thus, for example, if you are creating a VM scaleset named "myvmss" along with all its associated resources, the NSG is named "myvmss-nsg", the virtual network is "myvmss-vnet", the load balancer is "myvmss-lb", the public IP address is "myvmss-ip", and the autoscaler is "myvm-as".

[max(div(int(parameters('instanceCount')), 5), 1)]

Value

asScaleValue

An object of S3 class vmss_config, that can be used by the create_vm_scaleset method.

See Also

```
scaleset_options for options relating to the scaleset resource itself
nsg_config, ip_config, vnet_config, lb_config, autoscaler_config for other resource configs
build_template for template builder methods
vm_config for configuring an individual virtual machine
create_vm_scaleset
```

Examples

```
# basic Linux (Ubuntu) and Windows configs
ubuntu_18.04_ss()
windows_2019_ss()

# Windows DSVM scaleset, no load balancer and autoscaler
windows_dsvm_ss(load_balancer=NULL, autoscaler=NULL)

# RHEL VM exposing ports 80 (HTTP) and 443 (HTTPS)
rhel_8_ss(nsg=nsg_config(nsg_rule_allow_http, nsg_rule_allow_https))
```

```
# exposing no ports externally
rhel_8_ss(nsg=nsg_config(list()))

# low-priority (spot) VMs, large scaleset (>100 instances allowed), no managed identity
rhel_8_ss(options=scaleset_options(priority="spot", large_scaleset=TRUE, managed_identity=FALSE))

## Not run:

# reusing existing resources: placing a scaleset in an existing vnet/subnet
# we don't need a new network security group either
vnet <- AzureRMR::get_azure_login()$
    get_subscription("sub_id")$
    get_resource_group("rgname")$
    get_resource(type="Microsoft.Network/virtualNetworks", name="myvnet")

ubuntu_18.04_ss(vnet=vnet, nsg=NULL)

## End(Not run)</pre>
```

create_vm

Create a new virtual machine or scaleset of virtual machines

Description

Method for the AzureRMR::az_subscription and AzureRMR::az_resource_group classes.

Arguments

- name: The name of the VM or scaleset.
- location: For the subscription methods, the location for the VM or scaleset. Use the list_locations() method of the AzureRMR::az_subscription class to see what locations are available.
- resource_group: For the subscription methods, the resource group in which to place the VM or scaleset. Defaults to a new resource group with the same name as the VM.
- login_user: The details for the admin login account. An object of class user_config, obtained by a call to the user_config function.
- size: The VM (instance) size. Use the list_vm_sizes method to see what sizes are available.
- config: The VM or scaleset configuration. See 'Details' below for how to specify this. The default is to use an Ubuntu Data Science Virtual Machine.
- managed_identity: For create_vm, whether the VM should have a managed identity attached.
- datadisks: Any data disks to attach to the VM or scaleset. See 'Details' below.
- instances: For create_vm_scaleset, the initial number of instances in the scaleset.
- ... For the subscription methods, any of the other arguments listed here, which will be passed to the resource group method. For the resource group method, additional arguments to pass to the VM/scaleset configuration functions vm_config and vmss_config. See the examples below.
- template, parameters: The template definition and parameters to deploy. By default, these are constructed from the values of the other arguments, but you can supply your own template and/or parameters as well.
- wait: Whether to wait until the deployment is complete.
- mode: The template deployment mode. If "Complete", any existing resources in the resource group will be deleted.

Details

These methods deploy a template to create a new virtual machine or scaleset.

The config argument can be specified in the following ways:

- As the name of a supplied VM or scaleset configuration, like "ubuntu_dsvm" or "ubuntu_dsvm_ss".
 AzureVM comes with a number of supplied configurations to deploy commonly used images, which can be seen at vm_config and vmss_config. Any arguments in . . . will be passed to the configuration, allowing you to customise the deployment.
- As a call to the vm_config or vmss_config functions, to deploy a custom VM image.
- As an object of class vm_config or vmss_config.

The data disks for the VM can be specified as either a vector of numeric disk sizes in GB, or as a list of datadisk_config objects, created via calls to the datadisk_config function. Currently, AzureVM only supports creating data disks at deployment time for single VMs, not scalesets.

You can also supply your own template definition and parameters for deployment, via the template and parameters arguments. See AzureRMR::az_template for information how to create templates.

The AzureRMR::az_subscription methods will by default create the VM in *exclusive* mode, meaning a new resource group is created solely to hold the VM or scaleset. This simplifies managing the VM considerably; in particular deleting the resource group will also automatically delete all the deployed resources.

Value

For create_vm, an object of class az_vm_template representing the created VM. For create_vm_scaleset, an object of class az_vmss_template representing the scaleset.

See Also

```
az_vm_template, az_vmss_template
vm_config, vmss_config, user_config, datadisk_config
AzureRMR::az_subscription, AzureRMR::az_resource_group, Data Science Virtual Machine
```

Examples

```
## Not run:
sub <- AzureRMR::get_azure_login()$</pre>
    get_subscription("subscription_id")
# default Ubuntu 18.04 VM:
# SSH key login, Standard_DS3_v2, publicly accessible via SSH
sub$create_vm("myubuntuvm", user_config("myname", "~/.ssh/id_rsa.pub"),
              location="australiaeast")
# Windows Server 2019, with a 500GB datadisk attached, not publicly accessible
sub$create_vm("mywinvm", user_config("myname", password="Use-strong-passwords!"),
              size="Standard_DS4_v2", config="windows_2019", datadisks=500, ip=NULL,
              location="australiaeast")
# Ubuntu DSVM, GPU-enabled
sub$create_vm("mydsvm", user_config("myname", "~/.ssh/id_rsa.pub"), size="Standard_NC12",
              config="ubuntu_dsvm_ss",
              location="australiaeast")
## custom VM configuration: Windows 10 Pro 1903 with data disks
## this assumes you have a valid Win10 desktop license
user <- user_config("myname", password="Use-strong-passwords!")</pre>
image <- image_config(</pre>
     publisher="MicrosoftWindowsDesktop",
     offer="Windows-10",
     sku="19h1-pro"
datadisks <- list(</pre>
    datadisk_config(250, type="Premium_LRS"),
    datadisk_config(1000, type="Standard_LRS")
nsg <- nsg_config(</pre>
```

```
list(nsg_rule_allow_rdp)
)
config <- vm_config(</pre>
   image=image,
   keylogin=FALSE,
    datadisks=datadisks,
   properties=list(licenseType="Windows_Client")
sub$create_vm("mywin10vm", user, size="Standard_DS2_v2", config=config,
              location="australiaeast")
# default Ubuntu scaleset:
# load balancer and autoscaler enabled, Standard_DS1_v2
sub$create_vm_scaleset("mydsvmss", user_config("myname", "~/.ssh/id_rsa.pub"),
                       instances=5,
                       location="australiaeast"))
# Ubuntu DSVM scaleset with public GPU-enabled instances, no load balancer or autoscaler
sub$create_vm_scaleset("mydsvmss", user_config("myname", "~/.ssh/id_rsa.pub"),
                       instances=5, size="Standard_NC12", config="ubuntu_dsvm_ss",
                       options=scaleset_options(public=TRUE),
                       load_balancer=NULL, autoscaler=NULL,
                       location="australiaeast")
# RHEL scaleset, allow http/https access
sub$create_vm_scaleset("myrhelss", user_config("myname", "~/.ssh/id_rsa.pub"),
                        instances=5, config="rhel_8_ss",
                        nsg=nsg_config(list(nsg_rule_allow_http, nsg_rule_allow_https)),
                        location="australiaeast")
# Large Debian scaleset, using low-priority (spot) VMs
# need to set the instance size to something that supports low-pri
sub$create_vm_scaleset("mydebss", user_config("myname", "~/.ssh/id_rsa.pub"),
                   instances=50, size="Standard_DS3_v2", config="debian_9_backports_ss",
                       options=scaleset_options(priority="spot", large_scaleset=TRUE),
                       location="australiaeast")
## VM and scaleset in the same resource group and virtual network
# first, create the resgroup
rg <- sub$create_resource_group("rgname", "australiaeast")</pre>
# create the master
rg$create_vm("mastervm", user_config("myname", "~/.ssh/id_rsa.pub"))
# get the vnet resource
vnet <- rg$get_resource(type="Microsoft.Network/virtualNetworks", name="mastervm-vnet")</pre>
# create the scaleset
rg$create_vm_scaleset("slavess", user_config("myname", "~/.ssh/id_rsa.pub"),
                  instances=5, vnet=vnet, nsg=NULL, load_balancer=NULL, autoscaler=NULL)
```

28 delete_vm

```
## End(Not run)
```

defunct

Defunct methods

Description

Defunct methods

Usage

```
get_vm_cluster(...)
create_vm_cluster(...)
delete_vm_cluster(...)
```

These methods for the az_subscription and az_resource_group classes are defunct in AzureVM 2.0. To work with virtual machine clusters, call the get_vm_scaleset, create_vm_scaleset and delete_vm_scaleset methods instead.

delete_vm

Delete virtual machine

Description

Method for the AzureRMR::az_subscription and AzureRMR::az_resource_group classes.

get_vm 29

Arguments

- name: The name of the VM or scaleset.
- confirm: Whether to confirm the delete.
- free_resources: If this was a deployed template, whether to free all resources created during the deployment process.
- resource_group: For the AzureRMR::az_subscription method, the resource group containing the VM or scaleset.

Details

For the subscription methods, deleting the VM or scaleset will also delete its resource group.

See Also

```
create_vm, az_vm_template, az_vm_resource, AzureRMR::az_subscription, AzureRMR::az_resource_group
```

Examples

```
## Not run:
sub <- AzureRMR::get_azure_login()$
    get_subscription("subscription_id")
sub$delete_vm("myvm")
sub$delete_vm_scaleset("myscaleset")
## End(Not run)</pre>
```

get_vm

Get existing virtual machine(s)

Description

Method for the AzureRMR::az_subscription and AzureRMR::az_resource_group classes.

```
## R6 method for class 'az_subscription'
get_vm(name, resource_group = name)

## R6 method for class 'az_resource_group'
get_vm(name)

## R6 method for class 'az_subscription'
get_vm_scaleset(name, resource_group = name)
```

30 get_vm

```
## R6 method for class 'az_resource_group'
get_vm_scaleset(name)

## R6 method for class 'az_resource_group')
get_vm_resource(name)
get_vm_scaleset_resource(name)
```

Arguments

- name: The name of the VM or scaleset.
- resource_group: For the az_subscription methods, the resource group in which get_vm() and get_vm_scaleset() will look for the VM or scaleset. Defaults to the VM name.

Value

For get_vm(), an object representing the VM deployment. This will include other resources besides the VM itself, such as the network interface, virtual network, etc.

For get_vm_scaleset(), an object representing the scaleset deployment. Similarly to get_vm(), this includes other resources besides the scaleset.

For get_vm_resource() and get_vm_scaleset_resource(), the VM or scaleset resource itself.

See Also

az_vm_template, az_vm_resource, az_vmss_template, az_vmss_resource for the methods available for working with VMs and VM scalesets.

AzureRMR::az_subscription, AzureRMR::az_resource_group

Examples

```
## Not run:
sub <- AzureRMR::get_azure_login()$
    get_subscription("subscription_id")
sub$get_vm("myvirtualmachine")
sub$get_vm_scaleset("myscaleset")

rg <- sub$get_resource_group("rgname")
rg$get_vm("myothervirtualmachine")
rg$get_vm_scaleset("myotherscaleset")

## End(Not run)</pre>
```

ip_config 31

ip_config	Public IP address configuration
-----------	---------------------------------

Description

Public IP address configuration

Usage

```
ip_config(type = NULL, dynamic = NULL, ipv6 = FALSE,
  domain_name = "[parameters('vmName')]", ...)
```

Arguments

type	The SKU of the IP address resource: "basic" or "standard". If NULL (the default), this will be determined based on the VM's configuration.
dynamic	Whether the IP address should be dynamically or statically allocated. Note that the standard SKU only supports standard allocation. If NULL (the default) this will be determined based on the VM's configuration.
ipv6	Whether to create an IPv6 address. The default is IPv4.
domain_name	
	Other named arguments that will be treated as resource properties.

See Also

```
create_vm, vm_config, vmss_config
```

Examples

```
ip_config()
ip_config(type="basic", dynamic=TRUE)

# if you don't want a domain name associated with the IP address
ip_config(domain_name=NULL)
```

is_vm

Is an object an Azure VM

Description

Is an object an Azure VM

32 lb_config

Usage

```
is_vm(object)
is_vm_template(object)
is_vm_resource(object)
is_vm_scaleset(object)
is_vm_scaleset_template(object)
is_vm_scaleset_resource(object)
```

Arguments

object

an R object.

Value

is_vm and is_vm_template return TRUE for an object representing a virtual machine deployment (which will include other resources besides the VM itself).

is_vm_resource returns TRUE for an object representing the specific VM resource.

 $is_vm_scaleset \ and \ is_vm_scaleset_template \ return \ TRUE \ for \ an \ object \ representing \ a \ VM \ scaleset \ deployment.$

is_vm_scaleset_resource returns TRUE for an object representing the specific VM scaleset resource.

See Also

create_vm, create_vm_scaleset, az_vm_template, az_vm_resource, az_vmss_template, az_vmss_resource

lb_config

Load balancer configuration

Description

Load balancer configuration

```
lb_config(type = NULL, rules = list(), probes = list(), ...)
lb_probe(name, port, interval = 5, fail_on = 2, protocol = "Tcp")
lb_rule(name, frontend_port, backend_port = frontend_port,
    protocol = "Tcp", timeout = 5, floating_ip = FALSE, probe_name)
```

lb_rule_ssh 33

Arguments

	type	The SKU of the load balancer resource: "basic" or "standard". If NULL (the default), this will be determined based on the VM scaleset's configuration. Note that the load balancer SKU must be the same as that of its public IP address.
	rules	A list of load balancer rules, each obtained via a call to lb_rule.
	probes	A list of health checking probes, each obtained via a call to 1b_probe. There must be a probe corresponding to each rule.
		Other named arguments that will be treated as resource properties.
	name	For lb_rule, a name for the load balancing rule.
	port	For lb_probe, the port to probe.
	interval	For 1b_probe, the time interval between probes in seconds.
	fail_on	For lb_probe, the probe health check will fail after this many non-responses.
	protocol	For lb_probe and lb_rule, the protocol: either "Tcp" or "Ip".
frontend_port, backend_port For lb_rule, the ports for this rule.		
	timeout	The timeout interval for the rule. The default is 5 minutes.
	floating_ip	Whether to use floating IP addresses (direct server return). Only needed for specific scenarios, and when the frontend and backend ports don't match.
	probe_name	The name of the corresponding health check probe.

See Also

create_vm_scaleset, vmss_config, lb_rules for some predefined load balancing rules and probes

Examples

```
lb_config()
lb_config(type="basic")
lb_config(
    rules=list(lb_rule_ssh, lb_rule_rdp),
    probes=list(lb_probe_ssh, lb_probe_rdp)
)
```

Description

Load balancing rules

34 lb_rule_ssh

Usage

lb_rule_ssh

lb_rule_http

lb_rule_https

lb_rule_rdp

lb_rule_jupyter

lb_rule_rstudio

lb_rule_mssql

lb_rule_mssql_browser

lb_probe_ssh

lb_probe_http

lb_probe_https

lb_probe_rdp

lb_probe_jupyter

lb_probe_rstudio

lb_probe_mssql

lb_probe_mssql_browser

Format

Objects of class lb_rule and lb_probe.

An object of class lb_rule of length 2.

An object of class lb_rule of length 2.

An object of class 1b_rule of length 2.

An object of class lb_rule of length 2.

An object of class lb_rule of length 2.

An object of class lb_rule of length 2.

An object of class 1b_rule of length 2.

An object of class 1b_probe of length 2.

An object of class 1b_probe of length 2.

list_vm_sizes 35

```
An object of class 1b_probe of length 2.
```

An object of class 1b_probe of length 2.

Details

Some predefined load balancing objects, for commonly used ports. Each load balancing rule comes with its own health probe.

• HTTP: TCP port 80

• HTTPS: TCP port 443

• JupyterHub: TCP port 8000

• RDP: TCP port 3389

• RStudio Server: TCP port 8787

• SSH: TCP port 22

• SQL Server: TCP port 1433

• SQL Server browser service: TCP port 1434

See Also

lb_config

list_vm_sizes

List available VM sizes

Description

Method for the AzureRMR::az_subscription and AzureRMR::az_resource_group classes.

Usage

```
## R6 method for class 'az_subscription'
list_vm_sizes(location, name_only = FALSE)
## R6 method for class 'az_resource_group'
list_vm_sizes(name_only = FALSE)
```

Arguments

- location: For the subscription class method, the location/region for which to obtain available VM sizes.
- name_only: Whether to return only a vector of names, or all information on each VM size.

nic_config

Value

If name_only is TRUE, a character vector of names, suitable for passing to create_vm. If FALSE, a data frame containing the following information for each VM size: the name, number of cores, OS disk size, resource disk size, memory, and maximum data disks.

See Also

```
create_vm
```

Examples

```
## Not run:
sub <- AzureRMR::get_azure_login$
    get_subscription("subscription_id")
sub$list_vm_sizes("australiaeast")

# same output as above
rg <- sub$create_resource_group("rgname", location="australiaeast")
rg$list_vm_sizes()

## End(Not run)</pre>
```

nic_config

Network interface configuration

Description

Network interface configuration

Usage

```
nic_config(nic_ip = list(nic_ip_config()), ...)
nic_ip_config(name = "ipconfig", private_alloc = "dynamic",
    subnet = "[variables('subnetId')]",
    public_address = "[variables('ipId')]", ...)
```

Arguments

nic_ip For nic_config, a list of IP configuration objects, each obtained via a call to nic_ip_config.

Other named arguments that will be treated as resource properties.

For nic_ip_config, the name of the IP configuration.

Private_alloc
For nic_ip_config, the allocation method for a private IP address. Can be "dynamic" or "static".

nsg_config 37

subnet For nic_ip_config, the subnet to associate with this private IP address.

public_address For nic_ip_config, the public IP address. Defaults to the public IP address

created or used as part of this VM deployment. Ignored if the deployment does

not include a public address.

See Also

```
create_vm, vm_config
```

Examples

```
nic_config()
```

nsg_config

Network security group configuration

Description

Network security group configuration

Usage

```
nsg_config(rules = list(), ...)
nsg_rule(name, dest_port = "*", dest_addr = "*", dest_asgs = NULL,
    source_port = "*", source_addr = "*", source_asgs = NULL,
    access = "allow", direction = "inbound", protocol = "Tcp",
    priority = NULL)
```

Arguments

rules for nsg_config, a list of security rule objects, each obtained via a call to nsg_rule.

. . . Other named arguments that will be treated as resource properties.

name For nsg_rule, a name for the rule.

dest_port, dest_addr, dest_asgs

For nsg_rule, the destination port, address range, and application security groups

for a rule.

source_port, source_addr, source_asgs

For nsg_rule, the source port, address range, and application security groups

for a rule.

access For nsg_rule, the action to take: "allow" or "deny".

direction For nsg_rule, the direction of traffic: "inbound" or "outbound".

protocol For nsg_rule, the network protocol: either "Tcp" or "Udp".

priority For nsg_rule, the rule priority. If NULL, this will be set automatically by

AzureVM.

38 nsg_rule_allow_ssh

See Also

create_vm, vm_config, vmss_config, nsg_rules for some predefined security rules

Examples

```
nsg_config()
nsg_config(list(nsg_rule_allow_ssh)) # for Linux
nsg_config(list(nsg_rule_allow_rdp)) # for Windows
nsg_config(list(nsg_rule_allow_http, nsg_rule_allow_https))

# a custom rule
nsg_config(list(
    nsg_rule(
        name="whitelist",
        source_addr="114.198.100.0/24",
        access="allow",
        protocol="*"
    )
))
```

nsg_rule_allow_ssh

Network security rules

Description

Network security rules

```
nsg_rule_allow_ssh
nsg_rule_allow_http
nsg_rule_allow_https
nsg_rule_allow_rdp
nsg_rule_allow_jupyter
nsg_rule_allow_rstudio
nsg_rule_allow_mssql
nsg_rule_allow_mssql_browser
```

scaleset_options 39

Format

Objects of class nsg_rule.

An object of class nsg_rule of length 2.

Details

Some predefined network security rule objects, to unblock commonly used ports.

• HTTP: TCP port 80

• HTTPS: TCP port 443

• JupyterHub: TCP port 8000

• RDP: TCP port 3389

• RStudio Server: TCP port 8787

• SSH: TCP port 22

• SQL Server: TCP port 1433

• SQL Server browser service: TCP port 1434

See Also

nsg_config

scaleset_options

Virtual machine scaleset options

Description

Virtual machine scaleset options

```
scaleset_options(keylogin = TRUE, managed_identity = TRUE,
public = FALSE, priority = c("regular", "spot"),
delete_on_evict = FALSE, network_accel = FALSE, large_scaleset = FALSE,
overprovision = TRUE, upgrade_policy = list(mode = "manual"),
os_disk_type = c("Premium_LRS", "StandardSSD_LRS", "Standard_LRS"))
```

40 user_config

Arguments

keylogin Whether to use an SSH public key to login (TRUE) or a password (FALSE).

Note that Windows does not support SSH key logins.

managed_identity

Whether to provide a managed system identity for the VM.

public Whether the instances (nodes) of the scaleset should be visible from the public

internet.

priority The priority of the VM scaleset, either regular or spot. Spot VMs are consid-

erably cheaper but subject to eviction if other, higher-priority workloads require

compute resources.

delete_on_evict

If spot-priority VMs are being used, whether evicting (shutting down) a VM

should delete it, as opposed to just deallocating it.

network_accel Whether to enable accelerated networking. This option is only available for

certain VM sizes.

large_scaleset Whether to enable scaleset sizes > 100 instances.

overprovision Whether to overprovision the scaleset on creation.

upgrade_policy A list, giving the VM upgrade policy for the scaleset.

os_disk_type The type of primary disk for the VM. Change this to "StandardSSD_LRS" or

"Standard_LRS" if the VM size doesn't support premium storage.

user_config

Resource configuration functions for a virtual machine deployment

Description

Resource configuration functions for a virtual machine deployment

```
user_config(username, sshkey = NULL, password = NULL)

datadisk_config(size, name = "datadisk", create = "empty",
   type = c("StandardSSD_LRS", "Premium_LRS", "Standard_LRS", "UltraSSD_LRS"),
   write_accelerator = FALSE)

image_config(publisher = NULL, offer = NULL, sku = NULL,
   version = "latest", id = NULL)
```

user_config 41

Arguments

username For user_config, the name for the admin user account.

sshkey For user_config, the SSH public key. This can be supplied in a number of

ways: as a string with the key itself; the name of the public key file; or an AzureRMR::az_resource object pointing to an SSH public key resource (of

type "Microsoft.Compute/sshPublicKeys"). See the examples below.

password For user_config, the admin password. Supply either sshkey or password, but

not both; also, note that Windows does not support SSH logins.

size For datadisk_config, the size of the data disk in GB. St this to NULL for a

disk that will be created from an image.

name For datadisk_config, the disk name. Duplicate names will automatically be

disambiguated prior to VM deployment.

create For datadisk_config, the creation method. Can be "empty" (the default) to

create a blank disk, or "fromImage" to use an image.

type For datadisk_config, the disk type (SKU). Can be "Standard_LRS", "Stan-

dardSSD_LRS" (the default), "Premium_LRS" or "UltraSSD_LRS". Of these, "Standard_LRS" uses hard disks and the others use SSDs as the underlying hard-

ware.

write_accelerator

For datadisk_config, whether the disk should have write acceleration enabled.

publisher, offer, sku, version

For image_config, the details for a marketplace image.

id For image_config, the resource ID for a disk to use as a custom image.

Examples

```
## Not run:
## user_config: SSH public key resource in Azure
# create the resource
keyres <- rg$create_resource(type="Microsoft.Compute/sshPublicKeys", name="mysshkey")

# generate the public and private keys
keys <- keyres$do_operation("generateKeyPair", http_verb="POST")
keyres$sync_fields()

# save the private key (IMPORTANT)
writeBin(keys$privateKey, "mysshkey.pem")

# create a new VM using the public key resource for authentication
# you can then login to the VM with ssh -i mysshkey.pem <username@vmaddress>
rg$create_vm("myvm", user_config("username", sshkey=keyres), config="ubuntu_20.04")

## user_config: SSH public key as a file
rg$create_vm("myvm", user_config("username", sshkey="mysshkey.pub"), config="ubuntu_20.04")
```

vnet_config

```
## user_config: SSH public key as a string (read from a file)
pubkey <- readLines("mysshkey.pub")
rg$create_vm("myvm", user_config("username", sshkey=pubkey), config="ubuntu_20.04")
## End(Not run)</pre>
```

vnet_config

Virtual network configuration

Description

Virtual network configuration

Usage

```
vnet_config(address_space = "10.0.0.0/16", subnets = list(subnet_config()),
    ...)
subnet_config(name = "subnet", addresses = "10.0.0.0/16",
    nsg = "[variables('nsgId')]", ...)
```

Arguments

address_space	For vnet_config, the address range accessible by the virtual network, expressed in CIDR block format.
subnets	For vnet_config, a list of subnet objects, each obtained via a call to subnet_config.
	Other named arguments that will be treated as resource properties.
name	For subnet_config, the name of the subnet. Duplicate names will automatically be disambiguated prior to VM deployment.
addresses	For subnet_config, the address ranges spanned by this subnet. Must be a subset of the address space available to the parent virtual network.
nsg	The network security group associated with this subnet. Defaults to the NSG created as part of this VM deployment.

See Also

```
create_vm, vm_config, vmss_config
```

Examples

Index

```
* datasets
                                                 centos_8.1_ss (centos_7.5_ss), 18
    lb_rule_ssh, 33
                                                 create_vm, 11, 12, 17, 24, 29, 31, 32, 36-38,
    nsg_rule_allow_ssh, 38
                                                         42
                                                 create_vm_cluster (defunct), 28
autoscaler_config, 2, 23
                                                 create_vm_scaleset, 3, 7, 23, 28, 32, 33
autoscaler_profile (autoscaler_config),
                                                 create_vm_scaleset (create_vm), 24
az_vm_resource, 4, 6, 8, 10, 29, 30, 32
                                                 datadisk_config, 17, 26
az_vm_template, 9, 9, 26, 29, 30, 32
                                                 datadisk_config (user_config), 40
az_vmss_resource, 3, 7, 30, 32
                                                 debian_10_backports (centos_7.5), 13
az_vmss_template, 5, 5, 26, 30, 32
                                                 debian_10_backports_gen2 (centos_7.5),
AzureRMR::az_resource, 4, 5, 7-10
                                                         13
AzureRMR::az_resource_group, 24, 26,
                                                 debian_10_backports_gen2_ss
        28–30, 35
                                                         (centos_7.5_ss), 18
                                                 debian_10_backports_ss (centos_7.5_ss),
AzureRMR::az_subscription, 24, 26, 28-30,
        35
                                                 debian_8_backports (centos_7.5), 13
AzureRMR::az_template, 4, 6, 7, 10, 11, 25
AzureRMR::init_pool, 5, 7
                                                 debian_8_backports_ss (centos_7.5_ss),
build_template, 17, 23
                                                 debian_9_backports (centos_7.5), 13
build_template
                                                 debian_9_backports_ss (centos_7.5_ss),
        (build_template_definition.vm_config),
                                                         18
                                                 defunct, 28
build_template_definition.vm_config,
                                                 delete_vm, 11, 28
                                                 delete_vm_cluster (defunct), 28
build_template_definition.vmss_config
                                                 delete_vm_scaleset, 7, 28
        (build_template_definition.vm_config),delete_vm_scaleset (delete_vm), 28
        11
build_template_parameters.vm_config
                                                get_vm, 11, 29
        (build_template_definition.vm_config),get_vm_cluster (defunct), 28
                                                 get_vm_resource, 9
build_template_parameters.vmss_config
                                                 get_vm_resource (get_vm), 29
        (build_template_definition.vm_config),get_vm_scaleset, 7, 28
        11
                                                 get_vm_scaleset (get_vm), 29
                                                 get_vm_scaleset_resource, 5
centos_7.5, 13
                                                 get_vm_scaleset_resource (get_vm), 29
centos_7.5_ss, 18
centos_7.6 (centos_7.5), 13
                                                 image_config, 17
centos_7.6_ss (centos_7.5_ss), 18
                                                 image_config (user_config), 40
                                                 ip_config, 17, 23, 31
centos_8.1 (centos_7.5), 13
```

44 INDEX

$is_vm, 31$	nsg_rules, 38
<pre>is_vm_resource(is_vm), 31</pre>	<pre>nsg_rules (nsg_rule_allow_ssh), 38</pre>
<pre>is_vm_scaleset(is_vm), 31</pre>	
<pre>is_vm_scaleset_resource(is_vm), 31</pre>	rhel_7.6 (centos_7.5), 13
<pre>is_vm_scaleset_template(is_vm), 31</pre>	rhel_7.6_ss (centos_7.5_ss), 18
<pre>is_vm_template(is_vm), 31</pre>	rhel_8 (centos_7.5), 13
	rhel_8.1_gen2_ss (centos_7.5_ss), 18
lb_config, 23, 32, 35	rhel_8.1_ss (centos_7.5_ss), 18
lb_probe(lb_config), 32	rhel_8.2_gen2_ss (centos_7.5_ss), 18
<pre>lb_probe_http (lb_rule_ssh), 33</pre>	rhel_8.2_ss (centos_7.5_ss), 18
<pre>lb_probe_https (lb_rule_ssh), 33</pre>	rhel_8_ss (centos_7.5_ss), 18
<pre>lb_probe_jupyter(lb_rule_ssh), 33</pre>	
<pre>lb_probe_mssql (lb_rule_ssh), 33</pre>	scaleset_options, 23, 39
<pre>lb_probe_mssql_browser(lb_rule_ssh), 33</pre>	<pre>subnet_config (vnet_config), 42</pre>
lb_probe_rdp (lb_rule_ssh), 33	1 1 10 04 (1 7 5) 10
<pre>lb_probe_rstudio (lb_rule_ssh), 33</pre>	ubuntu_16.04 (centos_7.5), 13
lb_probe_ssh (lb_rule_ssh), 33	ubuntu_16.04_ss (centos_7.5_ss), 18
lb_rule(lb_config), 32	ubuntu_18.04 (centos_7.5), 13
<pre>lb_rule_http(lb_rule_ssh), 33</pre>	ubuntu_18.04_ss (centos_7.5_ss), 18
<pre>lb_rule_https (lb_rule_ssh), 33</pre>	ubuntu_20.04 (centos_7.5), 13
<pre>lb_rule_jupyter(lb_rule_ssh), 33</pre>	ubuntu_20.04_gen2 (centos_7.5), 13
<pre>lb_rule_mssql (lb_rule_ssh), 33</pre>	ubuntu_20.04_gen2_ss (centos_7.5_ss), 18
<pre>lb_rule_mssql_browser (lb_rule_ssh), 33</pre>	ubuntu_20.04_ss (centos_7.5_ss), 18
<pre>lb_rule_rdp (lb_rule_ssh), 33</pre>	ubuntu_dsvm (centos_7.5), 13
<pre>lb_rule_rstudio(lb_rule_ssh), 33</pre>	ubuntu_dsvm_gen2 (centos_7.5), 13
lb_rule_ssh, 33	ubuntu_dsvm_gen2_ss (centos_7.5_ss), 18
lb_rules, <i>33</i>	ubuntu_dsvm_ss (centos_7.5_ss), 18
lb_rules (lb_rule_ssh), 33	user_config, <i>17</i> , <i>26</i> , 40
list_vm_sizes, 25, 35	vm config 12 22 25 26 21 27 28 42
	vm_config, 12, 23, 25, 26, 31, 37, 38, 42
nic_config, <i>17</i> , 36	vm_config (centos_7.5), 13
<pre>nic_ip_config (nic_config), 36</pre>	vmss_config, 3, 12, 17, 25, 26, 31, 33, 38, 42
nsg_config, <i>17</i> , <i>23</i> , <i>37</i> , <i>39</i>	vmss_config (centos_7.5_ss), 18
nsg_rule (nsg_config), 37	vnet_config, <i>17</i> , <i>23</i> , 42
nsg_rule_allow_http	windows_2016 (centos_7.5), 13
(nsg_rule_allow_ssh), 38	windows_2016_ss (centos_7.5_ss), 18
nsg_rule_allow_https	windows_2019 (centos_7.5), 13
(nsg_rule_allow_ssh), 38	windows_2019_gen2 (centos_7.5), 13
nsg_rule_allow_jupyter	windows_2019_gen2_ss (centos_7.5_ss), 18
(nsg_rule_allow_ssh), 38	windows_2019_ss (centos_7.5_ss), 18
nsg_rule_allow_mssql	windows_dsvm (centos_7.5), 13
(nsg_rule_allow_ssh), 38	windows_dsvm_ss (centos_7.5_ss), 18
nsg_rule_allow_mssql_browser	WINGONS_USVIN_SS (CENTESS_7.5_SS), 18
(nsg_rule_allow_ssh), 38	
nsg_rule_allow_rdp	
(nsg_rule_allow_ssh), 38	
nsg_rule_allow_rstudio	
(nsg_rule_allow_ssh), 38	
nsg_rule_allow_ssh, 38	