Package 'ROptimus'

January 10, 2023

salidary 10, 2023
Title A Parallel General-Purpose Adaptive Optimisation Engine
Version 3.0.0
Description A general-purpose optimisation engine that supports i) Monte Carlo optimisation with Metropolis criterion [Metropolis et al. (1953) <doi:10.1063 1.1699114="">, Hastings (1970) <doi:10.1093 57.1.97="" biomet="">] and Acceptance Ratio Simulated Annealing [Kirk-patrick et al. (1983) <doi:10.1126 science.220.4598.671="">, Černý (1985) <doi:10.1007 bf00940812="">] on multiple cores, and ii) Acceptance Ratio Replica Exchange Monte Carlo Optimisation. In each case, the system pseudo-temperature is dynamically adjusted such that the observed acceptance ratio is kept near to the desired (fixed or changing) acceptance ratio.</doi:10.1007></doi:10.1126></doi:10.1093></doi:10.1063>
License GPL (>= 3)
Encoding UTF-8
RoxygenNote 7.2.3
Imports doParallel (>= 1.0.11), foreach (>= 1.4.4), iterators (>= 1.0.9), parallel (>= 3.4.2)
Depends R (>= $3.1.0$)
LazyData true
<pre>URL https://github.com/SahakyanLab/ROptimus</pre>
NeedsCompilation no
Author Nicholas Andre G. Johnson [aut], Liezel Tamon [aut], Xin Liu [aut], Aleksandr B. Sahakyan [aut, cre]
Maintainer Aleksandr B. Sahakyan <sahakyanlab@cantab.net></sahakyanlab@cantab.net>
Repository CRAN
Date/Publication 2023-01-10 13:20:05 UTC
R topics documented:
ex m fun

	ex.u.fun				
Index					8
ex.m.	fun	Tutorial 5 m() function	ı		
		l to Optimus() for repro	oducing Tutorial	5. This is for th	e small executable
Usage					
ex.	m.fun				
Format					
Fun	ction				

ex.r.fun

Description

ex.r.fun

2

The r() function supplied to Optimus() for reproducing Tutorial 5. This is for the small executable example.

Tutorial 5 r() function

Usage

ex.r.fun

Format

Function

ex.u.fun 3

ex.u.fun

Tutorial 5 u() function

Description

The u() function supplied to Optimus() for reproducing Tutorial 5. This is for the small executable example.

Usage

ex.u.fun

Format

Function

IJ_ORIG

Tutorial 5 Genomic Contact Data

Description

A dataset containing 734 genomic contact pairs for reproducing Tutorial 5. Here, we take a set of 734 pairs of i and j 40-kilobase DNA regions that are known to be in contact inside a cell. Binning the DNA (e.g., a single chromosome) into 40-kb regions, each region is represented as a single integer that is equal to its end position divided by the length of the region, which is 40 kb. For instance, the 1st region, with start and end positions at the 1st and 40000th nucleotides, respectively, is denoted as 1 (40000th base / 40000 bases = 1). This simplifies the notation for a contact between two regions to a pair of positive integers as in used in this dataset.

Usage

IJ_ORIG

Format

A data frame with 734 rows and 2 variables:

- i Integer representing 40-kb contact region partner of j
- j Integer representing 40-kb contact region partner of i

4 Optimus

Optimus

Acceptance Ratio Simulated Annealing and Acceptance Ratio Replica Exchange Monte Carlo Optimisation Engine

Description

Acceptance Ratio Simulated Annealing and Acceptance Ratio Replica Exchange Monte Carlo Optimisation Engine

Usage

```
Optimus(
 NUMITER = 1e+06,
 STATWINDOW = 70,
 T.INI = 1e-05,
 T.ADJSTEP = 5e-09,
 TSCLnum = 2,
 T.SCALING = 3,
 T.MIN = 5e-09,
 T.DELTA = 2,
 DUMP.FREQ = 10000,
 LIVEPLOT = TRUE,
 LIVEPLOT.FREQ = 1e+05,
 PDFheight = 29,
 PDFwidth = 20,
 NCPU = 4,
 LONG = TRUE,
  SEED = 840,
 OPTNAME = "",
 DATA = NULL,
 K.INITIAL = 0,
  rDEF,
 mDEF,
 uDEF,
 EXCHANGE.FREQ = 1000,
 ACCRATIO = c(90, 50, 5, 1),
 CYCLES = 10,
 ACCRATIO.IN = 90,
 ACCRATIO.FIN = 0.5,
 OPT.TYPE = "SA",
 DIR,
  starcore = NULL
)
```

Arguments

NUMITER

Number of model optimisation steps.

Optimus 5

STATWINDOW Number of last ongoing iterations to calculate acceptance ratio for temperature auto-adjustment. T.INI Initial temperature (K) for Metropolis criterion. T.ADJSTEP Temperature change step-size for temperature auto-adjustment based on the actual acceptance ratio. **TSCLnum** Cutoff for one of the NumofAccRatSMIdeal and NumofAccRatGRIdeal numbers after which the adjustment step is multiplied by T.SCALING. T. SCALING See above. T.MIN Value to which the pseudo-temperature is set when the Minimum value by which acceptance ratio in a STATWINDOW must differ T.DELTA from the ideal acceptance ratio for the temperature control unit to make a temperature adjustment. DUMP.FREQ The frequency (in steps) of writing the found ongoing best model. LIVEPLOT Plotting the optimisation process in a pdf file. LIVEPLOT.FREQ Frequency (in steps) of plotting the results. **PDFheight** Plot height in inches. **PDFwidth** Plot width in inches. NCPU Number of CPU cores to use, by running more replicas of the optimisation. The usage of more than 1 cores will attempt to load the foreach and doParallel libraries in the case of SA Optimus LONG If TRUE, it means that a long simulation is expected to be done, hence the memory-friendly mode will be activated. **SEED** Setting the seed for the random number generator. **OPTNAME** The name of the optimisation process. DATA A list that holds any supplementary data that functions mDEF or uDEF need to K.INITIAL The initial parameter configuration from which the optimisation process will begin. rDEF Function that defines a rule by which the parameters(K) are randomly altered. **mDEF** Model function that operates on the parameters to be optimized (K) and returns an observable object O. uDEF Function that evaluates the performance of a given set of parameters K. EXCHANGE.FREQ Frequency of exchanges (NUMITER should be divisible by this number, for RE Optimus). **ACCRATIO** Vector of Acceptance Ratios for each replica (length of ACCRATIO must be equal to NCPU, for RE Optimus). **CYCLES** Number of annealing cycles (NUMITER should be divisible by this number, for SA Optimus). ACCRATIO. IN Initial acceptance ratio (%) at the beginning of each constituent annealing cycles

(for SA Optimus).

6 OptimusExamples

ACCRATIO.FIN	Final acceptance ratio (%) at the end of each constituent annealing cycles (for SA Optimus).
OPT.TYPE	String specifying which optimisation protocol to use. Enter "SA" for Simulated Annealing or "RE" for Replica Exchange (default value is "SA")
DIR	String specifying which optimisation protocol to use.
starcore	Experimental variable of type list, holding some parameters for in-lab starcore use only.

Value

A probabilistic optimal parameter configuration K.

Examples

OptimusExamples

Generate script for reproducing a tutorial

Description

Generate script for reproducing a tutorial

Usage

```
OptimusExamples(
   dir,
   example = 1,
   method = "SA",
   file_name = "example.R",
   mopac = NULL,
   vignette = TRUE
)
```

OptimusExamples 7

Arguments

dir String specifying directory where to save the script and vignette.

example Integer specifying tutorial or example number based on manual (default value is

1).

method String specifying which optimisation protocol to use. Enter "SA" for Simulated

Annealing or "RE" for Replica Exchange (default value is "SA").

file_name String specifying file name of script (default value is example.R).

mopac String specifying the path of the MOPAC (Molecular Orbital PACkage) exe-

cutable for tutorial 3 (Geometry Optimisation of Vitamin C Molecule) (default

value is NULL).

vignette If TRUE, add tutorial vignette to directory (default value is TRUE).

Value

A script (and optionally a vignette) for reproducing a tutorial.

Examples

```
out.dir <- tempdir()
OptimusExamples(dir=out.dir, example=1)</pre>
```

Index

```
* datasets
    ex.m.fun, 2
    ex.r.fun, 2
    ex.u.fun, 3
    IJ_ORIG, 3

ex.m.fun, 2
    ex.r.fun, 2
    ex.u.fun, 3

IJ_ORIG, 3

Optimus, 4
OptimusExamples, 6
```