Package 'HBSTM'

October 12, 2022

Type Package

Title Hierarchical Bayesian Space-Time Models for Gaussian Space-Time Data
Version 1.0.2
Author Pilar Munyoz, Alberto Lopez Moreno
Maintainer Alberto Lopez Moreno
Description Fits Hierarchical Bayesian space-Time models for Gaussian data. Furthermore, its functions have been implemented for analysing the fitting qualities of those models.
License GPL (>= 2.0)
Encoding UTF-8
LazyData true
Depends methods, MASS, fBasics, maps, stats, graphics, grDevices, utils
NeedsCompilation no
Repository CRAN
Date/Publication 2022-05-28 13:50:02 UTC
R topics documented:
HBSTM-package
Autoregressive-class
Autoregressive0-class
coordinates
estimation
hbstm
HBSTM-class
hbstm.fit
hirlam
Hyperpriors-class

2 HBSTM-package

HBSTN	1-package	Hie date	chi	ica	l E	Вау	esi	iar	ı S	pa	ісе	-Ti	im	e i	mo	ode	els	fo	r	Gα	เนร	ssic	an	sp	ac	:e-	tin	ıe
Index																												28
	Xt0-class		 					•							•									. .				27
	Xt-class																											
	VectSubdiag0-class																											
	VectSubdiag-class.																											
	SpatParam-class SpatParam0-class .																											
	Seas0-class																											
	Seas-class																											
	results		 																									19
	plotRes																											
	plotFit																											
	Parameters-class .																											
	Mu0-class		 																									1.5

Description

This package fits Hierarchical Bayesian space-Time models for Gaussian data. Furthermore, its functions have been implemented for analysing the fitting qualities of those models.

Details

Package: HBSTM Type: Package Version: 1.0

Date: 2013-12-24 License: GPL (>=2.0)

Depends: methods, MASS, msm, fBasics, maps

Author(s)

Pilar Munyoz and Alberto Lopez Moreno Maintainer: Alberto Lopez Moreno

 dertolomo@gmail.com>

See Also

Overview: HBSTM-package

 $Classes: \verb|HBSTM|, \verb|Parameters|, \verb|Mu|, \verb|Mt|, \verb|Xt|, \verb|Autoregressive|, Seas|, SpatParam|, VectSubdiag|, Hyperpriors|, Mu0|, Mt0|, Xt0|, Mt0|, Mt0$

Methods: hbstm, hbstm.fit, results, estimation, resid, mse

Plot:plotRes,plotFit

Autoregressive-class 3

Data: hirlam, coordinates

Autoregressive-class Class "Autoregressive"

Description

"Autoregressive" contains the parameter values of the autoregressive component, and it is an internal class stored in the class "Xt".

Slots

avect: An Sx1 "matrix" (S is the number of spatial points on the predicted grid) containing the temporal autoregressive parameter avect

a0vect: An Sx1 "matrix" containing the temporal autoregressive parameter a0vect

a0L: A 3x1 "matrix" containing the temporal autoregressive parameter a0L

spatialA: An object of class "SpatParam" containing the fitted values of the spatial parameters of avect.

sigma2A: Contains the fitted value of the variance sigma2A.

H: An SxS "matrix" containing all the autoregressive space-time parameters.

subdiag: An object of class "VectSubdiag" containing the fitted values of the space-time parameters.

Methods

```
[ signature(x = "Autoregressive", i = "character", j = "missing", drop = "missing"): extract the components of the model.
```

[<- signature(x = "Autoregressive", i = "character", j = "missing"): assign values to the components of the model.

Author(s)

Pilar Munyoz and Alberto Lopez Moreno

See Also

Overview: HBSTM-package

 $Classes: \verb|HBSTM|, \verb|Parameters|, \verb|Mu|, \verb|Mt|, \verb|Xt|, \verb|Autoregressive|, Seas|, SpatParam|, \verb|VectSubdiag|, Hyperpriors|, Mu0|, Mt0|, Xt0|, Mt0|, M$

Methods: hbstm, hbstm.fit, results, estimation, resid, mse

Plot: plotRes, plotFit
Data: hirlam, coordinates

Autoregressive0-class

Autoregressive0-class Class "Autoregressive0"

Description

"Autoregressive0" contains the hyperprior values of the autoregressive component, and it is an internal class stored in the class "Xt0".

Slots

a0L0: A "vector" of length 3 with the mean hyperprior values of the parameter a0L.

siga0L0: A "matrix" of dimension 3X3 with the hyperprior variance of the parameter a0L.

sigma2A0: A "vector" of length 2 with the hyperprior values of the parameter sigma2A.

spatial A0: An object of class "SpatParam0" containing the hyperprior values of the spatial parameters of avector

subdiag0: An object of class "VectSubdiag0" containing the hyperprior values of the spatial-temporal parameters.

Methods

```
[ signature(x = "Autoregressive0", i = "character", j = "missing", drop = "missing"): extract the components of the model.
```

[<- signature(x = "Autoregressive0", i = "character", j = "missing"): assign values to the components of the model.

Author(s)

Pilar Munyoz and Alberto Lopez Moreno

See Also

Overview: HBSTM-package

Classes: HBSTM, Parameters, Mu, Mt, Xt, Autoregressive, Seas, SpatParam, VectSubdiag, Hyperpriors, Mu0, Mt0, Xt0,

Methods: hbstm, hbstm.fit, results, estimation, resid, mse

Plot: plotRes, plotFit
Data: hirlam, coordinates

coordinates 5

coordinates	Coordinates of the dataset "hirlam"
Cool aillates	Coordinates of the dataset nitrain

Description

The coordinates data is a data set that contains the spatial coordinates of the space-time data hirlam.

Format

A data frame with 70 observations on the following 2 variables.

Longitude the longitude coordinates.

Latitude the latitude coordinates.

estimation

Estimation of the median parameters

Description

Estimates the median parameters of an object of class HBSTM.

Usage

```
estimation(object,digits)
```

Arguments

object an object of class "HBSTM".

digits integer indicating the number of decimal places to round the median values.

Details

In caste the MCMC samples of the object parameter are a specific component of the model, the others components have value -9999999.

Value

Returns an object of class Parameters with the median estimation of the parameters MCMC samples.

Author(s)

Pilar Munyoz and Alberto Lopez Moreno

6 hbstm

See Also

Overview: HBSTM-package

Classes: HBSTM, Parameters, Mu, Mt, Xt, Autoregressive, Seas, SpatParam, VectSubdiag, Hyperpriors, Mu0, Mt0, Xt0,

Methods: hbstm, hbstm.fit, results, estimation, resid, mse

Plot: plotRes, plotFit
Data: hirlam, coordinates

Examples

See 'tutorial.pdf', included in the documentation of the package, to see a full example

hbstm

Fitting Hierarchical Bayesian Space Time models

Description

hbstm is used to fit Hierarchical Bayesian Space Time models.

Usage

hbstm(Zt,K,newGrid,reglag,seas,spatlags,hyperpriors,initialvalues, nIter,nBurn,fit,plots,posterior,save,control)

Arguments

Zt :]	MxT	"data.	frame"	containing	the data.	The rows	contains	the	"M"	spatial
--------	-----	--------	--------	------------	-----------	----------	----------	-----	-----	---------

points and the columns the "T" temporal observations.

K: MxS "matrix" that relates the observed spatial points with the new Grid. S is

the number of predicted spatial points.

newGrid An Sx2 "data.frame" containing the "Longitude" and the "Latitude" of the

new Grid.

reglag A vector containing the temporal autoregressive lags of the model.

seas A vector containing the seasonal coefficients of the model.

spatlags A vector of length 4 containing the spatial lags of the model. See details for

more information.

hyperpriors An object of class Hyperpriors containing all the values of the model hyper-

nriors

initial values An object of class Parameters containing all the initial values of the model

parameters.

nIter Number of Gibbs Sampling iterations. Default value is 1000.

nBurn Number of burn-in samples. This number of samples will be discarded before

making any inference. Default value is the 20 percent of nIter.

fit A "logical" indicating whether the HBSTM is fitted.

hbstm 7

plots A "logical" indicating whether the method shows the plots of the execution

(The mse, Zt vs X*Yt and the ACF/PACF of the residuals.

posterior A "character" indicating whether the function returns the 'mean' and 'sd' the

fitted values of Yt or returns the 'median' with its 95 percent credibility intervals.

save A "character" indicating if, for each iteration, the algorithm saves the estima-

tion of certain parameters. See "Details"s for more information.

control a list of control parameters. See "Details".

Details

Each position of the argument spatlags refers to the spatial lags of a specified direction. These four directions are "east-west", "north-south", "north-west-southeast" and "northeast-southwest".

The save argument is a "character" that can have any of the following options:

-"all": Save an object of class Parameters.

-"Mu": Save an object of class Mu.

-"Mt": Save an object of class Mt.

-"Xt": Save an object of class Xt.

The control argument is a list that can supply any of the following components:

- -time: A "logical" indicating whether the method shows the estimated time of execution.
- -timerem: A "logical" indicating whether the method shows the estimated remaining time of execution
- -seed: The seed to use in the function "set.seed" and set it to fit the model.

Value

hbstm returns an object of class HBSTM

Author(s)

Pilar Munyoz and Alberto Lopez Moreno

See Also

Overview: HBSTM-package

Classes: HBSTM, Parameters, Mu, Mt, Xt, Autoregressive, Seas, SpatParam, VectSubdiag, Hyperpriors, Mu0, Mt0, Xt0,

Methods: hbstm, hbstm.fit, results, estimation, resid, mse

Plot: plotRes, plotFit
Data: hirlam, coordinates

Examples

See 'tutorial.pdf', included in the documentation of the package, to see a full example

8 HBSTM-class

HBSTM-class

Class "HBSTM"

Description

"HBSTM" contains all the information of the fitted Hierarchical Bayesian Space-Time model.

Slots

Parameters: An object of "Parameters" containing all the parameters of the fitted model.

Hyperpriors: An object of class "Hyperpriors" containing all the hyperpiors used in the fitted model.

seed: The seed used to fit the model.

mse: A vector containing the MSE of each iteration of the algorithm.

iterations: The total number of iterations that the algorithm has executed.

newGrid: An Sx2 "matrix" (S is the number of spatial points of the predicted grid) containing the Longitude (1rst col.) and the Latitudes (2nd col.) of the new grid.

K: An MxS "matrix" (M = observed spatial points) that relates the observations to the new grid.

Zt: A MxT "matrix" (T is the temporal points) containing the data.

fitted: An "array" which contains the estimation of the fitted values of 'Yt'. The dimension of the array is SxTx2 when the algorithm estimates the mean and the standard deviation and is SxTx3 when the algorithm estimates the median and its 95 percent credibility intervals.

residuals: A MxT "matrix" with the obtained model residuals.

MCMCsamp: A "list" of length: the number of executed iterations containing the MCMC samples of the objects of class "Parameters", "Mu", "Mt" or "Xt", for each iteration.

MCMCclass: A "character" that specifies which type of object is stored in MCMCsamp. The options are "Parameters", "Mu", "Mt" or "Xt"

Methods

```
[ signature(x = "HBSTM", i = "character", j = "missing", drop = "missing"): extract the components of the model.
```

[<- signature(x = "HBSTM", i = "character", j = "missing"): assign values to the components of the model.

```
hbstm.fit signature(HBSTM = "HBSTM", niter = "numeric"): ...
```

hbstm.save signature(HBSTM = "HBSTM", name = "character"): ...

Author(s)

Pilar Munyoz and Alberto Lopez Moreno

hbstm.fit 9

See Also

Overview: HBSTM-package

 $Classes: \verb|HBSTM|, \verb|Parameters|, \verb|Mu|, \verb|Mt|, \verb|Xt|, \verb|Autoregressive|, Seas|, SpatParam|, VectSubdiag|, Hyperpriors|, Mu0|, Mt0|, Xt0|, Mt0|, Mt0$

Methods: hbstm, hbstm.fit, results, estimation, resid, mse

Plot: plotRes, plotFit
Data: hirlam, coordinates

hbstm.fit

Fitted function for Hierarchical Bayesian Space Time models

Description

This is the basic computing engine that hbstm uses to fit Hierarchical Bayesian Space Time models. In general, this should not be used directly, unless by experienced users.

Usage

hbstm.fit(HBSTM, nIter, nBurn, time, timerem, plots, posterior, save)

Arguments

HBSTM	An object of class "HBSTM".
nIter	Number of Gibbs Sampling iterations. Default value is 1000.
nBurn	Number of burn-in samples. This number of samples will be discarded before making any inference. Default value is the 20 percent of nIter.
time	A "logical" indicating whether the method shows the estimated time of execution.
timerem	A "logical" indicating whether the method shows the estimated remaining time of execution.
plots	A "logical" indicating whether the method shows the plots of the execution (the mse, Zt vs K*Yt and the ACF/PACF of the residuals.
posterior	A "character" indicating whether the function returns the mean and the standard deviation of the fitted values of Yt or returns the median with its 95 percent credibility intervals.
save	A "character" indicating if, for each iteration, the algorithm save the estimation of certain parameters. See "Details" for more information.

Details

The save argument is a "character" that can have any of the following options:

- -"all": Save an object of class Parameters.
- -"Mu": Save an object of class Mu.
- -"Mt": Save an object of class Mt.
- -"Xt": Save an object of class Xt.

10 hirlam

Value

hbstm.fit returns an object of class HBSTM

Author(s)

Pilar Munyoz and Alberto Lopez Moreno

See Also

Overview: HBSTM-package

 $\pmb{Classes: \texttt{HBSTM}, Parameters, \texttt{Mu}, \texttt{Mt}, \texttt{Xt}, \texttt{Autoregressive}, \texttt{Seas}, \texttt{SpatParam}, \texttt{VectSubdiag}, \texttt{Hyperpriors}, \texttt{Mu0}, \texttt{Mt0}, \texttt{Xt0}, \texttt{Mt0}, \texttt{Xt0}, \texttt{Mt0}, \texttt{Mt$

Methods: hbstm, hbstm.fit, results, estimation, resid, mse

Plot: plotRes, plotFit
Data: hirlam, coordinates

Examples

See 'tutorial.pdf', included in the documentation of the package, to see a full example

hirlam

hirlam

Description

The data store the temperature, which is collected in a grid of 70 points ($n=7 \times m=10$ points in the grid) in the area that extends from 4 degrees 30" W to 6 degrees 30"W longitude, and from 35 degrees 3"N to 36 degrees 5"N.

The analysed period covers January 1st 2009 to December 31st 2010; the frequency of the data is every 3 hours (temporal reference system is UTC); it starts at 00:00 (daily analysis) and forecasting is at 3:00, 6:00, 9:00, 12:00, 15:00, 18:00 and 21:00. The temperature is recorded every day, eight times a day; so we have a time series for each variable: one for each point on the grid with 5824 time observations.

Format

A data frame with 70 x 5824 observations.

- The rows represent the spatial points ordered from up to down and left to right in the hirlam)
 coordinates.
- The columns represent the time observations.

Hyperpriors-class 11

Hyperpriors-class

Class "Hyperpriors"

Description

"Hyperpriors" contains all the hyperpriors of the fitted HBSTM. It is an internal class and is stored in "HBSTM"

Slots

```
Mu0: An object of class "Mu0" containing all the hyperpriors of the component "Mu".
```

Mt0: An object of class "Mt0" containing all the hyperpriors of the component "Mt".

Xt0: An object of class "Xt0" containing all the hyperpriors of the component "Xt".

sigma2Y0: A "vector" of length 2 with the hyperprior values of the parameter sigma2Y.

sigma2E0: A "vector" of length 2 with the hyperprior values of the parameter sigma2E.

Methods

```
[ signature(x = "Hyperpriors", i = "character", j = "missing", drop = "missing"): extract the components of the model.
```

[<- signature(x = "Hyperpriors", i = "character", j = "missing"): assign values to the components of the model.

Author(s)

Pilar Munyoz and Alberto Lopez Moreno

See Also

Overview: HBSTM-package

 $Classes: \verb|HBSTM|, \verb|Parameters|, \verb|Mu|, \verb|Mt|, \verb|Xt|, \verb|Autoregressive|, Seas|, SpatParam|, VectSubdiag|, Hyperpriors|, Mu0|, Mt0|, Xt0|, Mt0|, Mt0$

Methods: hbstm, hbstm.fit, results, estimation, resid, mse

Plot: plotRes, plotFit
Data: hirlam, coordinates

12 Mt-class

mse

Mean Square Error

Description

Calculate the mean square error of an object of class HBSTM.

Usage

mse(object)

Arguments

object

An object of class "HBSTM".

Value

Returns a "numeric" with the mean square error value.

Author(s)

Pilar Munyoz and Alberto Lopez Moreno

See Also

Overview: HBSTM-package

 $\pmb{Classes: \texttt{HBSTM}, Parameters, \texttt{Mu}, \texttt{Mt}, \texttt{Xt}, \texttt{Autoregressive}, \texttt{Seas}, \texttt{SpatParam}, \texttt{VectSubdiag}, \texttt{Hyperpriors}, \texttt{Mu0}, \texttt{Mt0}, \texttt{Xt0}, \texttt{Mt0}, \texttt{Xt0}, \texttt{Mt0}, \texttt{Mt$

Methods: hbstm, hbstm.fit, results, estimation, resid, mse

Plot: plotRes, plotFit
Data: hirlam, coordinates

Mt-class

Class "Mt"

Description

"Mt" contains the parameter values of the seasonal component and is an internal class stored in "Parameters".

Slots

Mt: A "matrix" of dimension SxT (S = predicted spatial points and T = temporal points) containing the fitted values of the parameter Mt

seas: A "list" of objects of class "Seas", one for each seasonality of the model.

Mt0-class 13

Methods

```
[ signature(x = "Mt", i = "character", j = "missing", drop = "missing"): extract the components of the model.
```

[<- signature(x = "Mt", i = "character", j = "missing"): assign values to the components of the model.

Author(s)

Pilar Munyoz and Alberto Lopez Moreno

See Also

Overview: HBSTM-package

 $Classes: \verb|HBSTM|, \verb|Parameters|, \verb|Mu|, \verb|Mt|, \verb|Xt|, \verb|Autoregressive|, Seas|, SpatParam|, VectSubdiag|, Hyperpriors|, Mu0|, Mt0|, Xt0|, Mt0|, Mt0$

Methods: hbstm, hbstm.fit, results, estimation, resid, mse

Plot: plotRes, plotFit Data: hirlam, coordinates

Mt0-class

Class "Mt0"

Description

"Mt0" contains the hyperprior values of the seasonal component and it is an internal class stored in "Parameters0".

Slots

seas0: A "list" of objects of class "Seas0", one for each seasonality of the model.

Methods

```
[ signature(x = "Mt0", i = "character", j = "missing", drop = "missing"): extract the components of the model.
```

[<- signature(x = "Mt0", i = "character", j = "missing"): assign values to the components of the model.

Author(s)

Pilar Munyoz and Alberto Lopez Moreno

Mu-class

See Also

Overview: HBSTM-package

Classes: HBSTM, Parameters, Mu, Mt, Xt, Autoregressive, Seas, SpatParam, VectSubdiag, Hyperpriors, Mu0, Mt0, Xt0,

Methods: hbstm, hbstm.fit, results, estimation, resid, mse

Plot: plotRes, plotFit
Data: hirlam, coordinates

Mu-class

Class "Mu"

Description

"Mu" contains the parameter values of the mean component and is an internal class stored in "Parameters".

Slots

muvect: An Sx1 "matrix" (S is the number of spatial points of the predicted grid) containing the temporal autoregressive parameter muvect

mu0vect: An Sx1 "matrix" containing the temporal autoregressive parameter mu0vect

mu0L: A 3x1 "matrix" containing the temporal autoregressive parameter a0L

sigma2Mu: Contains the fitted value of the variance sigma2Mu.

spatialMu: An object of class "SpatParam" containing the fitted values of the spatial parameters of muvect.

Methods

```
[ signature(x = "Mu", i = "character", j = "missing", drop = "missing"): extract the components of the model.
```

[<- signature(x = "Mu", i = "character", j = "missing"): assign values to the components of the model.

Author(s)

Pilar Munyoz and Alberto Lopez Moreno

See Also

Overview: HBSTM-package

Classes: HBSTM, Parameters, Mu, Mt, Xt, Autoregressive, Seas, SpatParam, VectSubdiag, Hyperpriors, Mu0, Mt0, Xt0,

Methods: hbstm, hbstm.fit, results, estimation, resid, mse

Plot: plotRes, plotFit
Data: hirlam, coordinates

Mu0-class 15

Mu0-class Class "Mu0"

Description

"Mu0" contains the hyperprior values of the mean component and it is an internal class stored in the class "Parameters0".

Slots

mu0L0: A "vector" of length 3 with the mean hyperprior values of the parameter mu0L sigmu0L0: A "matrix" of dimension 3X3 with the hyperprior variance of the parameter mu0L sigma2Mu0: A "vector" of length 2 with the hyperprior values of the parameter sigma2Mu spatialMu0: An object of class "SpatParam0" containing the hyperprior values of the spatial parameters of Mu

Methods

```
[ signature(x = "Mu0", i = "character", j = "missing", drop = "missing"): extract the components of the model.
[<- signature(x = "Mu0", i = "character", j = "missing"): assign values to the components of the model.</pre>
```

Author(s)

Pilar Munyoz and Alberto Lopez Moreno

See Also

Overview: HBSTM-package

 $Classes: \verb|HBSTM|, \verb|Parameters|, \verb|Mu|, \verb|Mt|, \verb|Xt|, \verb|Autoregressive|, Seas|, SpatParam|, VectSubdiag|, Hyperpriors|, Mu0|, Mt0|, Xt0|, Mt0|, Mt0$

Methods: hbstm, hbstm.fit, results, estimation, resid, mse

Plot: plotRes, plotFit Data: hirlam, coordinates

16 Parameters-class

Parameters-class

Class "Parameters"

Description

"Parameters" contains all the values of the fitted HBSTM parameters and it is an internal class stored in "HBSTM".

Slots

Mu: An object of class "Mu" containing the parameters of the mean component.

Mt: An object of class "Mt" containing the parameters of the seasonal component.

Xt: An object of class "Xt" containing the parameters of the autoregressive space-time component.

Yt: A "matrix" of dimension SxT (S = predicted spatial points and T = temporal points) containing the fitted values of the parameter Yt

sigma2Y: Contains the fitted value of the variance sigma2Y.

sigma2E: Contains the fitted value of the variance sigma2E.

Methods

```
[ signature(x = "Parameters", i = "character", j = "missing", drop = "missing"): extract the components of the model.
```

[<- signature(x = "Parameters", i = "character", j = "missing"): assign values to the components of the model.

Author(s)

Pilar Munyoz and Alberto Lopez Moreno

See Also

Overview: HBSTM-package

Classes: HBSTM, Parameters, Mu, Mt, Xt, Autoregressive, Seas, SpatParam, VectSubdiag, Hyperpriors, Mu0, Mt0, Xt0,

Methods: hbstm, hbstm.fit, results, estimation, resid, mse

Plot: plotRes, plotFit Data: hirlam, coordinates

plotFit 17

plotFit	Plot the spatial data, estimation and residuals of an object of class
	HBSTM

Description

Fits an object of class HBSTM

Usage

```
plotFit(object,time,values)
```

Arguments

object An object of class "HBSTM".

time A integer indicating the time data to show in the spatial grid. By default, it is the

last temporal observation.

values A "logical" indicating whether the function returns the values shown in the

plot.

Value

By default, plotFit returns an object of class "NULL". If the attribute matrices is TRUE, plotFit returns a "data.frame" with three variables:

"Zt" : The data in a fixed temporal observation specified by the attribute codetime. "EstZt"

: The data estimation in a fixed temporal observation specified by the attribute

codetime.

: The residuals extracted from "Zt" and "EstZt". "Et"

Author(s)

Pilar Munyoz and Alberto Lopez Moreno

See Also

Overview: HBSTM-package

Classes: HBSTM, Parameters, Mu, Mt, Xt, Autoregressive, Seas, SpatParam, VectSubdiag, Hyperpriors, Mu0, Mt0, Xt0,

Methods: hbstm, hbstm.fit, results, estimation, resid, mse

Plot: plotRes, plotFit Data: hirlam, coordinates

Examples

See 'tutorial.pdf', included in the documentation of the package, to see a full example

18 plotRes

|--|

Description

Plot the residuals of the fitted values of an object of class HBSTM.

Usage

```
plotRes(object,point,ARlags,ARperiod)
```

Arguments

object An object of class "HBSTM".

point A integer indicating the spatial point to show the results. By default a random

spatial point is selected.

ARlags Maximum lag at which the ACF and the PACF are calculated. Default is 10*log10(N/m),

where N is the number of observations and m the number of series. It will be automatically limited to one less than the number of observations in the series

ARperiod The period of the data. Prints in red the lag in the period.

Value

null

Author(s)

Pilar Munyoz and Alberto Lopez Moreno

See Also

Overview: HBSTM-package

Classes: HBSTM, Parameters, Mu, Mt, Xt, Autoregressive, Seas, SpatParam, VectSubdiag, Hyperpriors, Mu0, Mt0, Xt0,

Methods: hbstm, hbstm.fit, results, estimation, resid, mse

Plot: plotRes, plotFit
Data: hirlam, coordinates

Examples

```
## See 'tutorial.pdf', included in the documentation of the package, to see a full example
```

results 19

results Results summary

Description

It shows the results of fitting an object of class HBSTM.

Usage

```
results(object,spatTemp,inter,digits,component,plots,file)
```

Arguments

object	An object of class "HBSTM".
spatTemp	A list of vectors containing the spatial and the temporal points to show. See details.
inter	An optional numeric value for the interval credibility level. Default is 0.95
digits	Integer indicating the number of decimal places to round the values.
component	An optional "character" indicating which component have to be shown ("Parameters", "Mu", "Mt" or "Xt").
plots	Plot the medians and the credibility intervals of the parameters.
file	An optional "character" containing the name of the .tex file where the results are stored (in the current work directory). By default the function does not store the results.

Details

Each position in the spaTemp list contains a numerical vector, in which the first position refers to a spatial point of the data and the second position to a temporal point of the data.

Value

null

Author(s)

Pilar Munyoz and Alberto Lopez Moreno

See Also

Overview: HBSTM-package

 $Classes: \verb|HBSTM|, \verb|Parameters|, \verb|Mu|, \verb|Mt|, \verb|Xt|, \verb|Autoregressive|, Seas|, SpatParam|, VectSubdiag|, Hyperpriors|, Mu0|, Mt0|, Xt0|, Mt0|, Mt0$

Methods: hbstm, hbstm.fit, results, estimation, resid, mse

Plot: plotRes, plotFit Data: hirlam, coordinates

20 Seas-class

Examples

See 'tutorial.pdf', included in the documentation of the package, to see a full example

Seas-class

Class "Seas"

Description

"Seas" contains the parameter values of the seasonal component and is an internal class stored in "Mt".

Slots

w: The period of the seasonality

fvect: An Sx1 "matrix" (S is the number of spatial points of the predicted grid) containing the temporal autoregressive parameter fvect

fol: A 3x1 "matrix" containing the temporal autoregressive parameter fol

gvect: A Sx1 "matrix" containing the temporal autoregressive parameter gvect

gOL: A 3x1 "matrix" containing the temporal autoregressive parameter gOL

Methods

```
[ signature(x = "Seas", i = "character", j = "missing", drop = "missing"): extract the components of the model.
```

[<- signature(x = "Seas", i = "character", j = "missing"): assign values to the components of the model.

Author(s)

Pilar Munyoz and Alberto Lopez Moreno

See Also

Overview: HBSTM-package

 $Classes: \verb|HBSTM|, \verb|Parameters|, \verb|Mu|, \verb|Mt|, \verb|Xt|, \verb|Autoregressive|, Seas|, SpatParam|, VectSubdiag|, Hyperpriors|, Mu0|, Mt0|, Xt0|, Mt0|, Mt0$

Methods: hbstm, hbstm.fit, results, estimation, resid, mse

Plot: plotRes, plotFit Data: hirlam, coordinates

Seas0-class 21

Seas0-class Class "Seas0"

Description

"Seas0" contains the hyperprior values of the seasonal component and is an internal class stored in the class "Mt0".

Slots

```
f0L0: A "vector" of length 3 with the mean hyperprior values of the parameter f0L sigf0L0: A "matrix" of dimension 3X3 with the hyperprior variance of the parameter f0L g0L0: A "vector" of length 3 with the mean hyperprior values of the parameter g0L sigg0L0: A "matrix" of dimension 3X3 with the hyperprior variance of the parameter g0L
```

Methods

```
[ signature(x = "Seas0", i = "character", j = "missing", drop = "missing"): extract the com-
ponents of the model.
[<- signature(x = "Seas0", i = "character", j = "missing"): assign values to the compo-
nents of the model.</pre>
```

Author(s)

Pilar Munyoz and Alberto Lopez Moreno

See Also

Overview: HBSTM-package

 $Classes: \verb|HBSTM|, \verb|Parameters|, \verb|Mu|, \verb|Mt|, \verb|Xt|, \verb|Autoregressive|, Seas|, SpatParam|, VectSubdiag|, Hyperpriors|, Mu0|, Mt0|, Xt0|, Mt0|, Mt0$

Methods: hbstm, hbstm.fit, results, estimation, resid, mse

Plot: plotRes, plotFit Data: hirlam, coordinates

SpatParam-class

Class "SpatParam"

Description

"SpatParam" contains the values of the spatial parameters and is an internal class stored in the classes "Mu" and "Autorregressive".

22 SpatParam0-class

Slots

alpha: A "vector" of length: the number of horizontal (east-west) spatial lags. It contains the fitted values of the horizontal spatial parameters.

beta: A "vector" of length: the number of vertical (north-south) spatial lags. It contains the fitted values of the vertical spatial parameters.

phi: A "vector" of length: the number of diagonal (southeast-northwest) spatial lags. It contains the fitted values of the diagonal spatial parameters.

theta: A "vector" of length: the number of inverse-diagonal (southwest-northeast) spatial lags. It contains the fitted values of the inverse-diagonal spatial parameters.

Cmat: An SxS "matrix" (S is the number of spatial points of the predicted grid) containing all the spatial parameters.

lags: A "vector" containing the spatial lags for each direction. Each position of the vector is related to the lags of alpha, beta, phi and theta, respectively.

dirs: A "vector" containing the considered spatial directions of the model.

Methods

[signature(x = "SpatParam", i = "character", j = "missing", drop = "missing"): extract the components of the model.

[<- signature(x = "SpatParam", i = "character", j = "missing"): assign values to the components of the model.

Author(s)

Pilar Munyoz and Alberto Lopez Moreno

See Also

Overview: HBSTM-package

Classes: HBSTM, Parameters, Mu, Mt, Xt, Autoregressive, Seas, SpatParam, VectSubdiag, Hyperpriors, Mu0, Mt0, Xt0,

Methods: hbstm, hbstm.fit, results, estimation, resid, mse

Plot: plotRes, plotFit
Data: hirlam, coordinates

SpatParam0-class

Class "SpatParam0"

Description

"SpatParam0" contains the hyperprior values of the specified spatial parameters and is an internal class stored in the classes "Mu0" and "Autorregressive0".

VectSubdiag-class 23

Slots

alpha0: A "matrix" of dimension 2X(Length of alpha vector) with the means in the first row and the variance in the second row.

beta0: A "matrix" of dimension 2X(Length of beta vector) with the means in the first row and the variance in the second row.

phi0: A "matrix" of dimension 2X(Length of phi vector) with the means in the first row and the variance in the second row.

theta0: A "matrix" of dimension 2X(Length of theta vector) with the means in the first row and the variance in the second row.

Methods

```
[ signature(x = "SpatParam0", i = "character", j = "missing", drop = "missing"): extract the components of the model.
```

[<- signature(x = "SpatParam0", i = "character", j = "missing"): assign values to the components of the model.

Author(s)

Pilar Munyoz and Alberto Lopez Moreno

See Also

Overview: HBSTM-package

Classes: HBSTM, Parameters, Mu, Mt, Xt, Autoregressive, Seas, SpatParam, VectSubdiag, Hyperpriors, Mu0, Mt0, Xt0,

Methods: hbstm, hbstm.fit, results, estimation, resid, mse

Plot: plotRes,plotFit
Data: hirlam,coordinates

VectSubdiag-class

Class "VectSubdiag"

Description

"VectSubdiag" contains all the values of the space-time parameters and it is an internal class stored in "Autorregressive".

Slots

east: A "vector" of length: the number of east spatial lags. It contains the fitted values of the east spatial-temporal parameters.

west: A "vector" of length: the number of west spatial lags. It contains the fitted values of the west spatial-temporal parameters.

north: A "vector" of length: the number of north spatial lags. It contains the fitted values of the north spatial-temporal parameters.

24 VectSubdiag0-class

south: A "vector" of length: the number of south spatial lags. It contains the fitted values of the south spatial-temporal parameters.

- southeast: A "vector" of length: the number of southeast spatial. It and contains the fitted values of the southeast spatial-temporal parameters.
- northwest: A "vector" of length: the number of northwest spatial. It and contains the fitted values of the northwest spatial-temporal parameters.
- southwest: A "vector" of length: the number of southwest spatial. It and contains the fitted values of the southwest spatial-temporal parameters.
- northeast: A "vector" of length: the number of northeast spatial. It and contains the fitted values of the northeast spatial-temporal parameters.
- lags: A "vector" containing the spatial lags for each direction. Each position of the vector is related to the lags of east, weast, north, south, southeast, northwest, southwest and northeast, respectively.
- dirs: A "vector" containing all the space-time directions included in the model.

Methods

- [signature(x = "VectSubdiag", i = "character", j = "missing", drop = "missing"): extract the components of the model.
- [<- signature(x = "VectSubdiag", i = "character", j = "missing"): assign values to the components of the model.

Author(s)

Pilar Munyoz and Alberto Lopez Moreno

See Also

Overview: HBSTM-package

Classes: HBSTM, Parameters, Mu, Mt, Xt, Autoregressive, Seas, SpatParam, VectSubdiag, Hyperpriors, Mu0, Mt0, Xt0,

Methods: hbstm, hbstm.fit, results, estimation, resid, mse

Plot: plotRes,plotFit
Data: hirlam,coordinates

VectSubdiag0-class

Class "VectSubdiag0"

Description

"VectSubdiago" contains the hyperprior values of the specified space-time parameters, and it is an internal class stored in "Autorregressiveo"

VectSubdiag0-class 25

Slots

east0: A "matrix" of dimension 2X(Length of vector east) with the means in the first row and the variance in the second row.

- west0: A "matrix" of dimension 2X(Length of vector west) with the means in the first row and the variance in the second row.
- north0: A "matrix" of dimension 2X(Length of vector north) with the means in the first row and the variance in the second row.
- south0: A "matrix" of dimension 2X(Length of vector south) with the means in the first row and the variance in the second row.
- southeast0: A "matrix" of dimension 2X(Length of vector southeast) with the means in the first row and the variance in the second row.
- northwest0: A "matrix" of dimension 2X(Length of vector northwest) with the means in the first row and the variance in the second row.
- southwest0: A "matrix" of dimension 2X(Length of vector southwest) with the means in the first row and the variance in the second row.
- northeast0: A "matrix" of dimension 2X(Length of vector northeast) with the means in the first row and the variance in the second row.

Methods

- [signature(x = "VectSubdiag0", i = "character", j = "missing", drop = "missing"): extract the components of the model.
- [<- signature(x = "VectSubdiag0", i = "character", j = "missing"): assign values to the components of the model.

Author(s)

Pilar Munyoz and Alberto Lopez Moreno

See Also

Overview: HBSTM-package

Classes: HBSTM, Parameters, Mu, Mt, Xt, Autoregressive, Seas, SpatParam, VectSubdiag, Hyperpriors, Mu0, Mt0, Xt0,

Methods: hbstm, hbstm.fit, results, estimation, resid, mse

Plot: plotRes, plotFit
Data: hirlam, coordinates

26 Xt-class

Xt-class

Class "Xt"

Description

"Xt" contains the parameter values of the autoregressive part and is an internal class stored in "Parameters".

Slots

Xt: A "matrix" of dimension SxT (S = predicted spatial points and T = temporal points) containing the fitted values of the parameter Xt.

X0: An Sx1 "matrix" containing the auxiliary parameter X0.

sigma2N: Contains the fitted value of the variance sigmaN.

AR: A "list" of objects of class Autoregressive, one for each temporal lag of the model.

templags: A "vector" containing the temporal lags of the model.

Methods

[signature(x = "Xt", i = "character", j = "missing", drop = "missing"): extract the components of the model.

[<- signature(x = "Xt", i = "character", j = "missing"): assign values to the components of the model..

Author(s)

Pilar Munyoz and Alberto Lopez Moreno

See Also

Overview: HBSTM-package

Classes: HBSTM, Parameters, Parameters, Mu, Mt, Xt, Autoregressive, Seas, SpatParam, VectSubdiag, Hyperpriors, N

Methods: hbstm, hbstm.fit, results, estimation, resid

Plot: plotRes

Xt0-class 27

Xt0-class

Class "Xt0"

Description

"Xt0" contains the hyperprior values of the autoregressive part and is an internal class and is stored in "Parameters0"

Slots

X00: A "vector" of length S (S is the number of spatial points of the predicted grid) with the mean hyperprior values of the parameter X0

sigma2X00: A "matrix" of dimension SXS with the hyperprior variance of the parameter X0

ARO: A "list" of objects of class "Autorregresive0", one for each temporal lag of the model.

sigma2N0: A "vector" of length 2 with the hyperprior values of the parameter sigma2N

Methods

```
[ signature(x = "Xt0", i = "character", j = "missing", drop = "missing"): extract the components of the model.
```

[<- signature(x = "Xt0", i = "character", j = "missing"): assign values to the components of the model.

Author(s)

Pilar Munyoz and Alberto Lopez Moreno

See Also

Overview: HBSTM-package

 $Classes: \verb|HBSTM|, \verb|Parameters|, \verb|Mu|, \verb|Mt|, \verb|Xt|, \verb|Autoregressive|, Seas|, SpatParam|, VectSubdiag|, Hyperpriors|, Mu0|, Mt0|, Xt0|, Mt0|, Mt0$

 $Methods: \verb|hbstm|, \verb|hbstm|, \verb|fit|, \verb|results|, estimation|, \verb|resid|, \verb|mse|$

Plot: plotRes,plotFit Data: hirlam,coordinates

Index

* classes	(Mu0-class), 15
Autoregressive0-class,4	[,Parameters,character,missing,missing-method
HBSTM-class, 8	(Parameters-class), 16
Hyperpriors-class, 11	[,Seas,character,missing,missing-method
Mt-class, 12	(Seas-class), 20
Mt0-class, 13	[,Seas0,character,missing,missing-method
Mu-class, 14	(Seas0-class), 21
Mu0-class, 15	[,SpatC,character,missing,missing-method
Parameters-class, 16	(HBSTM-package), 2
Seas-class, 20	[,SpatH,character,missing,missing-method
Seas0-class, 21	(HBSTM-package), 2
SpatParam-class, 21	[,SpatParam,character,missing,missing-method
SpatParam0-class,22	(SpatParam-class), 21
VectSubdiag-class, 23	[,SpatParam0,character,missing,missing-method
<pre>VectSubdiag0-class, 24</pre>	(SpatParam0-class), 22
Xt-class, 26	[,VectSubdiag,character,missing,missing-method
Xt0-class, 27	(VectSubdiag-class), 23
* datasets	$\hbox{\tt [,VectSubdiag0,character,missing,missing-method]}$
coordinates, 5	(VectSubdiag0-class), 24
hirlam, 10	[,Xt,character,missing,missing-method
[,Autoregressive,character,missing,missing-m	
(Autoregressive-class), 3	[,Xt0,character,missing,missing-method
[,Autoregressive0,character,missing,missing-	
(Autoregressive0-class), 4	[<-,Autoregressive,character,missing-method
[,CosSinMatrix,character,missing,missing-met	
(HBSTM-package), 2	[<-,Autoregressive0,character,missing-method
[,HBSTM,character,missing,missing-method	(Autoregressive0-class), 4
(HBSTM-class), 8	[<-,CosSinMatrix,character,missing-method
[,Hyperpriors,character,missing,missing-meth	
(Hyperpriors-class), 11	[<-,HBSTM,character,missing-method
[,Mt,character,missing,missing-method	(HBSTM-class), 8
(Mt-class), 12	[<-, Hyperpriors, character, missing-method
[,Mt0,character,missing,missing-method	(Hyperpriors-class), 11
(Mt0-class), 13	[<-,Mt,character,missing-method
[,MtAux,character,missing,missing-method	(Mt-class), 12
(HBSTM-package), 2	[<-,Mt0,character,missing-method
[,Mu,character,missing,missing-method (Mu-class), 14	(Mt0-class), 13
[,Mu0,character,missing,missing-method	<pre>[<-,MtAux,character,missing-method</pre>
L, rido, chai acter, ilitsstrig, ilitsstrig-ille chou	(IIDSTIT-package), Z

INDEX 29

[<-,Mu,character,missing-method	hirlam, 3, 4, 6, 7, 9, 10, 10, 11-25, 27
(Mu-class), 14	Hyperpriors, 2-4, 6, 7, 9-27
[<-,Mu0,character,missing-method	Hyperpriors-class, 11
(Mu0-class), 15	
[<-,Parameters,character,missing-method	mse, 2–4, 6, 7, 9–12, 12, 13–25, 27
(Parameters-class), 16	mse, HBSTM-method (mse), 12
[<-, Seas, character, missing-method	mse-methods (mse), 12
(Seas-class), 20	mse.HBSTM (mse), 12
[<-,Seas0,character,missing-method	Mt, 2–4, 6, 7, 9–27
(Seas0-class), 21	Mt-class, 12
[<-,SpatC,character,missing-method	Mt0, 2-4, 6, 7, 9-27
(HBSTM-package), 2	Mt0-class, 13
[<-,SpatH,character,missing-method	Mu, 2–4, 6, 7, 9–27
(HBSTM-package), 2	Mu-class, 14
	Mu0, 2–4, 6, 7, 9–27
[<-,SpatParam,character,missing-method	Mu0-class, 15
(SpatParam-class), 21	1100 01033, 13
[<-,SpatParam0,character,missing-method	Parameters, 2-4, 6, 7, 9-27
(SpatParam0-class), 22	Parameters-class, 16
[<-, VectSubdiag, character, missing-method	plotFit, 2–4, 6, 7, 9–17, 17, 18–25, 27
(VectSubdiag-class), 23	plotFit, HBSTM-method (plotFit), 17
[<-,VectSubdiag0,character,missing-method	plotFit-methods (plotFit), 17
(VectSubdiag0-class), 24	plotRes, 2–4, 6, 7, 9–18, 18, 19–27
<pre>[<-,Xt,character,missing-method</pre>	plotRes, HBSTM-method (plotRes), 18
(Xt-class), 26	plotRes-methods (plotRes), 18
<pre>[<-,Xt0,character,missing-method</pre>	proties-illetilous (proties), 18
(Xt0-class), 27	resid, 2-4, 6, 7, 9-27
	results, 2–4, 6, 7, 9–19, 19, 20–27
Autoregressive, 2–4, 6, 7, 9–27	results, HBSTM-method (results), 19
Autoregressive-class, 3	results-methods (results), 19
Autoregressive0, 2-4, 6, 7, 9-27	results methods (results), 17
Autoregressive0-class,4	Seas, 2–4, 6, 7, 9–27
	Seas-class, 20
coordinates, <i>3</i> , <i>4</i> , <i>5</i> , <i>6</i> , <i>7</i> , <i>9</i> – <i>25</i> , <i>27</i>	Seas0, 2–4, 6, 7, 9–27
	Seas0-class, 21
estimation, 2-4, 5, 6, 7, 9-27	SpatParam, 2–4, 6, 7, 9–27
estimation, HBSTM-method (estimation), 5	SpatParam-class, 21
estimation-methods (estimation), 5	Spatraram C1ass, 21 SpatParam0, 2–4, 6, 7, 9–27
HBSTM, 2–4, 6, 7, 9–27	SpatParam0-class, 22
HBSTM (HBSTM-package), 2	VectSubdiag, 2-4, 6, 7, 9-27
hbstm, 2-4, 6, 6, 7, 9-27	VectSubdiag-class, 23
hbstm,data.frame,matrix,data.frame,vector,ve	ector, vectouding class, 25 ector, 25
(hbstm), 6	VectSubdiag0-class, 24
HBSTM-class, 8	vectsubulage-class, 24
hbstm-methods (hbstm), 6	Xt, 2–4, 6, 7, 9–27
HBSTM-package, 2	Xt-class, 26
hbstm.fit, 2-4, 6, 7, 9, 9, 10-27	7.0 0±000, 20
	X+0 2_4 6 7 9_27
hbstm.fit, HBSTM-method (hbstm.fit), 9	Xt0, 2–4, 6, 7, 9–27 Xt0-class, 27