Package 'mvpd'

September 3, 2023

Title Multivariate Product Distributions for Elliptically Contoured Distributions
Version 0.0.4
Description Estimates multivariate subgaussian stable densities and probabilities as well as generates random variates using product distribution theory. A function for estimating the parameters from data to fit a distribution to data is also provided, using the method from Nolan (2013) <doi:10.1007 s00180-013-0396-7="">.</doi:10.1007>
Imports matrixStats, stabledist, libstable4u, mvtnorm, stats, cubature, Matrix
Depends R (>= 3.4.0)
License MIT + file LICENSE
Encoding UTF-8
RoxygenNote 7.2.1
Suggests rmarkdown, knitr, testthat (>= 3.0.0)
Config/testthat/edition 3
URL https://github.com/swihart/mvpd
BugReports https://github.com/swihart/mvpd/issues
NeedsCompilation no
Author Bruce Swihart [aut, cre] (https://orcid.org/0000-0002-4216-9942)
Maintainer Bruce Swihart <bruce.swihart@gmail.com></bruce.swihart@gmail.com>
Repository CRAN
Date/Publication 2023-09-03 14:20:02 UTC
R topics documented:
adaptIntegrate_inf_limPD

```
      pmvss
      8

      pmvss_mc
      10

      rmvss
      12
```

Index 13

```
adaptIntegrate_inf_limPD
```

Adaptive multivariate integration over hypercubes (admitting infinite limits)

Description

The function performs adaptive multidimensional integration (cubature) of (possibly) vector-valued integrands over hypercubes. It is a wrapper for cubature:::adaptIntegrate, transforming (-)Inf appropriately as described in cubature's help page (http://ab-initio.mit.edu/wiki/index.php/Cubature#Infinite_intervals).

Usage

```
adaptIntegrate_inf_limPD(
   f,
   lowerLimit,
   upperLimit,
   ...,
   tol.ai = 1e-05,
   fDim.ai = 1,
   maxEval.ai = 0,
   absError.ai = 0,
   doChecking.ai = FALSE
)
```

Arguments

f	The function (integrand) to be integrated
lowerLimit	The lower limit of integration, a vector for hypercubes
upperLimit	The upper limit of integration, a vector for hypercubes
	All other arguments passed to the function f
tol.ai	The maximum tolerance, default 1e-5.
fDim.ai	The dimension of the integrand, default 1, bears no relation to the dimension of the hypercube
maxEval.ai	The maximum number of function evaluations needed, default 0 implying no limit
absError.ai	The maximum absolute error tolerated
doChecking.ai	A flag to be thorough checking inputs to C routines. A FALSE value results in approximately 9 percent speed gain in our experiments. Your mileage will of course vary. Default value is FALSE.

dmvss 3

Examples

```
## integrate Cauchy Density from -Inf to Inf
adaptIntegrate_inf_limPD(function(x) 1/pi * 1/(1+x^2), -Inf, Inf)
adaptIntegrate_inf_limPD(function(x, scale) 1/(pi*scale) * 1/(1+(x/scale)^2), -Inf, Inf, scale=4)
## integrate Cauchy Density from -Inf to -3
adaptIntegrate_inf_limPD(function(x) 1/pi * 1/(1+x^2), -Inf, -3)$int
stats::pcauchy(-3)
adaptIntegrate_inf_limPD(function(x, scale) 1/(pi*scale) * 1/(1+(x/scale)^2), -Inf, -3, scale=4)$int
stats::pcauchy(-3, scale=4)
```

dmvss

Multivariate Subgaussian Stable Density

Description

Computes the density function of the multivariate subgaussian stable distribution for arbitrary alpha, shape matrices, and location vectors. See Nolan (2013).

Usage

```
dmvss(
 х,
 alpha = 1,
 Q = NULL,
  delta = rep(0, d),
  outermost.int = c("stats::integrate", "cubature::adaptIntegrate")[1],
  spherical = FALSE,
  subdivisions.si = 100L,
  rel.tol.si = .Machine$double.eps^0.25,
  abs.tol.si = rel.tol.si,
  stop.on.error.si = TRUE,
  tol.ai = 1e-05,
  fDim.ai = 1,
 maxEval.ai = 0,
 absError.ai = 0,
 doChecking.ai = FALSE,
  which.stable = c("libstable4u", "stabledist")[1]
)
```

Arguments

```
x vector of quantiles.
alpha default to 1 (Cauchy). Must be 0<alpha<2
Q Shape matrix. See Nolan (2013).
delta location vector
```

4 dmvss

outermost.int select which integration function to use for outermost integral. Default is "stats::integrate" and one can specify the following options with the .si suffix. For diagonal Q, one can also specify "cubature::adaptIntegrate" and use the .ai suffix options below (currently there is a bug for non-diagnoal Q). spherical default is FALSE. If true, use the spherical transformation, Results will be identical to spherical = FALSE but may be faster. subdivisions.si the maximum number of subintervals. The suffix .si indicates a stats::integrate() option for the outermost semi-infinite integral in the product distribution formulation. rel.tol.si relative accuracy requested. The suffix .si indicates a stats::integrate() option for the outermost semi-infinite integral in the product distribution formulation. abs.tol.si absolute accuracy requested. The suffix .si indicates a stats::integrate() option for the outermost semi-infinite integral in the product distribution formulation. stop.on.error.si logical. If true (the default) an error stops the function. If false some errors will give a result with a warning in the message component. The suffix . si indicates a stats::integrate() option for the outermost semi-infinite integral in the product distribution formulation. tol.ai The maximum tolerance, default 1e-5. The suffix .ai indicates a cubature::adaptIntegrate type option for the outermost semi-infinite integral in the product distribution formulation. fDim.ai The dimension of the integrand, default 1, bears no relation to the dimension of the hypercube The suffix .ai indicates a cubature::adaptIntegrate type option for the outermost semi-infinite integral in the product distribution formulation. maxEval.ai The maximum number of function evaluations needed, default 0 implying no limit The suffix .ai indicates a cubature::adaptIntegrate type option for the outermost semi-infinite integral in the product distribution formulation. The maximum absolute error tolerated The suffix .ai indicates a cubature::adaptIntegrate absError.ai type option for the outermost semi-infinite integral in the product distribution formulation. A flag to be thorough checking inputs to C routines. A FALSE value results doChecking.ai in approximately 9 percent speed gain in our experiments. Your mileage will of course vary. Default value is FALSE. The suffix .ai indicates a cubature::adaptIntegrate type option for the outermost semi-infinite integral in the product distribution formulation. which.stable defaults to "libstable4u", other option is "stabledist". Indicates which package should provide the univariate stable distribution in this production distribution

Value

The object returned depends on what is selected for outermost.int. In the case of the default, stats::integrate, the value is a list of class "integrate" with components:

form of a univariate stable and multivariate normal.

fit_mvss 5

- value the final estimate of the integral.
- abs.error estimate of the modulus of the absolute error.
- subdivisions the number of subintervals produced in the subdivision process.
- message "OK" or a character string giving the error message.
- call the matched call.

Note: The reported abs.error is likely an under-estimate as integrate assumes the integrand was without error, which is not the case in this application.

References

Nolan, John P. "Multivariate elliptically contoured stable distributions: theory and estimation." Computational Statistics 28.5 (2013): 2067-2089.

Examples

```
## print("mvsubgaussPD (d=2, alpha=1.71):")
Q <- matrix(c(10,7.5,7.5,10),2)
mvpd::dmvss(x=c(0,1), alpha=1.71, Q=Q)

## more accuracy = longer runtime
mvpd::dmvss(x=c(0,1),alpha=1.71, Q=Q, abs.tol=1e-8)

Q <- matrix(c(10,7.5,7.5,7.5,10,7.5,7.5,7.5,10),3)
## print("mvsubgausPD (d=3, alpha=1.71):")
mvpd::dmvss(x=c(0,1,2), alpha=1.71, Q=Q)
mvpd::dmvss(x=c(0,1,2), alpha=1.71, Q=Q, spherical=TRUE)

## How `delta` works: same as centering
X <- c(1,1,1)
Q <- matrix(c(10,7.5,7.5,7.5,10,7.5,7.5,7.5,10),3)
D <- c(0.75, 0.65, -0.35)
mvpd::dmvss(X-D, alpha=1.71, Q=Q)
mvpd::dmvss(X , alpha=1.71, Q=Q, delta=D)</pre>
```

fit_mvss

Fit a Multivariate Subgaussian Distribution

Description

Estimates the parameters (namely, alpha, shape matrix Q, and location vector) of the multivariate subgaussian distribution for an input matrix X.

Usage

```
fit_mvss(x)
```

6 fit_mvss

Arguments

Х

a matrix for which the parameters for a d-dimensional multivariate subgaussian distribution will be estimated. The number of columns will be d.

Details

Using the protocols outlined in Nolan (2013), this function uses libstable4u's univariate fit functions for each component.

Value

A list with parameters from the column-wise univariate fits and the multivariate alpha and shape matrix estimates (the univ_deltas are the mult_deltas):

- univ_alphas the alphas from the column-wise univariate fits
- univ_betas the betas from the column-wise univariate fits
- univ_gammas the gammas from the column-wise univariate fits
- univ_deltas the deltas from the column-wise univariate fits
- mult_alpha the mean(univ_alphas); equivalently the multivariate alpha estimate
- mult_Q_raw the multivariate shape matrix estimate (before applying nearPD())
- mult_Q_posdef the nearest positive definite multivariate shape matrix estimate, nearPD(mult_Q_raw)

References

Nolan JP (2013), *Multivariate elliptically contoured stable distributions: theory and estimation*. Comput Stat (2013) 28:2067–2089 DOI 10.1007/s00180-013-0396-7

See Also

```
Rfast::mvnorm.mle, alphastable::mfitstab.elliptical
```

Examples

mvpd 7

```
delta=fmv$univ_deltas,
maxpts.pmvnorm = 25000*10)
```

mvpd

Multivariate Product Distributions

Description

The purpose of this package is to offer density, probability, and random variate generating (abbreviated as [d/p/r], respectively) functions for multivariate distributions that can be represented as a product distribution. Specifically, the package will primarily focus on the product of a multivariate normal distribution and a univariate random variable. These product distributions are called Scale Mixtures of Multivariate Normal Distributions, and for particular choices of the univariate random variable distribution the resultant product distribution may be a family of interest. For instance, the square-root of a positive stable random variable multiplied by a multivariate normal distribution is the multivariate subgaussian stable distribution. Product distribution theory is applied for implementing their computation.

Multivariate subgaussian stable distributions

```
dmvss – multivariate subgaussian stable distribution density

pmvss – multivariate subgaussian stable distribution probabilities

rmvss – multivariate subgaussian stable distribution random variates

pmvss_mc – Monte Carlo version of probabilities, using rmvss

fit_mvss – Fit a multivariate subgaussian stable distribution (e.g. estimate parameters given data)
```

Author(s)

Maintainer: Bruce Swihart <bruce.swihart@gmail.com> (ORCID)

See Also

Useful links:

- https://github.com/swihart/mvpd
- Report bugs at https://github.com/swihart/mvpd/issues

8 pmvss

pmvss

Multivariate Subgaussian Stable Distribution

Description

Computes the probabilities for the multivariate subgaussian stable distribution for arbitrary limits, alpha, shape matrices, and location vectors. See Nolan (2013).

Usage

```
pmvss(
  lower = rep(-Inf, d),
  upper = rep(Inf, d),
  alpha = 1,
  Q = NULL,
  delta = rep(0, d),
 maxpts.pmvnorm = 25000,
  abseps.pmvnorm = 0.001,
  outermost.int = c("stats::integrate", "cubature::adaptIntegrate")[1],
  subdivisions.si = 100L,
  rel.tol.si = .Machine$double.eps^0.25,
  abs.tol.si = rel.tol.si,
  stop.on.error.si = TRUE,
  tol.ai = 1e-05,
  fDim.ai = 1,
 maxEval.ai = 0,
  absError.ai = 0,
  doChecking.ai = FALSE,
  which.stable = c("libstable4u", "stabledist")[1]
)
```

the vector of lower limits of length n.

Arguments

lower

	e e e e e e e e e e e e e e e e e e e
upper	the vector of upper limits of length n.
alpha	default to 1 (Cauchy). Must be 0 <alpha<2< td=""></alpha<2<>
Q	Shape matrix. See Nolan (2013).
delta	location vector.
maxpts.pmvnorm	Defaults to 25000. Passed to the $F_G = pmvnorm()$ in the integrand of the outermost integral.
abseps.pmvnorm	Defaults to 1e-3. Passed to the $F_G = pmvnorm()$ in the integrand of the outermost integral.
outermost.int	select which integration function to use for outermost integral. Default is "stats::integrate" and one can specify the following options with the <code>.si</code> suffix. For diagonal Q, one can also specify "cubature::adaptIntegrate" and use the <code>.ai</code> suffix options below (currently there is a bug for non-diagonal Q).

pmvss 9

subdivisions.si

the maximum number of subintervals. The suffix .si indicates a stats::integrate() option for the outermost semi-infinite integral in the product distribution formulation.

rel.tol.si relative accuracy requested. The suffix .si indicates a stats::integrate() option for the outermost semi-infinite integral in the product distribution formulation.

abs.tol.si absolute accuracy requested. The suffix .si indicates a stats::integrate() option for the outermost semi-infinite integral in the product distribution formulation.

stop.on.error.si

doChecking.ai

which.stable

logical. If true (the default) an error stops the function. If false some errors will give a result with a warning in the message component. The suffix .si indicates a stats::integrate() option for the outermost semi-infinite integral in the product distribution formulation.

tol.ai The maximum tolerance, default 1e-5. The suffix .ai indicates a cubature::adaptIntegrate type option for the outermost semi-infinite integral in the product distribution formulation.

fDim.ai The dimension of the integrand, default 1, bears no relation to the dimension of the hypercube The suffix .ai indicates a cubature::adaptIntegrate type option for the outermost semi-infinite integral in the product distribution formulation.

The maximum number of function evaluations needed, default 0 implying no limit The suffix .ai indicates a cubature::adaptIntegrate type option for the outermost semi-infinite integral in the product distribution formulation.

absError.ai The maximum absolute error tolerated The suffix .ai indicates a cubature::adaptIntegrate type option for the outermost semi-infinite integral in the product distribution formulation.

A flag to be thorough checking inputs to C routines. A FALSE value results in approximately 9 percent speed gain in our experiments. Your mileage will of course vary. Default value is FALSE. The suffix .ai indicates a cubature::adaptIntegrate type option for the outermost semi-infinite integral in the product distribution formulation.

defaults to "libstable4u", other option is "stabledist". Indicates which package should provide the univariate stable distribution in this production distribution form of a univariate stable and multivariate normal.

Value

The object returned depends on what is selected for outermost.int. In the case of the default, stats::integrate, the value is a list of class "integrate" with components:

- value the final estimate of the integral.
- abs.error estimate of the modulus of the absolute error.
- subdivisions the number of subintervals produced in the subdivision process.
- message "OK" or a character string giving the error message.

10 pmvss_mc

• call the matched call.

Note: The reported abs.error is likely an under-estimate as integrate assumes the integrand was without error, which is not the case in this application.

References

Nolan JP (2013), *Multivariate elliptically contoured stable distributions: theory and estimation*. Comput Stat (2013) 28:2067–2089 DOI 10.1007/s00180-013-0396-7

Examples

```
## bivariate
U <- c(1,1)
L <- -U
Q \leftarrow matrix(c(10,7.5,7.5,10),2)
mvpd::pmvss(L, U, alpha=1.71, Q=Q)
## trivariate
U \leftarrow c(1,1,1)
L <- -U
Q \leftarrow matrix(c(10,7.5,7.5,7.5,10,7.5,7.5,7.5,10),3)
mvpd::pmvss(L, U, alpha=1.71, Q=Q)
## How `delta` works: same as centering
U \leftarrow c(1,1,1)
L <- -U
Q \leftarrow matrix(c(10,7.5,7.5,7.5,10,7.5,7.5,7.5,10),3)
D < -c(0.75, 0.65, -0.35)
mvpd::pmvss(L-D, U-D, alpha=1.71, Q=Q)
mvpd::pmvss(L , U , alpha=1.71, Q=Q, delta=D)
```

pmvss_mc

Monte Carlo Multivariate Subgaussian Stable Distribution

Description

Computes probabilities of the multivariate subgaussian stable distribution for arbitrary limits, alpha, shape matrices, and location vectors via Monte Carlo (thus the suffix _mc).

Usage

```
pmvss_mc(
  lower = rep(-Inf, d),
  upper = rep(Inf, d),
  alpha = 1,
```

pmvss_mc 11

```
Q = NULL,
delta = rep(0, d),
which.stable = c("libstable4u", "stabledist")[1],
n = NULL
)
```

Arguments

lower the vector of lower limits of length n.

upper the vector of upper limits of length n.

alpha default to 1 (Cauchy). Must be 0<alpha<2

Q Shape matrix. See Nolan (2013).

delta location vector.

which.stable defaults to "libstable4u", other option is "stabledist". Indicates which package should provide the univariate stable distribution in this production distribution form of a univariate stable and multivariate normal.

number of random vectors to be drawn for Monte Carlo calculation.

Value

n

a number between 0 and 1, the estimated probability via Monte Carlo

References

Nolan JP (2013), *Multivariate elliptically contoured stable distributions: theory and estimation*. Comput Stat (2013) 28:2067–2089 DOI 10.1007/s00180-013-0396-7

Examples

```
## print("mvpd (d=2, alpha=1.71):")
U <- c(1,1)
L <- -U
Q <- matrix(c(10,7.5,7.5,10),2)
mvpd::pmvss_mc(L, U, alpha=1.71, Q=Q, n=1e3)
mvpd::pmvss (L, U, alpha=1.71, Q=Q)

## more accuracy = longer runtime
mvpd::pmvss_mc(L, U, alpha=1.71, Q=Q, n=1e4)

U <- c(1,1,1)
L <- -U
Q <- matrix(c(10,7.5,7.5,7.5,10,7.5,7.5,7.5,10),3)
## print("mvpd: (d=3, alpha=1.71):")
mvpd::pmvss_mc(L, U, alpha=1.71, Q=Q, n=1e3)</pre>
```

12 rmvss

rmvss

Multivariate Subgaussian Stable Random Variates

Description

Computes random vectors of the multivariate subgaussian stable distribution for arbitrary alpha, shape matrices, and location vectors. See Nolan (2013).

Usage

```
rmvss(
    n,
    alpha = 1,
    Q = NULL,
    delta = rep(0, d),
    which.stable = c("libstable4u", "stabledist")[1]
)
```

Arguments

n number of observations

alpha default to 1 (Cauchy). Must be 0<alpha<2

Q Shape matrix. See Nolan (2013).

delta location vector.

which.stable defaults to "libstable4u", other option is "stabledist". Indicates which

package should provide the univariate stable distribution in this production dis-

tribution form of a univariate stable and multivariate normal.

Value

Returns the n by d matrix containing multivariate subgaussian stable random variates where d=nrow(Q).

References

Nolan JP (2013), *Multivariate elliptically contoured stable distributions: theory and estimation*. Comput Stat (2013) 28:2067–2089 DOI 10.1007/s00180-013-0396-7

Examples

```
## generate 10 random variates of a bivariate mvss rmvss(n=10, alpha=1.71, Q=matrix(c(10,7.5,7.5,10),2)) ## generate 10 random variates of a trivariate mvss Q <- matrix(c(10,7.5,7.5,7.5,10,7.5,7.5,7.5,10),3) rmvss(n=10, alpha=1.71, Q=Q)
```

Index

```
\ast distribution
     dmvss, 3
     {\tt fit\_mvss}, {\tt 5}
    pmvss, 8
    rmvss, 12
*\ \textbf{integration}
     {\tt adaptIntegrate\_inf\_limPD, 2}
*\ multivariate
    adaptIntegrate_inf_limPD, 2
*\ numerical
    adaptIntegrate_inf_limPD, 2
adaptIntegrate_inf_limPD, 2
dmvss, 3, 7
fit_mvss, 5, 7
mvpd, 7
mvpd-package (mvpd), 7
pmvss, 7, 8
pmvss\_mc, 7, 10
rmvss, 7, 12
```