# VMware vSphere Integrated Containers for vSphere Administrators

vSphere Integrated Containers 1.1



## **Table of Contents**

phere Administrators	1.1
Overview for vSphere Admins	1.1.1
Interoperability	1.1.1.1
Networking	1.1.1.2
Installation	1.1.2
Download	1.1.2.1
Deploy the Appliance	1.1.2.2
Installing the Plug-ins	1.1.2.3
vCenter Server for Windows	1.1.2.3.1
vCenter Server Appliance	1.1.2.3.2
Access the vSphere Integrated Containers View	1.1.2.3.3
Find VCH Information	1.1.2.3.4
Find Container Information	1.1.2.3.5
DeployVCHs	1.1.3
Contents of the vSphere Integrated Containers Engine Binaries	1.1.3.1
Environment Prerequisites for VCH Deployment	1.1.3.2
Open the Required Ports on ESXi Hosts	1.1.3.3
Deploy a VCH to an ESXi Host with No vCenter Server	1.1.3.4
Deploy a VCH to a Basic vCenter Server Cluster	1.1.3.5
Verify the Deployment of a VCH	1.1.3.6
VCH Deployment Options	1.1.3.7
Advanced Examples of Deploying a VCH	1.1.3.8
Deploy a VCH for Use with vSphere Integrated Containers Registry	1.1.3.9
Use Different User Accounts for VCH Deployment and Operation	1.1.3.10
Upgrading	1.1.4
Upgrade the Appliance	1.1.4.1
Upgrade VCHs	1.1.4.2
VCH Upgrade Options	1.1.4.2.1
Upgrade Plug-In on Windows	1.1.4.3
Upgrade Plug-In VCSA	1.1.4.4
Upgrade 0.5 Registry	1.1.4.5
Managing the Appliance	1.1.5
Reconfigure the Appliance	1.1.5.1
Check Service Status	1.1.5.2
Restart Services	1.1.5.3
Managing VCHs	1.1.6
Obtain Version Information	1.1.6.
Common Options	1.1.6.2
List VCHs	1.1.6.3
Obtain VCH Information	1.1.6.4
Delete a VCH	1.1.6.5

VCH Delete Options	1.1.6.5.1
Debugging the VCH	1.1.6.6
Enable Shell Access	1.1.6.6.1
Authorize SSH Access	1.1.6.6.2
VCH Debug Options	1.1.6.6.3
Access the VCH Admin Portal	1.1.6.7
Browser-Based Certificate Login	1.1.6.7.1
Command Line Certificate Login	1.1.6.7.2
VCH Admin Status Reference	1.1.6.7.3
Access Log Bundles	1.1.6.8
Troubleshooting	1.1.7
VCH Deployment Times Out	1.1.7.1
Certificate Verification Error	1.1.7.2
Missing Common Name Error Even When TLS Options Are Specified Correctly	1.1.7.3
Firewall Validation Error	1.1.7.4
Certificate cname Mismatch	1.1.7.5
Docker API Endpoint Check Failed Error	1.1.7.6
No Single Host Can Access All Datastores	1.1.7.7
Plug-In Does Not Appear	1.1.7.8
Deleting or Inspecting a VCH Fails	1.1.7.9
Certificate Errors when Using Full TLS Authentication with Trusted Certificates	1.1.7.10
Security Reference	1.1.8

## vSphere Integrated Containers for vSphere Administrators

vSphere Integrated Containers for vSphere Administrators provides information about how to use VMware vSphere® Integrated Containers ™ as a vSphere administrator.

Product version: 1.1

This documentation applies to all 1.1.x releases.

## **Intended Audience**

This information is intended for VMware vSphere® administrators who want to install and set up vSphere Integrated Containers. The information is written for experienced vSphere administrators who are familiar with virtual machine technology and datacenter operations. Knowledge of container technology and Docker is useful.

Copyright © 2016, 2017 VMware, Inc. All rights reserved. Copyright and trademark information. Any feedback you provide to VMware is subject to the terms at www.vmware.com/community\_terms.html.

VMware, Inc.

3401 Hillview Ave. Palo Alto, CA94304

www.vmware.com

## Overview of vSphere Integrated Containers for vSphere Administrators

vSphere Integrated Containers enables IT teams to run traditional and container workloads side-by-side on existing infrastructure seamlessly. This overview is intended for vSphere administrators who intend to use vSphere Integrated Containers to manage container workloads in their vSphere environment.

- Introduction to Containers, Images and Volumes
  - Runtime
  - Packaging
- What is vSphere Integrated Containers?
- What Does vSphere Integrated Containers Engine Do?
- What Is vSphere Integrated Containers Engine For?
- vSphere Integrated Containers Engine Concepts
  - Container VMs
  - Virtual Container Hosts
  - The VCH Endpoint VM
  - The vic-machine Utility
- What Is vSphere Integrated Containers Registry?
- What Is vSphere Integrated Containers Management Portal

## Introduction to Containers, Images and Volumes

The word "container" is an overloaded one these days. When understanding containers and how they relate to vSphere Integrated Containers, it is helpful to distinguish the *runtime* aspect from the *packaging* aspect.

#### **Runtime**

At its most basic, a container is simply a sandbox in which a process can run. The sandbox isolates the process from other processes that are running on the same system. Acontainer has a lifecycle which is typically tied to the lifecycle of the process that it is designed to run. If you start a container, it starts its main process and when that process ends, the container stops. The container might have access to some storage. It typically has an identity on a network.

Conceptually, a container represents many of the same capabilities as a VM. The main difference between the two is the abstraction layer:

- Asoftware container is a sandbox within a guest OS and it is up to the guest to provide the container with its dependencies
  and to enforce isolation. Multiple containers share the guest kernel, networking, and storage. Acontainer does not boot. It is
  simply a slice of an already-running OS. The OS running the container is called its host.
- In contrast, a VM is a sandbox within a hypervisor. It is the hypervisor that provides a VM with its dependencies, such as
  virtual disks and NICs. AVM has to boot an OS and its lifecycle is typically tied to that of the OS rather than to that of any one
  process. By design, a VM is strongly isolated from other VMs and its host.

One of the most interesting facets of containers is how they deal with state. Any data that a container writes is non-persistent by default and is lost when that container is deleted. State, however, can persist beyond the lifespan of a container by attaching a *volume* to it or by sending it over a network. Binary dependencies that the container needs, such as OS libraries or application binaries, are encapsulated in *images*. Images are immutable.

#### **Packaging**

One of the most significant benefits of containers is that they allow you to package up the entire environment that an application needs and run it anywhere. You can go to Docker Hub, select from hundreds of thousands of applications and run that application anywhere that you have installed Docker on a compatible OS. The packaging encapsulates the binary dependencies, environment variables, volumes, and even the network configuration.

The format of this packaging is called an *image*. An image is a template from which many containers can instantiate. The Docker image format allows for images to be composed in a parent-child relationship, just like a disk snapshot. This image hierarchy allows containers to share common dependencies. For example, you might have a Debian 8 image that has a child image with Java installed. That Java image might have a child with Tomcat installed. The Debian 8 image might have other children, such as PHP, Python, and so on.

The immutability of the image format means that you never modify an image, you always create a new one. The layered nature of the image format means that you can cache commonly-used layers so that you only need to download or upload the layers that you do not already have. It also means that if you want to patch a particular image, you create a new image and then rebuild all of its children.

The main advantage of the image format is its portability. As long as you have a destination that is running a container engine, for example Docker, you can download and run an image on it. This portability is facilitated by a *registry*. Aregistry is a service that indexes and stores images. You can run your own private image registry that forms part of a development pipeline. You can *push* images to the registry from development, *pull* them into a test environment for verification, and then *pull* them into a production environment.

## What is vSphere Integrated Containers?

vSphere Integrated Containers comprises three major components:

- vSphere Integrated Containers Engine, a container runtime for vSphere that allows you to provision containers as virtual machines, offering the same security and functionality of virtual machines in VMware ESXi™ hosts or vCenter Server® instances.
- vSphere Integrated Containers Registry, an enterprise-class container registry server that stores and distributes container
  images. vSphere Integrated Containers Registry extends the Docker Distribution open source project by adding the
  functionalities that an enterprise requires, such as security, identity and management.
- vSphere Integrated Containers Management Portal, a container management portal that provides a UI for DevOps teams
  to provision and manage containers, including the ability to obtain statistics and information about container instances.
   Cloud administrators can manage container hosts and apply governance to their usage, including capacity quotas and
  approval workflows.

These components currently support the Docker image format. vSphere Integrated Containers is entirely Open Source and free to use. Support for vSphere Integrated Containers is included in the vSphere Enterprise Plus license.

vSphere Integrated Containers is designed to solve many of the challenges associated with putting containerized applications into production. It directly uses the clustering, dynamic scheduling, and virtualized infrastructure in vSphere and bypasses the need to maintain discrete Linux VMs as container hosts.

vSphere Integrated Containers allows you, the vSphere administrator, to provide a container management endpoint to a user as a service. At the same time, you remain in complete control over the infrastructure that the container management endpoint service depends on. The main differences between vSphere Integrated Containers and a classic container environment are the following:

- vSphere, not Linux, is the container host:
  - Containers are deployed as VMs, not in VMs.
  - Every container is fully isolated from the host and from the other containers.
  - vSphere provides per-tenant dynamic resource limits within a vCenter Server cluster
- vSphere, not Linux, is the infrastructure:
  - You can select vSphere networks that appear in the Docker client as container networks.
  - Images, volumes, and container state are provisioned directly to VMFS.
- vSphere is the control plane:
  - Use the Docker client to directly control selected elements of vSphere infrastructure.
  - Acontainer endpoint Service-as-a-Service presents as a service abstraction, not as laaS.

vSphere Integrated Containers is designed to be the fastest and easiest way to provision any Linux-based workload to vSphere, if that workload can be serialized as a Docker image.

## What Does vSphere Integrated Containers Do?

vSphere Integrated Containers gives you, the vSphere administrator, the tools to easily make your vSphere infrastructure accessible to users so that they can provision container workloads into production.

#### Scenario 1: A Classic Container Environment

In a classic container environment:

- Auser raises a ticket and says, "I need Docker".
- You provision a large Linux VM and send them the IP address.
- The user installs Docker, patches the OS, configures in-guest network and storage virtualization, secures the guest, isolates the containers, packages the containers efficiently, and manages upgrades and downtime.

In this scenario, what you have provided is similar to a nested hypervisor that they have to manage and which is opaque to you. If you scale that up to one large Linux VM per tenant, you end up creating a large distributed silo for containers.

#### Scenario 2: vSphere Integrated Containers

With vSphere Integrated Containers:

- Auser raises a ticket and says, "I need Docker".
- · You identify datastores, networking, and compute on your cluster that the user can use for their Docker environment.
- You use a utility called vic-machine to install a small appliance, called a virtual container host (VCH). The VCH represents
  an authorization to use the infrastructure that you have identified, into which the user can self-provision container
  workloads.
- The appliance runs a secure remote Docker API, that is the only access that the user has to the vSphere infrastructure.
- Instead of sending your user a Linux VM, you send them the IP address of the appliance, the port of the remote Docker API, and a certificate for secure access.

In this scenario, you have provided the user with a service portal. This is better for the user because they do not have to worry about isolation, patching, security, backup, and so on. It is better for you because every container that the user deploys is a container VM. You can perform vMotion and monitor container VMs just like all of your other VMs.

If the user needs more compute capacity, in Scenario 1, the pragmatic choice is to power down the VM and reconfigure it, or give the user a new VM and let them deal with the clustering implications. Both of these solutions are disruptive to the user. With vSphere Integrated Containers in Scenario 2, you can reconfigure the VCH in vSphere, or redeploy it with a new configuration in a way that is completely transparent to the user.

vSphere Integrated Containers allows you to select and dictate the appropriate infrastructure for the task in hand:

- Networking: You can select multiple port groups for different types of network traffic, ensuring that all of the containers that a user provisions get the appropriate interfaces on the right networks.
- Storage: You can select different vSphere datastores for different types of state. For example, container state is ephemeral
  and is unlikely to need to be backed up, but volume state almost certainly should be backed up. vSphere Integrated
  Containers automatically ensures that state gets written to the appropriate datastore when the user provisions a container.

To summarize, vSphere Integrated Containers gives you a mechanism that allows users to self-provision VMs as containers into your virtual infrastructure.


## What Is vSphere Integrated Containers Engine For?

vSphere Integrated Containers Engine currently offers a subset of the Docker API. It is designed to specifically address the provisioning of containers into production, solving many of the problems highlighted in What Does vSphere Integrated Containers Engine Do?.

vSphere Integrated Containers Engine exploits the portability of the Docker image format to present itself as an enterprise deployment target. Developers build containers on one system and push them to a registry. Containers are tested by another system and are approved for production. vSphere Integrated Containers Engine can then pull the containers out of the registry and deploy them to vSphere.

## vSphere Integrated Containers Engine Concepts

If you consider a Venn diagram with "What vSphere Does" in one circle and "What Docker Does" in another, the overlap is significant. The objective of vSphere Integrated Containers Engine is to take as much of vSphere as possible and layer whatever Docker capabilities are missing on top, reusing as much of Docker's own code as possible. The result should not sacrifice the portability of the Docker image format and should be completely transparent to a Docker client. The following sections describe key concepts and components that make this possible.



#### **Container VMs**

The container VMs that vSphere Integrated Containers Engine creates have all of the characteristics of software containers:

- An ephemeral storage layer with optionally attached persistent volumes.
- Acustom Linux guest OS that is designed to be "just a kernel" and that needs images to be functional.
- Amechanism for persisting and attaching read-only binary image layers.
- APID 1 guest agent tether extends the control plane into the container VM.
- Various well-defined methods of configuration and state ingress and egress
- Automatically configured to various network topologies.

The provisioned container VM does not contain any OS container abstraction.

- The container VM boots from an ISO that contains the Photon Linux kernel. Note that container VMs do not run the full Photon OS.
- The container VM is configured with a container image that is mounted as a disk.
- Container image layers are represented as a read-only VMDK snapshot hierarchy on a vSphere datastore. At the top of this hierarchy is a read-write snapshot that stores ephemeral state.
- Container volumes are formatted VMDKs that are attached as disks and indexed on a datastore.

• Networks are distributed port groups that are attached as vNICs.

#### **Virtual Container Hosts**

A virtual container host (VCH) is the functional equivalent of a Linux VM that runs Docker, but with some significant benefits. A VCH represents the following elements:

- · Aclustered pool of resource into which to provision container VMs.
- Asingle-tenant container namespace.
- An isolated Docker API endpoint.
- Authorization to use and configure pre-approved virtual infrastructure.
- · Aprivate network that containers are attached to by default.

If you deploy a VCH in a vCenter Server cluster it spans all of the hosts in the cluster, providing the same flexibility and dynamic use of host resources as is the norm.

AVCH is functionally distinct from a traditional container host in the following ways:

- It naturally encapsulates clustering and dynamic scheduling by provisioning to vSphere targets.
- The resource constraints are dynamically configurable with no impact on the containers.
- · Containers do not share a kernel.
- There is no local image cache. This is kept on a datastore in the cluster that you specify when you deploy a VCH.
- There is no read-write shared storage

AVCH is a multi-functional appliance that you deploy as a vApp in a vCenter Server cluster or as a resource pool on an ESXi host. The vApp or resource pool provides a useful visual parent-child relationship in the vSphere Client so that you can easily identify the container VMs that are provisioned into a VCH. You can also specify resource limits on the vApp. You can provision multiple VCHs onto a single ESXi host, into a vSphere resource pool, or into a vCenter Server cluster.

#### The VCH Endpoint VM

The VCH endoint VM is the VM that runs inside the VCH vApp or resource pool. There is a 1:1 relationship between a VCH and a VCH endpoint VM. The VCH endpoint VM provides the following functions:

- Runs the services that a VCH requires.
- Provides a secure remote API to a client.
- Receives Docker commands and translates those commands into vSphere API calls and vSphere infrastructure constructs
- Provides network forwarding so that ports to containers can be opened on the VCH endoint VM and the containers can access a public network.
- . Manages the lifecycle of the containers, the image store, the volume store, and the container state
- Provides logging and monitoring of its own services and of its containers.

The lifecycle of the VCH endpoint VM is managed by a utility called vic-machine.

#### The vic-machine Utility

The vic-machine utility is a binary for Windows, Linux, and OSX that manages the lifecycle of VCHs. vic-machine has been designed for use by vSphere administrators. It takes pre-existing compute, network, storage and a vSphere user as input and creates a VCH as output. It has the following additional functions:

- Creates certificates for Docker client TLS authentication.
- Checks that the prerequisites for VCH deployment are met on the cluster or host, namely that the firewall, licenses, and so on are configured correctly.
- Configures existing VCHs for debugging.
- Lists, inspects, upgrades, and deletes VCHs.

## What Is vSphere Integrated Containers Registry?

vSphere Integrated Containers Registry is an enterprise-class registry server that you can use to store and distribute container images. vSphere Integrated Containers Registry allows DevOps administrators to organize image repositories in projects, and to set up role-based access control to those projects to define which users can access which repositories. vSphere Integrated Containers Registry also provides rule-based replication of images between registries, implements Docker Content Trust, and provides detailed logging for project and user auditing.

For a more detailed overview of vSphere Integrated Containers Registry, see Managing Images, Projects, and Users with vSphere Integrated Containers Registry in vSphere Integrated Containers for DevOps Administrators.

## What Is vSphere Integrated Containers Management Portal?

vSphere Integrated Containers Management Portal is a highly scalable and very lightweight container management platform for deploying and managing container based applications. It is designed to have a small footprint and boot extremely quickly. vSphere Integrated Containers Management Portal is intended to provide DevOps administrators with automated deployment and lifecycle management of containers.

- Rule-based resource management, allowing DevOps administrators to set deployment preferences which let vSphere
  Integrated Containers Management Portal manage container placement.
- · Live state updates that provide a live view of the container system.
- Multi-container template management, that enables logical multi-container application deployments.

For a more information about vSphere Integrated Containers Management Portal, see View and Manage VCHs, Add Registries, and Provision Containers Through the Management Portal in vSphere Integrated Containers for DevOps Administrators.

## Interoperability of vSphere Integrated Containers with Other VMware Software

vSphere administrators can use vSphere to view and manage the vSphere Integrated Containers appliance, virtual container hosts (VCHs), and container VMs. You can use any vSphere feature to manage the vSphere Integrated Containers appliance without affecting its behavior.

This topic describes the interoperability of vSphere Integrated Containers Engine with other vSphere features and VMware products.

- Performing Operations on VCHs and Container VMs in vSphere
- VMware vRealize® Suite
- VMware vSphere vMotion®
- VMware vSphere High Availability
- VMware NSX®
- Maintenance Mode
- VMware vSAN™
- Enhanced Linked Mode Environments
- vSphere Features Not Supported in This Release

## Performing Operations on VCHs and Container VMs in vSphere

- If you restart a VCH endpoint VM, it comes back up in the same state that it was in when it shut down.
- If you use DHCP on the client network, the IP address of the VCH endpoint VM might change after a restart. Use vic-machine inspect to obtain the new IP address.
- Do not manually delete a VCH vApp, the VCH endpoint VM, or container VMs. Always use vic-machine delete to delete VCHs and use Docker commands to perform operations on container VMs.
- Manually restarting container VMs, either individually or by manually restarting the VCH vApp, can result in incorrect endtimes for container operations. Do not manually restart the vApp or container VMs. Always use Docker commands to perform operations on container VMs.

#### VMware vRealize Suite

Your organization could use VMware vRealize Automation to provide a self-provisioning service for VCHs, by using the vRealize Automation interface or APIs to request VCHs. At the end of the provisioning process, vRealize Automation would communicate the VCH endpoint VM address to the requester. If you deploy VCHs with TLS authentication, vic-machine create generates a file named vch\_name.env. The env file contains Docker environment variables that are specific to the VCH. vRealize Automation could potentially provide the env file at the end of a provisioning process for VCHs.

## VMware vSphere vMotion

You can use vMotion to move VCHs without needing to take the container VMs offline. The VCH endpoint VM does not need to be running for vMotion to occur on the container VMs. Clusters with a mix of container VMs and non-container VMs can use vMotion with fully automated DRS.

## VMware vSphere High Availability

You can apply vSphere High Availability to clusters on which VCHs and container VMs run. If the host on which a VCH or container VMs are running goes offline, the VCH and container VMs migrate to another host in the cluster. VCHs restart on the new host immediately. Container VMs that were running before the migration restart one by one, after the VCH has restarted.

## **VMware NSX**

You can deploy the vSphere Integrated Containers appliance on an NSX network. VCHs require distributed port groups and a bridge network. You can deploy VCHs to NSX networks if those networks are configured to provide distributed port groups. You can use NSX networks for the management, bridge, public, and container networks.

## **Maintenance Mode**

In a cluster with fully automated DRS, if you put a host into maintenance mode, DRS migrates the VCHs and container VMs to another host in the cluster. Putting hosts into maintenance mode requires manual intervention in certain circumstances:

- If VCHs and container VMs are running on a standalone ESXi host, you must power off the VCHs and container VMs before
  you put the host into maintenance mode.
- If container VMs have active docker attach sessions, you cannot put the host into maintenance mode until the attach sessions end.

#### VMware vSAN

VCHs maintain file system layers inherent in container images by mapping to discrete VMDK files, all of which can be housed in shared vSphere datastores, including vSAN, NFS, Fibre Channel, and iSCSI datastores.

#### **Enhanced Linked Mode Environments**

You can deploy VCHs in Enhanced Linked Mode environments. Any vCenter Server instance in the Enhanced Linked Mode environment can access VCH and container VM information.

## vSphere Features Not Supported in This Release

vSphere Integrated Containers Engine does not currently support the following vSphere features:

- vSphere Storage DRS™: You cannot configure VCHs to use Storage DRS datastore clusters. However, you can specify the path to a specific datastore within a Storage DRS datastore cluster by specifying the full inventory path to the datastore in the vic-machine create --image-store option. For example, --image-store /dc1/datastore/my-storage-pod/datastore1. You can also specify the relative path from a datastore folder in a datacenter, for example --image-store my-storage-pod/datastore1.
- vSphere Fault Tolerance: vSphere Integrated Containers does not implement vSphere Fault Tolerance. However, VCH processes that stop unexpectedly do restart automatically, independently of vSphere Fault Tolerance.
- vSphere Virtual Volumes™: You cannot use Virtual Volumes as the target datastores for image stores or volume stores.
- Snapshots: Creating and reverting to snapshots of the VCH endpoint VM or container VMs can cause vSphere Integrated Containers Engine not to function correctly.

## **Networks Used by vSphere Integrated Containers**

You can configure networks on a virtual container host (VCH) that are tied into the vSphere infrastructure. You define which networks are available to a VCH when you deploy the VCH.


Each network that a VCH uses is a port group on either a vCenter Server instance or ESXi host. You can deploy VCHs on NSX networks.

This topic provides an overview of the different network types that virtual container hosts use.

- High-Level View of VCH Networking
- Management Network
- Public Network
- Client Network
- Bridge Network
- Container Networks

## **High-Level View of VCH Networking**

The image below shows a high-level view of the networks that a VCH uses and how they connect to your vSphere environment, to vSphere Integrated Containers Registry and Management Portal, and to the Docker environment.



The following sections describe each of the VCH network types.

**IMPORTANT**: AVCH supports a maximum of 3 distinct network interfaces. The bridge network requires its own port group, at least two of the public, client, and management networks must share a network interface and therefore a port group. Container networks do not go through the VCH, so they are not subject to this limitation. This limitation will be removed in a future release.

## **Management Network**

The network for communication between the VCH, vCenter Server, and ESXi hosts. The VCH uses this network to provide the attach function of the Docker API.

**IMPORTANT**: Because the management network provides access to your vSphere environment, and because container VMs use this network to communicate with the VCH, always use a secure network for the management network. Ideally, use separate networks for the management network and the container networks.

You define the management network by setting the --management-network option when you run vic-machine create. For more detailed information about management networks, see the section on the --management-network option in VCH Deployment Options.

### **Public Network**

The network that container VMs use to connect to the internet. Ports that containers expose with docker create -p when connected to the default bridge network are made available on the public interface of the VCH endpoint VM via network address translation (NAT), so that containers can publish network services.

You define the public network by setting the --public-network option when you run vic-machine create. For more detailed information about management networks, see the section on the --public-network option in VCH Deployment Options.

### **Client Network**

The network on which the VCH endpoint VM makes the Docker API available to Docker clients. The client network isolates the Docker endpoints from the public network. VCHs can access vSphere Integrated Containers Registry over the client network, but it is recommended to connect to registries either over the public network or over the management network. vSphere Integrated Containers Management Portal and vSphere Integrated Containers Registry require a connection to the client network.

You define the Docker management endpoint network by setting the --client-network option when you run vic-machine create. For more detailed information about Docker management endpoint networks, see the section on the --client-network option in VCH Deployment Options.

## **Bridge Network**

The network or networks that container VMs use to communicate with each other. Each VCH requires a unique bridge network. The bridge network is a port group on a distributed virtual switch.

IMPORTANT: Do not use the bridge network for any other VM workloads, or as a bridge for more than one VCH.

You define the bridge networks by setting the --bridge-network option when you run vic-machine create. For more detailed information about bridge networks, see the section on the --bridge-network option in VCH Deployment Options.

Container application developers can also use docker network create to create additional bridge networks. These networks are represented by the User-Created Bridge Network in the image above. Additional bridge networks are created by IP address segregation and are not new port groups. You can define a range of IP addresses that additional bridge networks can use by defining the bridge-network-range option when you run vic-machine create. For more detailed information about how to set bridge network ranges, see the section on the bridge-network-range option.

### **Container Networks**

Container networks allow the vSphere administrator to make vSphere networks directly available to containers. This is done during deployment of a VCH by providing a mapping of the vSphere network name to an alias that is used inside the VCH endpoint VM. The mapped networks are then listed as available by the Docker API. Running docker network 1s shows these networks, and container developers can attach them to containers in the normal way by using commands such as docker run or create, with the --network=\_mapped-network-name\_ or docker network connect. The containers connected to container networks are connected directly to these networks, and traffic does not route though the VCH endpoint VM using NAT.

You can share one network alias between multiple containers. For more detailed information about setting up container networks, see the sections on the container-network-xxx options in Virtual Container Host Deployment Options.

## **Installing vSphere Integrated Containers**

You install vSphere Integrated Containers by deploying an OVAappliance. The OVAappliance provides access to all of the vSphere Integrated Containers components.

The installation process involves several steps.

- Download the OVA from http://www.vmware.com/go/download-vic.
- Deploy the OVA, providing configuration information for vSphere Integrated Containers Registry and vSphere Integrated Containers Management Portal. The OVA deploys an appliance VM that provides the following services:
  - Runs vSphere Integrated Containers Registry
  - Runs vSphere Integrated Containers Management Portal
  - Makes the vSphere Integrated Containers Engine binaries available for download
  - Hosts the vSphere Client plug-in packages for vCenter Server
- Run the scripts to install the vSphere Client plug-ins on vCenter Server.
- Run the command line utility, vic-machine, to deploy and manage virtual container hosts.

## **Download vSphere Integrated Containers**

You can download different versions of vSphere Integrated Containers, that have different levels of stability and support.

### Official Releases

To obtain the latest official release of vSphere Integrated Containers, go to the official vSphere Integrated Containers downloads page on vmware.com and download the OVAinstaller. The OVAinstaller allows you to deploy all of the vSphere Integrated Containers components.

Full support of vSphere Integrated Containers requires the vSphere Enterprise Plus license. To make a support request, contact VMware Global Support.

## Open Source Builds of vSphere Integrated Containers

You can obtain open source builds of vSphere Integrated Containers Engine, vSphere Integrated Containers Portal, and vSphere Integrated Containers Registry, that have different levels of stability.

- Download tagged open source software (OSS) versions of the vSphere Integrated Containers components that have been tested and released to the open source community, but that might not reflect the most up-to-date version of the code:
  - vSphere Integrated Containers Engine
  - vSphere Integrated Containers Registry
  - vSphere Integrated Containers Portal
- Download built vSphere Integrated Containers Engine binaries. Builds usually happen after every successful merge into
  the source code. These builds have been minimally tested for integration. You need a Google account to access these
  builds
- Build the latest source version of the vSphere Integrated Containers components:
  - vSphere Integrated Containers Engine
  - vSphere Integrated Containers Registry
  - vSphere Integrated Containers Portal

IMPORTANT: Open source builds are not supported by VMware Global Support.

- · You can obtain community support for open source builds by reporting bugs and creating issues on Github.
- For general questions, visit the vSphere Integrated Containers channel on Slack.com. If you do not have an @vmware.com or @emc.com email address, sign up at https://code.vmware.com/home to get an invitation.

## Deploy the vSphere Integrated Containers Appliance

You install vSphere Integrated Containers by deploying a virtual appliance. The appliance runs vSphere Integrated Containers Registry and vSphere Integrated Containers Management Portal, and makes the download of the vSphere Integrated Containers Engine binaries available.

#### **Prerequisites**

- You downloaded the OVAinstaller from the official vSphere Integrated Containers downloads page on vmware.com.
- Deploy the appliance to a vCenter Server instance. Deploying the appliance directly on an ESXi host is not supported.
- Deploy the appliance to a vCenter Server system that meets the minimum system requirements:
  - o 2 vCPUs
  - 8GB RAM
  - o 80GB free disk space on the datastore

#### **Procedure**

- 1. In the vSphere Web Client, right-click an object in the vCenter Server inventory, select **Deploy OVF template**, and navigate to the OVA file.
- 2. Follow the installer prompts to perform basic configuration of the appliance and to select the vSphere resources for it to use.
  - · Accept or modify the appliance name
  - Destination datacenter or folder
  - · Destination host, cluster, or resource pool
  - · Accept the end user license agreements (EULA)
  - · Disk format and destination datastore
  - · Network that the appliance connects to
- 3. On the **Customize template** page, under **Appliance Security**, set the root password for the appliance VM and optionally uncheck the **Permit Root Login** checkbox.

Setting the root password for the appliance is mandatory.

4. Expand Networking Properties and optionally configure a static IP address for the appliance VM.

Leave the networking properties blank to use DHCP.

**IMPORTANT**: If you set a static IP address for the appliance, use spaces to separate DNS servers. Do not use comma separation for DNS servers.

- 5. Expand Registry Configuration to configure the deployment of vSphere Integrated Containers Registry.
  - If you do not want to deploy vSphere Integrated Containers Registry, uncheck the Deploy Registry check box.
  - In the Registry Port text box, optionally change the port on which to publish the vSphere Integrated Containers Registry service.
  - In the Notary Port text box, optionally change the port on which to publish the Docker Notary service for vSphere Integrated Containers Registry.
  - In the Registry Admin Password text box, set the password for the vSphere Integrated Containers Registry admin account.
  - In the Database Password text box, set the password for the root user of the MySQL database that vSphere Integrated Containers Registry uses.
  - Optionally check the **Garbage Collection** check box to enable garbage collection when the appliance reboots.
  - To use custom certificates to authenticate connections to vSphere Integrated Containers Registry, optionally paste the
    content of the appropriate certificate and key files in the SSL Cert and SSL Cert Key text boxes. Leave the text boxes
    blank to use auto-generated certificates.
- 6. Expand **Management Portal Configuration** to configure the deployment of vSphere Integrated Containers Management Portal.
  - If you do not want to deploy vSphere Integrated Containers Management Portal, uncheck the Deploy Management Portal check box.

- In the Management Portal Port text box, optionally change the port on which to publish the vSphere Integrated Containers Management Portal service.
- To use custom certificates to authenticate connections to vSphere Integrated Containers Management Portal, optionally
  paste the content of the appropriate certificate and key files in the SSL Cert and SSL Cert Key text boxes. Leave the text
  boxes blank to use auto-generated certificates.
- 7. Expand **Fileserver Configuration** to configure the file server from which you download vSphere Integrated Containers Engine and which publishes the plug-in packages for the vSphere Client.
  - In the Fileserver Port text box, optionally change the port on which the vSphere Integrated Containers Engine file server
  - To use custom certificates to authenticate connections to the vSphere Integrated Containers Engine file server,
     optionally paste the content of the appropriate certificate and key files in the SSL Cert and SSL Cert Key text boxes.
     Leave the text boxes blank to use auto-generated certificates.
- 8. Click **Next** and **Finish** to deploy the vSphere Integrated Containers appliance.
- 9. When the deployment completes, power on the appliance VM.

#### What to Do Next

- Go to the file server that runs in the vSphere Integrated Containers appliance at https://vic\_appliance\_address:9443. If the vSphere Integrated Containers appliance uses a different port for the vSphere Integrated Containers Engine file server, replace 9443 with the appropriate port.
- Download the vSphere Integrated Containers Engine binaries bundle, vic\_1.1.x.tar.gz, from the file server. Unpack the
  bundle and start deploying virtual container hosts (VCHs). For information about deploying VCHs, see Using vic-machine to
  Deploy VCHs.
- Install the vSphere Client plug-ins for vSphere Integrated Containers.
  - **NOTE**: Do not download the client plug-in files, <code>com.vmware.vic-v1.1.x.zip</code> and <code>com.vmware.vic.ui-v1.1.x.zip</code>, directly from the file server. You install the vSphere Integrated Containers plug-ins by running a script that pulls these files from the file server. For information about installing the plug-ins, see <a href="Installing the vSphere Client Plug-ins">Installing the vSphere Client Plug-ins</a>.
- Log in to vSphere Integrated Containers Registry at https://vic\_appliance\_address:443. If the vSphere Integrated Containers appliance uses a different port for vSphere Integrated Containers Registry, replace 443 with the appropriate port. For information about how to use vSphere Integrated Containers Registry, see Managing Images, Projects, and Users with vSphere Integrated Containers Registry.
- Log in to vSphere Integrated Containers Management Portal: https://vic\_appliance\_address:8282. If the vSphere Integrated
  Containers appliance uses a different port for vSphere Integrated Containers Management Portal, replace 8282 with the
  appropriate port. For information about how to use vSphere Integrated Containers Management Portal, see View and
  Manage VCHs, Add Registries, and Provision Containers Through the Management Portal.

## Installing the vSphere Client Plug-Ins

vSphere Integrated Containers provides two UI plug-ins for vSphere:

- Abasic Flex-based plug-in that adds information about virtual container hosts (VCHs) and container VMs in the Flex-based vSphere Web Client. The basic plug-in works with the Flex-based vSphere Web Client for both vSphere 6.0 and 6.5.
- An HTML5 plug-in with more complete functionality for the HTML5 vSphere Client. The HTML5 vSphere Client is only available with vSphere 6.5.

You can deploy the plug-ins on a vCenter Server instance that runs on Windows, or on a vCenter Server Appliance.

For information about the Flex-based vSphere Web Client and the HTML5 vSphere Client for vSphere 6.5, see Introduction to the vSphere Client in the vSphere 6.5 documentation.

- Install the Client Plug-Ins on vCenter Server for Windows
- Install the Client Plug-Ins on a vCenter Server Appliance
- · Access the vSphere Integrated Containers View
- Find VCH Information in the vSphere Clients
- Find Container Information in the vSphere Clients

## Install the Client Plug-Ins on vCenter Server for Windows

To install the vSphere Client plug-ins for vSphere Integrated Containers, you log in to the Windows system on which vCenter Server runs and run a script. The script registers an extension with vCenter Server, and instructs vCenter Server to download the plug-in files from the file server in the vSphere Integrated Containers appliance.

- You can install the the Flex-based vSphere Web Client plug-in on vCenter Server 6.0 or 6.5.
- You can install the the HTML5 vSphere Client plug-in on vCenter Server 6.5.

#### **Prerequisites**

- The vCenter Server instance on which to install the plug-in runs on Windows. If you are running a vCenter Server appliance instance, see Install the Client Plug-Ins on a vCenter Server Appliance.
- You deployed the vSphere Integrated Containers appliance. For information about deploying the appliance, see Deploy the vSphere Integrated Containers Appliance.
- Log in to the Windows system on which vCenter Server is running. You must perform all of the steps in this procedure on this Windows system.
- Go to https://vic\_appliance\_address:9443 in a Web browser, download the vSphere Integrated Containers Engine package,
   vic\_1.1.x.tar.gz , and unpack it on the Desktop. Do not download the client plug-in files, com.vmware.vic-v1.1.x.zip and
   com.vmware.vic.ui-v1.1.x.zip , directly from the file server. The plug-in installation script pulls these files from the file server.

**NOTE**: If the vSphere Integrated Containers appliance uses a different port for the file server, replace 9443 with the appropriate port in the prerequisites above and in the procedure below.

#### **Procedure**

1. Open a command prompt as Administrator and run the following command to obtain the SHA-1 thumprint of the file server that is running in the vSphere Integrated Containers appliance.

```
echo | "%VMWARE_OPENSSL_BIN%" s_client -connect vic_appliance_address:9443 | "%VMWARE_OPENSSL_BIN%" x509 -fingerprint -sha1 -noout
```

2. Open the \vic\ui\vCenterForWindows\configs file in a text editor.

```
notepad %USERPROFILE%\Desktop\vic\ui\vCenterForWindows\configs
```

3. Enter the IPv4 address or FQDN of the vCenter Server instance on which to install the plug-in.

```
SET target_vcenter_ip=vcenter_server_address
```

4. Enter the URL of the vSphere Integrated Containers appliance file server.

```
SET vic_ui_host_url=https://vic_appliance_address:9443/
```

You must enter the full URL and include the closing forward slash ( / ) after the port number.

5. Copy the SHA-1 thumbprint of the file server that you obtained in step 1 and paste it into the configs file.

```
SET vic_ui_host_thumbprint=thumbprint
```

NOTE: Use colon delimitation in the thumbprint. Do not use space delimitation.

- 6 Save the configs file
- 7. Open the \vic\ui\vCenterForWindows\install.bat file in a text editor.

```
notepad %USERPROFILE%\Desktop\vic\ui\vCenterForWindows\install.bat
```

- 8. Insert a missing v character before %version%.zip in the following line and save the install.bat file:
  - Before: SET PLUGIN\_URL=%vic\_ui\_host\_url%key%-%version%.zip
  - After: SET PLUGIN\_URL=%vic\_ui\_host\_url%key%-v%version%.zip

9. Run the installer, entering the user name and password for the vCenter Server administrator account when prompted.

%USERPROFILE%\Desktop\vic\ui\vCenterForWindows\install.bat

This first run of the script installs the HTML5 client.

10. When the installation finishes, stop and restart the HTML5 vSphere Client service.

"C:\Program Files\VMware\vCenter Server\bin\service-control" --stop vsphere-ui

"C:\Program Files\VMware\vCenter Server\bin\service-control" --start vsphere-ui

11. To install the plug-in for the Flex-based vSphere Web Client, reopen the configs file and set the target version to 6.0.

SET target\_vc\_version=6.0

- 12. Save and close the configs file.
- 13. Run the installer again, entering the user name and password for the vCenter Server administrator account when prompted.

%USERPROFILE%\Desktop\vic\ui\vCenterForWindows\install.bat

14. When the installation finishes, stop and restart the vSphere Web Client service.

"C:\Program Files\VMware\vCenter Server\bin\service-control" --stop vspherewebclientsvc

"C:\Program Files\VMware\vCenter Server\bin\service-control" --start vspherewebclientsvc

#### What to Do Next

To verify the deployment of the plug-in, see Access the vSphere Integrated Containers View in the HTML5 vSphere Client, Find VCH Information in the vSphere Clients, and Find Container Information in the vSphere Clients.

## Install the Client Plug-Ins on a vCenter Server Appliance

You install the vSphere Client plug-ins for vSphere Integrated Containers by logging into the vCenter Server appliance and running a script. The script registers an extension with vCenter Server, and instructs vCenter Server to download the plug-in files from the file server in the vSphere Integrated Containers appliance.

- You can install the the Flex-based vSphere Web Client plug-in on vCenter Server 6.0 or 6.5.
- You can install the the HTML5 vSphere Client plug-in on vCenter Server 6.5.

#### **Prerequisites**

- You are installing the plug-ins on a vCenter Server appliance instance. If you are running vCenter Server on Windows, see Install the Client Plug-Ins on vCenter Server for Windows.
- Go to the vCenter Server Appliance Management Interface (VAMI) at https://vcsa\_address:5480, click **Access**, and make sure that Bash Shell is enabled.
- You deployed the vSphere Integrated Containers appliance. For information about deploying the appliance, see Deploy the vSphere Integrated Containers Appliance.

**NOTE**: If the vSphere Integrated Containers appliance uses a different port for the file server, replace 9443 with the appropriate port in the procedure below.

#### **Procedure**

1. Connect as root user to the vCenter Server Appliance by using SSH.

```
ssh root@vcsa_address
```

2. Use curl to copy the vSphere Integrated Containers Engine binaries from the vSphere Integrated Containers appliance file server to the vCenter Server Appliance.

```
curl -k https://vic_appliance_address:9443/vic_1.1.1.tar.gz -o vic_1.1.1.tar.gz
```

**NOTE**: Update vic\_1.1.x to the appropriate version in the command above and in the next step.

3. Unpack the vSphere Integrated Containers binaries.

```
tar -zxf vic_1.1.x.tar.gz
```

4. Use a text editor to set the vCenter Server address in the /vic/ui/vcsa/configs file.

```
VCENTER_IP="vcsa_address"
```

Alternatively, you can use a utility such as sed to update the configs file:

```
sed -i 's#^\(VCENTER_IP=\).*$#\1"vcsa_address"#' ~/vic/ui/*/configs
```

5. Set the URL of the vSphere Integrated Containers appliance file server in the /vic/ui/vCSA/configs file.

```
VIC_UI_HOST_URL="https://vic_appliance_address:9443/"
```

You must enter the full URL and include the closing forward slash ( / ) after the port number.

Alternatively, you can use sed:

```
sed -i 's#^\(VIC_UI_HOST_URL=\).*$#\1"https://vic_appliance_address:9443"#'
~/vic/ui/*/configs
```

6. Obtain the thumbprint of the vSphere Integrated Containers appliance file server certificate.

```
echo | openssl s_client -connect vic_appliance_address:9443 | openssl x509 -fingerprint - sha1 -noout
```

7. Set the certificate thumbprint in the /vic/ui/vcsA/configs file, replacing thumbprint with the output of the command from the preceding step.

```
VIC_UI_HOST_THUMBPRINT="thumbprint"
```

Alternatively, you can use sed:

```
sed -i 's#^\(VIC_UI_HOST_THUMBPRINT=\).*$#\1"thumbprint"#' ~/vic/ui/*/configs
```

8. Navigate to /vic/ui/vcsA, and run the installer script, entering the user name and password for the vCenter Server administrator account when prompted.

```
cd vic/ui/VCSA
```

```
./install.sh
```

This first run of the script installs the HTML5 client.

9. When the installation finishes, stop and restart the HTML5 vSphere Client service.

```
service-control --stop vsphere-ui
```

```
service-control --start vsphere-ui
```

10. To install the plug-in for the Flex-based vSphere Web Client, edit /vic/ui/vcsA/configs again and set the plug-in type to flex .

```
PLUGIN_TYPE="flex"
```

Alternatively, you can use sed:

```
sed -i 's#^\(PLUGIN_TYPE=\).*$#\1"flex"#' ~/vic/ui/*/configs
```

11. Run the installer script, entering the user name and password for the vCenter Server administrator account when prompted.

```
cd vic/ui/VCSA
```

```
./install.sh
```

12. When the installation finishes, stop and restart the Flex-based vSphere Web Client service.

```
service-control --stop vsphere-client
```

```
service-control --start vsphere-client
```

#### What to Do Next

To verify the deployment of the plug-in, see Access the vSphere Integrated Containers View in the HTML5 vSphere Client, Find VCH Information in the vSphere Clients, and Find Container Information in the vSphere Clients.

## Access the vSphere Integrated Containers View in the HTML5 vSphere Client

If you have installed the HTML5 plug-in for vSphere Integrated Containers, you can find information about your vSphere Integrated Containers deployment in the HTML5 vSphere Client.

**IMPORTANT**: Do not use the vSphere Client or to perform operations on virtual container host (VCH) appliances or container VMs. Specifically, using the vSphere Client to power off, power on, or delete VCH appliances or container VMs can cause vSphere Integrated Containers Engine to not function correctly. Always use vic-machine to perform operations on VCHs. Always use Docker commands to perform operations on containers.

#### Prerequisites

- You are running vCenter Server 6.5.
- You installed the HTML5 plug-in for vSphere Integrated Containers.

#### **Procedure**

- 1. Log in to the HTML5 vSphere Client and go to the **Home** page.
- 2. Click vSphere Integrated Containers.

#### Result

The vSphere Integrated Containers view presents the number of VCHs and container VMs that you have deployed.

NOTE: More functionality will be added to the vSphere Integrated Containers view in future releases.

## Find VCH Information in the vSphere Clients

After you have installed either or both of the HTML5 or Flex-based client plug-ins for vSphere Integrated Containers, you can find information about virtual container hosts (VCHs) in the HTML5 vSphere Client or the Flex-based vSphere Web Client.

**IMPORTANT**: Do not use the vSphere Client to perform operations on VCH appliances or container VMs. Specifically, using the vSphere Client to power off, power on, or delete VCH appliances or container VMs can cause vSphere Integrated Containers Engine to not function correctly. Always use vic-machine to perform operations on VCHs. Always use Docker commands to perform operations on containers.

#### Prerequisites

- You deployed a VCH.
- You installed either or both of HTML5 or Flex-based plug-ins for vSphere Integrated Containers.

#### **Procedure**

- 1. Log in to either the HTML5 vSphere Client or the Flex-based vSphere Web Client.
- 2. On the Home page, select Hosts and Clusters.
- 3. Expand the hierarchy of vCenter Server objects to navigate to the VCH vApp.
- 4. Expand the VCH vApp and select the VCH endpoint VM.
- 5. Click the Summary tab for the VCH endpoint VM and scroll down to the Virtual Container Host portlet.

#### Result

Information about the VCH appears in the VCH portlet in the Summary tab:

- The address of the Docker API endpoint for this VCH
- Alink to the VCH Admin portal for the VCH, from which you can obtain health information and download log bundles for the VCH.

## Find Container Information in the vSphere Clients

After you have installed either or both of the plug-ins for vSphere Integrated Containers, you can find information about the container VMs that are running in virtual container hosts (VCHs).

**IMPORTANT**: Do not use the vSphere Client to perform operations on VCH appliances or container VMs. Specifically, using the vSphere Client to power off, power on, or delete VCH appliances or container VMs can cause vSphere Integrated Containers Engine to not function correctly. Always use vic-machine to perform operations on VCHs. Always use Docker commands to perform operations on containers.

#### **Prerequisites**

- You deployed a VCH and pulled and ran at least one container.
- You installed either or both of HTML5 or Flex-based plug-ins for vSphere Integrated Containers.

#### **Procedure**

- 1. Log in to either the HTML5 vSphere Client or the Flex-based vSphere Web Client.
- 2. On the Home page, select Hosts and Clusters.
- 3. Expand the hierarchy of vCenter Server objects to navigate to the VCH vApp.
- 4. Expand the VCH vApp and select a container VM.
- 5. Click the Summary tab for the container VM and scroll down to the Container portlet.

#### Result

Information about the container VM appears in the Container portlet in the **Summary** tab:

- The name of the running container. If the container developer used docker run -name container\_name to run the container, container\_name appears in the portlet.
- The image from which the container was deployed.
- If the container developer used docker run -p port to map a port when running the container, the port number and the protocol appear in the portlet.

## Using vic-machine to Deploy Virtual Container Hosts

After you deploy the vSphere Integrated Containers appliance, you can download the vSphere Integrated Containers Engine binaries, vic\_1.1.x-version.tar.gz, from https://vic\_appliance\_address:9443. The vSphere Integrated Containers Engine binaries include the vic-machine utility, that you use to deploy virtual container hosts (VCHs).

- Contents of the vSphere Integrated Containers Engine Binaries
- Environment Prerequisites for VCH Deployment
- Open the Required Ports on ESXi Hosts
- Deploy a VCH to an ESXi Host with No vCenter Server
- Deploy a VCH to a Basic vCenter Server Cluster
- Verify the Deployment of a VCH
- VCH Deployment Options
- Advanced Examples of Deploying a VCH
- Deploy a VCH for Use with vSphere Integrated Containers Registry
- Use Different User Accounts for VCH Deployment and Operation

## **Contents of the vSphere Integrated Containers Engine Binaries**

You download vSphere Integrated Containers Engine binaries from https://vic\_appliance\_address:9443. When you unpack the vSphere Integrated Containers Engine binary bundle, you obtain following files:

File	Description
appliance.iso	The Photon based boot image for the virtual container host (VCH) endpoint VM
bootstrap.iso	The Photon based boot image for the container VMs.
ui/	Afolder that contains the files and scripts for the installation of the vSphere Client plug-in.
vic-machine-darwin	The OSX command line utility for the deployment and management of VCHs.
vic-machine-linux	The Linux command line utility for the deployment and management of VCHs.
vic-machine-windows.exe	The Windows command line utility for the deployment and management of VCHs.
vic-ui-darwin	The OSX executable for the deployment of the vSphere Client plug-in.
	NOTE: Do not run this executable directly. <sup>(1)</sup>
vic-ui-linux	The Linux executable for the deployment of the vSphere Client plug-in.
	NOTE: Do not run this executable directly. <sup>(1)</sup>
vic-ui-windows.exe	The Windows executable for the deployment of the vSphere Client plug-in.
	NOTE: Do not run this executable directly. <sup>(1)</sup>
README	Contains a link to the vSphere Integrated Containers Engine repository on GitHub.
LICENSE	The license file.

<sup>(1)</sup> For information about how to install the vSphere Client plug-in, see Installing the vSphere Client Plug-Ins.

## **Environment Prerequisites for VCH Deployment**

Before you deploy vSphere Integrated Containers Engine, you must ensure that your vSphere infrastructure meets the requirements.

- Supported Platforms for vic-machine
- · Supported vSphere Configurations
- License Requirements
- ESXi Host Firewall Requirements
- ESXi Host Storage Requirements for vCenter Server Clusters
- General Network Requirements
- vCenter Server Network Requirements

## **Supported Platforms for** vic-machine

The vSphere Integrated Containers management utility, vic-machine, has been tested and verified on the following 64-bit Windows, Mac OS, and Linux OS systems.

Platform	Supported Versions
Windows	7, 10
Mac OS X	10.11 (El Capitan)
Linux	Ubuntu 16.04 LTS

Other recent 64-bit OS versions should work but are untested.

## **Supported vSphere Configurations**

You can deploy vSphere Integrated Containers Engine in the following vSphere setups:

- vCenter Server 6.0 or 6.5, managing a cluster of ESXi 6.0 or 6.5 hosts, with VMware vSphere Distributed Resource Scheduler™ (DRS) enabled.
- vCenter Server 6.0 or 6.5, managing one or more standalone ESXi 6.0 or 6.5 hosts.
- Standalone ESXi 6.0 or 6.5 host that is not managed by a vCenter Server instance.

#### Caveats and limitations:

- VMware does not support the use of nested ESXi hosts, namely running ESXi in virtual machines. Deploying vSphere
  Integrated Containers Engine to a nested ESXi host is acceptable for testing purposes only.
- If you deploy a virtual container host (VCH) onto an ESXi host that is not managed by vCenter Server, and you then move that
  host into a cluster, the VCH might not function correctly.

## License Requirements

vSphere Integrated Containers Engine requires a vSphere Enterprise Plus license.

All of the ESXi hosts in a cluster require an appropriate license. Deployment fails if your environment includes one or more ESXi hosts that have inadequate licenses.

## **ESXi Host Firewall Requirements**

To be valid targets for VCHs and container VMs, ESXi hosts must have the following firewall configuration:

• Allow outbound TCP traffic to port 2377 on the endpoint VM, for use by the interactive container shell.

• Allow inbound HTTPS/TCP traffic on port 443, for uploading to and downloading from datastores.

These requirements apply to standalone ESXi hosts and to ESXi hosts in vCenter Server clusters.

For information about how to open ports on ESXi hosts, see Open the Required Ports on ESXi Hosts.

## **ESXi Host Storage Requirements for vCenter Server Clusters**

ESXi hosts in vCenter Server clusters must meet the following storage requirements in order to be usable by a VCH:

- Be attached to the datastores that you will use for image stores and volume stores.
- Have access to shared storage to allow VCHs to use more than one host in the cluster.

For information about image stores and volumes stores, see the Datastore Options section of VCH Deployment Options.

## **General Network Requirements**

The following network requirements apply to deployment of VCHs to standalone ESXi hosts and to vCenter Server:

- Use a trusted network for the deployment and use of vSphere Integrated Containers Engine.
- Use a trusted network for the management network.
- Connections between Docker clients and the VCH are encrypted via TLS unless you explicitly disable TLS. The client network does not need to be trusted.
- Each VCH requires an IPv4 address on each of the networks that it is connected to. The bridge network is handled internally, but other interfaces must have a static IP configured on them, or be able to acquire one via DHCP.
- Each VCH requires access to at least one network, for use as the public network. You can share this network between multiple VCHs. The public network does not need to be trusted.
- Do not share the bridge network interface with with any other network, unless you ensure that the bridge IP ranges do not conflict with other VCHs or VMs on that network. It is highly recommended that a bridge network be solely for use by only one VCH.

## vCenter Server Network Requirements

The following network requirements apply to the deployment of VCHs to vCenter Server:

- Create a distributed virtual switch with a port group for each VCH, for use as the bridge network. You can create multiple port groups on the same distributed virtual switch, but each VCH requires its own port group for the bridge network.
- Optionally create port groups for use as mapped container networks.
- All hosts in a cluster must be attached to the port groups that you will use for the VCH bridge network and for any mapped container networks.
- Isolate the bridge network and any mapped container networks. You can isolate networks by using a separate VLAN for each network.

For information about bridge networks and container networks, see the --bridge-network and --container-network options in VCH Deployment Options.

For information about how to create a distributed virtual switch and a port group, see Create a vSphere Distributed Switch in the vSphere documentation.

For information about how to add hosts to a distributed virtual switch, see Add Hosts to a vSphere Distributed Switch in the vSphere documentation.

For information about how to assign a VLAN ID to a port group, see VMware KB 1003825. For more information about private VLAN, see VMware KB 1010691.

## Open the Required Ports on ESXi Hosts

ESXi hosts communicate with the virtual container hosts (VCHs) through port 2377 via Serial Over LAN. For the deployment of a VCH to succeed, port 2377 must be open for outgoing connections on all ESXi hosts before you run vic-machine create to deploy a VCH. Opening port 2377 for outgoing connections on ESXi hosts opens port 2377 for inbound connections on the VCHs.

The vic-machine utility includes an update firewall command, that you can use to modify the firewall on a standalone ESXi host or all of the ESXi hosts in a cluster.

You use the --allow and --deny flags to enable and disable a firewall rule named vspc. When enabled, the vspc rule allows all outbound TCP traffic from the target host or hosts. If you disable the rule, you must configure the firewall via another method to allow outbound connections on port 2377 over TCP. If you do not enable the rule or configure the firewall, vSphere Integrated Containers Engine does not function, and you cannot deploy VCHs.

The vic-machine create command does not modify the firewall. Run vic-machine update firewall --allow before you run vic-machine create .

#### **Prerequisites**

- Deploy the vSphere Integrated Containers appliance. For information about deploying the appliance, see Deploy the vSphere Integrated Containers Appliance.
- Download the vSphere Integrated Containers Engine bundle, vic\_1.1.0-version.tar.gz, from
   https://vic\_appliance\_address:9443 and unpack it on your working machine. If you configured the appliance to use a
   different port for the file server, replace 9443 with the appropriate port.

#### **Procedure**

- 1. Open a terminal on the system on which you downloaded and unpacked the vSphere Integrated Containers Engine binary
- 2. Navigate to the directory that contains the vic-machine utility:
- 3. Run the vic-machine update firewall command.

To open the appropriate ports on all of the hosts in a vCenter Server cluster, run the following command:

```
$ vic-machine-operating_system update firewall
--target vcenter_server_address
--user "Administrator@vsphere.local"
--password vcenter_server_password
--compute-resource cluster_name
--thumbprint thumbprint
--allow
```

To open the appropriate ports on an ESXi host that is not managed by vCenter Server, run the following command:

```
$ vic-machine-operating_system update firewall
--target esxi_host_address
--user root
--password esxi_host_password
--thumbprint thumbprint
--allow
```

The vic-machine update firewall command in these examples specifies the following information:

- The address of the vCenter Server instance and datacenter, or the ESXi host, on which to deploy the VCH in the --target option.
- The user name and password for the vCenter Server instance or ESXi host in the --user and --password options.
- In the case of a vCenter Server cluster, the name of the cluster in the --compute-resource option.

• The thumbprint of the vCenter Server or ESXI host certificate in the --thumbprint option, if they use untrusted, self-signed certificates.

**NOTE**: Use upper-case letters and colon delimitation in the thumbprint. Do not use space delimitation.

• The --allow option to open the port.

## Deploy a VCH to an ESXi Host with No vCenter Server

This topic provides instructions for deploying a virtual container host (VCH) to an ESXi host that is not managed by vCenter Server. This is the most straightforward way to deploy a VCH, and is ideal for testing.

#### **Prerequisites**

- Deploy the vSphere Integrated Containers appliance. For information about deploying the appliance, see Deploy the vSphere Integrated Containers Appliance.
- Download the vSphere Integrated Containers Engine bundle, vic\_1.1.x-version.tar.gz, from
   https://vic\_appliance\_address:9443 and unpack it on your working machine. If you configured the appliance to use a
   different port for the file server, replace 9443 with the appropriate port.
- Create or obtain an ESXi host with the following configuration:
  - One datastore
  - The VM Network is present
  - · You can use a nested ESXi host for this example
- Verify that the ESXi host meets the requirements in Environment Prerequisites for VCH Deployment.
- Make sure that the correct firewall port is open on the ESXi host. For information about how to open ports on ESXi hosts, see Open the Required Ports on ESXi Hosts.
- Familiarize yourself with the vSphere Integrated Containers Engine binaries, as described in Contents of the vSphere Integrated Containers Engine Binaries.
- Familiarize yourself with the options of the vic-machine create command described in VCH Deployment Options.

#### **Procedure**

- Open a terminal on the system on which you downloaded and unpacked the vSphere Integrated Containers Engine binary bundle.
- 2. Navigate to the directory that contains the vic-machine utility:
- 3. Run the vic-machine create command.

Wrap any option arguments that include spaces or special characters in quotes. Use single quotes if you are using <code>vic-machine</code> on a Linux or Mac OS system and double quotes on a Windows system. In these examples, the password is wrapped in quotes because it contains <code>@</code>.

Linux OS:

```
$ vic-machine-linux create
--target esxi_host_address
--user root
--password 'esxi_host_p@ssword'
--no-tlsverify
--force
```

Windows:

```
$ vic-machine-windows create
--target esxi_host_address
--user root
--password "esxi_host_p@ssword"
--no-tlsverify
--force
```

Mac OS:

```
$ vic-machine-darwin create
--target esxi_host_address
--user root
--password 'esxi_host_p@ssword'
```

```
--no-tlsverify
--force
```

The vic-machine create command in this example specifies the minimum information required to deploy a VCH to an ESXi host:

- The address of the ESXi host on which to deploy the VCH, in the --target option.
- The ESXi host root user and password in the --user and --password options.
- Disables the verification of clients that connect to this VCH by specifying the --no-tlsverify option.
- Disables the verification of the ESXi host certificate by specifying the --force option.

Because the ESXI host only has only one datastore and uses the VM Network network, vic-machine create automatically detects and uses those resources.

When deploying to an ESXi host, vic-machine create creates a standard virtual switch and a port group for use as the container bridge network, so you do not need to specify any network options if you do not have specific network requirements.

This example deploys a VCH with the default name virtual-container-host .

#### Result

At the end of a successful deployment, vic-machine displays information about the new VCH:

```
Initialization of appliance successful
VCH Admin Portal:
https://vch_address:2378
Published ports can be reached at:
vch_address

Docker environment variables:
DOCKER_HOST=vch_address:2376
Environment saved in virtual-container-host/virtual-container-host.env
Connect to docker:
docker -H vch_address:2376 --tls info
Installer completed successfully
```

#### What to Do Next

To test your VCH, see Verify the Deployment of a VCH.

For examples of commands to deploy a VCH in various other vSphere configurations, see Advanced Examples of Deploying a VCH.

# Deploy a VCH to a Basic vCenter Server Cluster

This topic provides instructions for deploying a virtual container host (VCH) in a very basic vCenter Server environment. This basic deployment allows you to test vSphere Integrated Containers Engine with vCenter Server before attempting a more complex deployment that corresponds to your real vSphere environment.

The vCenter Server instance to which you deploy the VCH must match the specifications listed in the prerequisites.

#### **Prerequisites**

- Deploy the vSphere Integrated Containers appliance. For information about deploying the appliance, see Deploy the vSphere Integrated Containers Appliance.
- Download the vSphere Integrated Containers Engine bundle, vic\_1.1.x-version.tar.gz, from
   https://vic\_appliance\_address:9443 and unpack it on your working machine. If you configured the appliance to use a
   different port for the file server, replace 9443 with the appropriate port.
- Create or obtain a vCenter Server instance with the following configuration:
  - One datacenter
  - o One cluster with two ESXi hosts and DRS enabled. You can use nested ESXi hosts for this example.
  - Ashared datastore, that is accessible by both of the ESXi hosts.
  - The VM Network is present
  - One distributed virtual switch with one port group named vic-bridge
- Verify that your vCenter Server instance and both of the ESXi hosts in the cluster meet the requirements in Environment Prerequisites for VCH Deployment.
- Make sure that the correct firewall ports are open on the ESXi hosts. For information about how to open ports on ESXi hosts, see Open the Required Ports on ESXi Hosts.
- Familiarize yourself with the vSphere Integrated Containers Engine binaries, as described in Contents of the vSphere Integrated Containers Engine Binaries.
- Familiarize yourself with the options of the vic-machine create command described in VCH Deployment Options.

## Procedure

- 1. Open a terminal on the system on which you downloaded and unpacked the vSphere Integrated Containers Engine binary
- 2. Navigate to the directory that contains the vic-machine utility:
- 3. Run the vic-machine create command.

Wrap any option arguments that include spaces or special characters in quotes. Use single quotes if you are using <code>vic-machine</code> on a Linux or Mac OS system and double quotes on a Windows system. In these examples, the user name is wrapped in quotes because it contains <code>@</code>.

· Linux OS:

```
$ vic-machine-linux create
--target vcenter_server_address
--user 'Administrator@vsphere.local'
--password vcenter_server_password
--bridge-network vic-bridge
--image-store shared_datastore_name
--no-tlsverify
--force
```

• Windows:

```
$ vic-machine-windows create
--target vcenter_server_address
--user "Administrator@vsphere.local"
--password vcenter_server_password
--bridge-network vic-bridge
```

```
--image-store shared_datastore_name
--no-tlsverify
--force
```

#### Mac OS:

```
$ vic-machine-darwin create
--target vcenter_server_address
--user 'Administrator@vsphere.local'
--password vcenter_server_password
--bridge-network vic-bridge
--image-store shared_datastore_name
--no-tlsverify
--force
```

The vic-machine create command in this example specifies the minimum information required to deploy a VCH to vCenter Server:

- The address of the vCenter Server instance on which to deploy the VCH, in the --target option.
- The vCenter Single Sign-On user and password in the --user and --password options.
- The port group named vic-bridge, for use as the container bridge network.
- The name of the shared datastore to use as the image store, in which to store container images.
- Disables the verification of clients that connect to this VCH by specifying the --no-tlsverify option.
- Disables the verification of the vCenter Server certificate by specifying the --force option.

Because the vCenter Server instance only has one datacenter and one cluster, and uses the VM Network network, vic-machine create automatically detects and uses these resources.

This example deploys a VCH with the default name virtual-container-host .

#### Result

At the end of a successful deployment, vic-machine displays information about the new VCH:

```
Initialization of appliance successful
VCH Admin Portal:
https://vch_address:2378
Published ports can be reached at:
vch_address
Docker environment variables:
DOCKER_HOST=vch_address:2376
Environment saved in virtual-container-host/virtual-container-host.env
Connect to docker:
docker -H vch_address:2376 --tls info
Installer completed successfully
```

#### What to Do Next

To test your VCH, see Verify the Deployment of a VCH.

For examples of commands to deploy a VCH in various other vSphere configurations, see Advanced Examples of Deploying a VCH.

# Verify the Deployment of a VCH

After you have deployed a virtual container host (VCH), you can verify the deployment by connecting a Docker client to the VCH and running Docker operations. You can check the results in the vSphere Client or vSphere Web Client.

**IMPORTANT**: Do not use the vSphere Client or vSphere Web Client to perform operations on VCH appliances or container VMs. Specifically, using the vSphere Client or vSphere Web Client to power off, power on, or delete VCH appliances or container VMs can cause vSphere Integrated Containers Engine to not function correctly. Always use vic-machine to perform operations on VCHs. Always use Docker commands to perform operations on containers.

#### **Prerequisites**

- You followed the instructions in Deploy a VCH to an ESXI Host with No vCenter Server or Deploy a VCH to a Basic vCenter Server Cluster to deploy a VCH to either an ESXI host or to a vCenter Server instance.
- Youran vic-machine create with the --no-tlsverify option.
- · You have installed a Docker client.
- If you deployed the VCH to vCenter Server, connect a vSphere Web Client to that vCenter Server instance.
- If you deployed the VCH to an ESXi host, connect a vSphere Client to that host.

#### **Procedure**

- 1. View the VCH appliance in the vSphere Web Client or vSphere Client.
  - vCenter Server: Go to Hosts and Clusters in the vSphere Web Client and select the cluster or host on which you
    deployed the VCH. You should see a vApp with the name that you set for the VCH.
  - ESXi host: Go to **Inventory** in the vSphere Client and select the host on which you deployed the VCH. You should see a resource pool with the name that you set for the VCH.

The vApp or resource pool contains the VCH endpoint VM.

2. Run the docker info command to confirm that you can connect to the VCH.

```
docker -H vch_address:2376 --tls info
```

You should see confirmation that the Storage Driver is  $\mbox{ vSphere Integrated Containers Backend Engine }.$ 

3. Pull a Docker container image into the VCH, for example, the BusyBox container.

```
docker -H vch_address:2376 --tls pull busybox
```

- 4. View the container image files in the vSphere Web Client or vSphere Client.
  - vCenter Server: Go to Storage, right-click the datastore that you designated as the image store, and select Browse Files.
  - ESXi host: Click the **Summary** tab for the ESXi host, right-click the datastore that you designated as the image store, and select **Browse Datastore**.

vSphere Integrated Containers Engine creates a folder a folder that has the same name as the VCH, that contains a folder named vic in which to store container image files.

- 5. Expand the vic folder to navigate to the images folder. The images folder contains a folder for every container image that you pull into the VCH. The folders contain the container image files.
- 6. In your Docker client, run the Docker container that you pulled into the VCH.

```
docker -H vch_address:2376 --tls run --name test busybox
```

- 7. View the container VMs in the vSphere Web Client or vSphere Client.
  - vCenter Server: Go to Hosts and Clusters and expand the VCH vApp.
  - ESXi host: Go to Inventory and expand the VCH resource pool.

You should see a VM for every container that you run, including a VM named  ${\tt test-container\_id}$  .

- 8. View the container VM files in the vSphere Web Client or vSphere Client.
  - vCenter Server: Go to **Storage** and select the datastore that you designated as the image store.
  - ESXi host: Click the **Summary** tab for the ESXi host, right-click the datastore that you designated as the image store, and select **Browse Datastore**.

At the top-level of the datastore, you should see a folder for every container that you run. The folders contain the container VM files.

# **VCH Deployment Options**

The command line utility for vSphere Integrated Containers Engine, vic-machine, provides a create command with options that allow you to customize the deployment of virtual container hosts (VCHs) to correspond to your vSphere environment.

- vSphere Target Options
- Security Options
- Private Registry Options
- Datastore Options
- Networking Options
- · General Deployment Options

To allow you to fine-tune the deployment of VCHs, vic-machine create provides Advanced Options.

- Options for Specifying a Static IP Address for the VCH Endpoint VM
- Options for Configuring a Non-DHCP Network for Container Traffic
- Options to Configure VCHs to Use Proxy Servers
- Advanced Resource Management Options
- Other Advanced Options

## **vSphere Target Options**

The create command of the vic-machine utility requires you to provide information about where in your vSphere environment to deploy the VCH and the vCenter Server or ESXi user account to use.

## --target

Short name: -t

The IPv4 address, fully qualified domain name (FQDN), or URL of the ESXi host or vCenter Server instance on which you are deploying a VCH. This option is always **mandatory**.

To facilitate IP address changes in your infrastructure, provide an FQDN whenever possible, rather than an IP address. If vic-machine create cannot resolve the FQDN, it fails with an error.

• If the target ESXi host is not managed by vCenter Server, provide the address of the ESXi host.

```
--target esxi_host_address
```

 If the target ESXi host is managed by vCenter Server, or if you are deploying to a cluster, provide the address of vCenter Server.

```
--target vcenter_server_address
```

You can include the user name and password in the target URL. If you are deploying a VCH on vCenter Server, specify the
username for an account that has the Administrator role on that vCenter Server instance.

```
--target vcenter_or_esxi_username:password@vcenter_or_esxi_address
```

Wrap the user name or password in single quotes (Linux or Mac OS) or double quotes (Windows) if they include special characters.

```
'vcenter_or_esxi_usern@me':'p@ssword'@vcenter_or_esxi_address
```

If you do not include the user name in the target URL, you must specify the user option. If you do not specify the password option or include the password in the target URL, vic-machine create prompts you to enter the password.

You can configure a VCH so that it uses a non-administrator account for post-deployment operations by specifying the \_\_\_\_ ops-user option.

If you are deploying a VCH on a vCenter Server instance that includes more than one datacenter, include the datacenter
name in the target URL. If you include an invalid datacenter name, vic-machine create fails and suggests the available
datacenters that you can specify.

```
--target vcenter_server_address/datacenter_name
```

Wrap the datacenter name in single quotes (') on Mac OS and Linux and in double quotes (") on Windows if it includes spaces.

```
--target vcenter_server_address/'datacenter name'
```

#### --user

Short name: -u

The username for the ESXi host or vCenter Server instance on which you are deploying a VCH.

If you are deploying a VCH on vCenter Server, specify a username for an account that has the Administrator role on that vCenter Server instance.

```
--user esxi_or_vcenter_server_username
```

Wrap the user name in single quotes (') on Mac OS and Linux and in double quotes (") on Windows if it includes special characters.

```
--user 'esxi_or_vcenter_server_usern@me'
```

You can specify the username in the URL that you pass to vic-machine create in the target option, in which case the user option is not required.

You can configure a VCH so that it uses a non-administrator account for post-deployment operations by specifying the option.

## --password

Short name: -p

The password for the user account on the vCenter Server on which you are deploying the VCH, or the password for the ESXi host if you are deploying directly to an ESXi host. If not specified, vic-machine prompts you to enter the password during deployment.

```
--password esxi_host_or_vcenter_server_password
```

Wrap the password in single quotes (') on Mac OS and Linux and in double quotes (") on Windows if it includes special characters.

```
--password 'esxi_host_or_vcenter_server_p@ssword'
```

You can also specify the username and password in the URL that you pass to vic-machine create in the target option, in which case the password option is not required.

## --compute-resource

Short name: -r

The host, cluster, or resource pool in which to deploy the VCH.

If the vCenter Server instance on which you are deploying a VCH only includes a single instance of a standalone host or cluster, vic-machine create automatically detects and uses those resources. In this case, you do not need to specify a compute resource when you run vic-machine create. If you are deploying the VCH directly to an ESXI host and you do not use --compute-resource to specify a resource pool, vic-machine create automatically uses the default resource pool.

You specify the --compute-resource option in the following circumstances:

- AvCenter Server instance includes multiple instances of standalone hosts or clusters, or a mixture of standalone hosts and clusters
- You want to deploy the VCH to a specific resource pool in your environment.

If you do not specify the --compute-resource option and multiple possible resources exist, or if you specify an invalid resource name, vic-machine create fails and suggests valid targets for --compute-resource in the failure message.

• To deploy to a specific resource pool on an ESXI host that is not managed by vCenter Server, specify the name of the resource pool:

```
--compute-resource resource_pool_name
```

To deploy to a vCenter Server instance that has multiple standalone hosts that are not part of a cluster, specify the IPv4
address or fully qualified domain name (FQDN) of the target host:

```
--compute-resource host_address
```

To deploy to a vCenter Server with multiple clusters, specify the name of the target cluster:

```
--compute-resource cluster_name
```

• To deploy to a specific resource pool on a standalone host that is managed by vCenter Server, or to a specific resource pool in a cluster, if the resource pool name is unique across all hosts and clusters, specify the name of the resource pool:

```
--compute-resource resource_pool_name
```

To deploy to a specific resource pool on a standalone host that is managed by vCenter Server, if the resource pool name is
not unique across all hosts, specify the IPv4 address or FQDN of the target host and name of the resource pool:

```
--compute-resource host_name/resource_pool_name
```

• To deploy to a specific resource pool in a cluster, if the resource pool name is not unique across all clusters, specify the full path to the resource pool:

```
--compute-resource cluster_name/Resources/resource_pool_name
```

 Wrap resource names in single quotes (') on Mac OS and Linux and in double quotes (") on Windows if they include spaces:

```
--compute-resource 'resource pool name'
```

```
--compute-resource 'cluster name'/Resources/'resource pool name'
```

## --thumbprint

Short name: None

The thumbprint of the vCenter Server or ESXi host certificate. Specify this option if your vSphere environment uses untrusted, self-signed certificates. If your vSphere environment uses trusted certificates that are signed by a known Certificate Authority (CA), you do not need to specify the --thumbprint option.

**NOTE** If your vSphere environment uses untrusted, self-signed certificates, you can run vic-machine create without the --thumbprint option by using the --force option. However, running vic-machine create with the --force option rather than providing the certificate thumbprint is not recommended, because it permits man-in-the-middle attacks to go undetected.

To obtain the thumbprint of the vCenter Server or ESXi host certificate, run vic-machine create without the specifying the -thumbprint or --force options. The deployment of the VCH fails, but the resulting error message includes the required
certificate thumbprint. You can copy the thumbprint from the error message and run vic-machine create again, including the -thumbprint option.

**NOTE**: If you obtain the thumbprint by other means, use upper-case letters and colon delimitation in the thumbprint. Do not use space delimitation.

--thumbprint certificate\_thumbprint

# **Security Options**

The security options that vic-machine create provides allow for 3 broad categories of security:

- Restrict access to the Docker API with Auto-Generated Certificates
- Restrict access to the Docker API with Custom Certificates
- Do Not Restrict Access to the Docker API

You can also configure a VCH to use different user accounts for deployment and operation.

**NOTE**: Certain options in this section are exposed in the vic-machine create help if you run vic-machine create --extended-help, or vic-machine create -x.

#### Restrict Access to the Docker API with Auto-Generated Certificates

As a convenience, vic-machine create provides the option of generating a client certificate, server certificate, and certificate authority (CA) as appropriate when you deploy a VCH. The generated certificates are functional, but they do not allow for fine control over aspects such as expiration, intermediate certificate authorities, and so on.

vSphere Integrated Containers Engine authenticates Docker API clients by using client certificates. This configuration is commonly referred to as tlsverify in documentation about containers and Docker. Aclient certificate is accepted if it is signed by a CAthat you provide by specifying one or more instances of the --tls-ca option. In the case of the certificates that vic-machine create generates, vic-machine create a CA and uses it to create and sign a single client certificate.

When using the Docker client, the client validates the server either by using CAs that are present in the root certificate bundle of the client system, or that are provided explicitly by using the --tlscacert option when running Docker commands. As a part of this validation, the server certificate must explicitly state at least one of the following, and must match the name or address that the client uses to access the server:

- The FQDN used to communicate with the server
- The IP address used to communicate with the server
- Awildcard domain that matches all of the FQDNs in a specific subdomain. For an example of a domain wildcard, see https://en.wikipedia.org/wiki/Wildcard\_certificate#Example.

#### --tls-cname

Short name: None

The FQDN or IP address to embed in an auto-generated server certificate. Specify an FQDN, IP address, or a domain wildcard. If you provide a custom server certificate by using the --cert option, you can use --tls-cname as a sanity check to ensure that the certificate is valid for the deployment.

If you do not specify --tls-cname but you do set a static address for the VCH on the client network interface, vic-machine create uses that address for the Common Name, with the same results as if you had specified --tls-cname=x.x.x.x. For information about setting a static IP address on the client network, see Options for Specifying a Static IP Address for the VCH Endpoint VM.

When you specify the --tls-cname option, vic-machine create performs the following actions during the deployment of the VCH:

- Checks for an existing certificate in either a folder that has the same name as the VCH that you are deploying, or in a location that you specify in the --cert-path option. If a valid certificate exists that includes the same Common Name attribute as the one that you specify in --tls-cname, vic-machine create reuses it. Reusing certificates allows you to delete and recreate VCHs for which you have already distributed the certificates to container developers.
- If certificates are present in the certificate folder that include a different Common Name attribute to the one that you specify in --tls-cname, vic-machine create fails.
- If a certificate folder does not exist, vic-machine create creates a folder with the same name as the VCH, or creates a folder in the location that you specify in the --cert-path option.
- If valid certificates do not already exist, vic-machine create creates the following trusted CA, server, and client certificate/key pairs in the certificate folder:
  - o ca.pem
  - o ca-key.pem
  - o cert.pem
  - o key.pem
  - o server-cert.pem
  - o server-key.pem
- Creates a browser-friendly PFX client certificate, cert.pfx, to use to authenticate connections to the VCH Admin portal for the VCH.

NOTE: The folder and file permissions for the generated certificate and key are readable only by the user who created them.

Running vic-machine create with the --tls-cname option also creates an environment file named vch\_name.env , that contains Docker environment variables that container developers can use to configure their Docker client environment:

• Activates TLS client verification.

```
DOCKER_TLS_VERIFY=1
```

• The path to the client certificates.

```
DOCKER_CERT_PATH=path_to_certs
```

• The address of the VCH.

```
DOCKER_HOST=vch_address:2376
```

You must provide copies of the cert.pem and key.pem client certificate files and the environment file to container developers so that they can connect Docker clients to the VCH. If you deploy the VCH with the --tls-cname option, container developers must configure the client appropriately with one of the following options:

- By using the following tlsverify, tlscert, and tlskey Docker options, adding tlscacert if a custom CAwas used to sign the server certificate.
- By setting DOCKER\_CERT\_PATH=/path/to/client/cert.pem and DOCKER\_TLS\_VERIFY=1.

```
--tls-cname vch-name.example.org
```

```
--tls-cname *.example.org
```

#### --cert-path

Short name: none

By default --cert-path is a folder in the current directory, that takes its name from the VCH name that you specify in the --name option. vic-machine create checks in --cert-path for existing certificates with the standard names and uses those certificates if they are present:

- server-cert.pem
- server-key.pem
- ca.pem

If vic-machine create does not find existing certificates with the standard names in --cert-path , or if you do not specify certificates directly by using the --cert , --key , and --tls-ca options, vic-machine create generates certificates. Generated certificates are saved in the --cert-path folder with the standard names listed. vic-machine create additionally generates other certificates:

- cert.pem and key.pem for client certificates, if required.
- ca-key.pem, the private key for the certificate authority.

```
--cert-path 'path_to_certificate_folder'
```

## --certificate-key-size

Short name: --ksz

The size of the key for vic-machine create to use when it creates auto-generated trusted certificates. You can optionally use --certificate-key-size if you specify --tls-cname. If not specified, vic-machine create creates keys with default size of 2048 bits. It is not recommended to use key sizes of less than 2048 bits.

```
--certificate-key-size 3072
```

#### --organization

Short name: None

Alist of identifiers to record in certificates generated by vic-machine. You can optionally use --organization if you specify --tls-cname. If not specified, vic-machine create uses the name of the VCH as the organization value.

NOTE: The client-ip-address is used for CommonName but not for Organisation .

```
--organization organization_name
```

## Restrict Access to the Docker API with Custom Certificates

To exercise fine control over the certificates that VCHs use, obtain or generate custom certificates yourself before you deploy a VCH. Use the --key, --cert, and --tls-ca options to pass the custom certificates to vic-machine create.

#### --cert

Short name: none

The path to a custom X.509 server certificate. This certificate identifies the VCH endpoint VM both to Docker clients and to browsers that connect to the VCH Admin portal.

- This certificate should have the following certificate usages:
  - o KeyEncipherment
  - O DigitalSignature
  - KeyAgreement
  - o ServerAuth
- This option is mandatory if you use custom TLS certificates, rather than auto-generated certificates.
- Use this option in combination with the --key option, that provides the path to the private key file for the custom certificate.
- Include the names of the certificate and key files in the paths.
- If you use trusted custom certificates, container developers run Docker commands with the --tlsverify, --tlscacert, --tlscert, and --tlskey options.

```
--cert path_to_certificate_file/certificate_file_name.pem
--key path_to_key_file/key_file_name.pem
```

Wrap the folder names in the paths in single quotes (Linux or Mac OS) or double quotes (Windows) if they include spaces.

```
--cert 'path to certificate file'/certificate_file_name.pem
--key 'path to key file'/key_file_name.pem
```

#### --key

Short name: none

The path to the private key file to use with a custom server certificate. This option is mandatory if you specify the --cert option, that provides the path to a custom X.509 certificate file. Include the names of the certificate and key files in the paths.

**IMPORTANT**: The key must not be encrypted.

```
--cert path_to_certificate_file/certificate_file_name.pem
--key path_to_key_file/key_file_name.pem
```

Wrap the folder names in the paths in single quotes (Linux or Mac OS) or double quotes (Windows) if they include spaces.

```
--cert 'path to certificate file'/certificate_file_name.pem
--key 'path to key file'/key_file_name.pem
```

#### --tls-ca

Short name: --ca

You can specify --tls-ca multiple times, to point vic-machine create to a file that contains the public portion of a CA. vic-machine create uses these CAs to validate client certificates that are offered as credentials for Docker API access. This does not need to be the same CAthat you use to sign the server certificate.

```
--tls-ca path_to_ca_file
```

**NOTE**: The --tls-ca option appears in the extended help that you see by running vic-machine-os create --extended-help or vic-machine-os create -x.

## Do Not Restrict Access to the Docker API

To deploy a VCH that does not restrict access to the Docker API, use the --no-tlsverify option. To completely disable TLS authentication, use the --no-tls option.

#### --no-tlsverify

Short name: --kv

The --no-tlsverify option prevents the use of CAs for client authentication. You still require a server certificate if you use --no-tlsverify. You can still supply a custom server certificate by using the --cert and --key options. If you do not use --cert and --key to supply a custom server certificate, vic-machine create generates a self-signed server certificate. If you specify --no-tlsverify there is no access control, however connections remain encrypted.

When you specify the --no-tisverify option, vic-machine create performs the following actions during the deployment of the VCH.

- Generates a self-signed server certificate if you do not specify --cert and --key .
- Creates a folder with the same name as the VCH in the location in which you run vic-machine create.
- Creates an environment file named vch\_name.env in that folder, that contains the DOCKER\_HOST=vch\_address environment variable, that you can provide to container developers to use to set up their Docker client environment.

If you deploy a VCH with the --no-tlsverify option, container developers run Docker commands with the --tls option, and the DOCKER\_TLS\_VERIFY environment variable must not be set. Note that setting DOCKER\_TLS\_VERIFY to 0 or false has no effect.

The --no-tlsverify option takes no arguments.

```
--no-tlsverify
```

#### --no-tls

Short name: -k

Disables TLS authentication of connections between the Docker client and the VCH. VCHs use neither client nor server certificates.

Set the no-tls option if you do not require TLS authentication between the VCH and the Docker client. Any Docker client can connect to the VCH if you disable TLS authentication and connections are not encrypted.

If you use the no-tls option, container developers connect Docker clients to the VCH via port 2375, instead of via port 2376.

```
--no-tls
```

## Specify Different User Accounts for VCH Deployment and Operation

Because deploying a VCH requires greater levels of permissions than running a VCH, you can configure a VCH so that it uses different user accounts for deployment and for operation. In this way, you can limit the day-to-day operation of a VCH to an account that does not have full administrator permissions on the target vCenter Server.

#### --ops-user

Short name: None

AvSphere user account with which the VCH runs after deployment. If not specified, the VCH runs with the vSphere Administrator credentials with which you deploy the VCH, that you specify in either --target or --user.

```
--ops-user user_name
```

Wrap the user name in single quotes (') on Mac OS and Linux and in double quotes (") on Windows if it includes special characters.

```
--ops-user 'user_n@me'
```

The user account that you specify in --ops-user must exist before you deploy the VCH. For information about the permissions that the --ops-user account requires, see Use Different User Accounts for VCH Deployment and Operation.

## --ops-password

Short name: None

The password or token for the operations user that you specify in --ops-user. If not specified, vic-machine create prompts you to enter the password for the --ops-user account.

```
--ops-password password
```

Wrap the password in single quotes (') on Mac OS and Linux and in double quotes (") on Windows if it includes special characters.

```
--ops-password 'p@ssword'
```

# **Private Registry Options**

If you use vSphere Integrated Containers Registry, or if container developers need to access Docker images that are stored in other private registry servers, you must configure VCHs to allow them to connect to these private registry servers when you deploy the VCHs. VCHs can connect to both secure and insecure private registry servers.

## --registry-ca

Short name: --rc

The path to a CAcertificate that can validate the server certificate of a private registry. You can specify --registry-ca multiple times to specify multiple CAcertificates for different registries. This allows a VCH to connect to multiple registries.

The use of registry certificates is independent of the Docker client security options that you specify. For example, it is possible to use the --no-tls option to disable TLS authentication between Docker clients and the VCH, and to use the --registry-ca option to enable TLS authentication between the VCH and a private registry.

You must use this option to allow a VCH to connect to vSphere Integrated Containers Registry. For information about how to obtain the CAcertificate from vSphere Integrated Containers Registry, see Deploy a VCH for Use with vSphere Integrated Containers Registry.

```
--registry-ca path_to_ca_cert_1
--registry-ca path_to_ca_cert_2
```

**NOTE**: The --registry-ca option appears in the extended help that you see by running vic-machine-os create --extended-help or vic-machine-os create -x .

## --insecure-registry

Short name: --dir

If you set the --insecure-registry option, the VCH does not verify the certificate of that registry when it pulls images. Insecure private registries are not recommended in production environments.

If you authorize a VCH to connect to an insecure private registry server, the VCH attempts to access the registry server via HTTP if access via HTTPS fails. VCHs always use HTTPS when connecting to registry servers for which you have not authorized insecure access.

You can specify --insecure-registry multiple times if multiple insecure registries are permitted. If the registry server listens on a specific port, add the port number to the URL

```
--insecure-registry registry_URL_1
--insecure-registry registry_URL_2:port_number
```

# **Datastore Options**

The vic-machine utility allows you to specify the datastore in which to store container image files, container VM files, and the files for the VCH. You can also specify datastores in which to create container volumes.

- vSphere Integrated Containers Engine fully supports VMware vSAN datastores.
- vSphere Integrated Containers Engine supports all alphanumeric characters, hyphens, and underscores in datastore paths and datastore names, but no other special characters.
- If you specify different datastores in the different datastore options, and if no single host in a cluster can access all of those datastores, vic-machine create fails with an error.

```
No single host can access all of the requested datastores.
Installation cannot continue.
```

• If you specify different datastores in the different datastore options, and if only one host in a cluster can access all of them, vic-machine create succeeds with a warning.

Only one host can access all of the image/container/volume datastores. This may be a point of contention/performance degradation and HA/DRS may not work as intended.

• VCHs do not support datastore name changes. If a datastore changes name after you have deployed a VCH that uses that datastore, that VCH will no longer function.

## --image-store

Short name: -i

The datastore in which to store container image files, container VM files, and the files for the VCH. The --image-store option is mandatory if there is more than one datastore in your vSphere environment. If there is only one datastore in your vSphere environment, the --image-store option is not required.

If you do not specify the --image-store option and multiple possible datastores exist, or if you specify an invalid datastore name, vic-machine create fails and suggests valid datastores in the failure message.

If you are deploying the VCH to a vCenter Server cluster, the datastore that you designate in the <code>image-store</code> option must be shared by at least two ESXi hosts in the cluster. Using non-shared datastores is possible, but limits the use of vSphere features such as vSphere vMotion® and vMware vSphere Distributed Resource Scheduler<sup>TM</sup> (DRS).

To specify a whole datastore as the image store, specify the datastore name in the --image-store option:

```
--image-store datastore_name
```

If you designate a whole datastore as the image store, vic-machine creates the following set of folders in the target datastore:

- datastore\_name/VIC/vch\_uuid/images, in which to store all of the container images that you pull into the VCH.
- datastore\_name/vch\_name , that contains the VM files for the VCH.
- datastore\_name/vch\_name/kvstores , a key-value store folder for the VCH.

You can specify a datastore folder to use as the image store by specifying a path in the --image-store option</code>:

```
--image-store datastore_name/path
```

If the folder that you specify in /path does not already exist, vic-machine create creates it. Wrap the datastore name and path in single quotes (') on Mac OS and Linux and in double quotes (") on Windows if they include spaces:

```
--image-store 'datastore name'/'datastore path'
```

If you designate a datastore folder as the image store, vic-machine creates the following set of folders in the target datastore:

- datastore\_name/path/vIC/vcu\_uuid/images, in which to store all of the container images that you pull into the VCH.
- datastore\_name/vch\_name, that contains the VM files for the VCH. This is the same as if you specified a datastore as the image store
- datastore\_name/vch\_name/kvstores , a key-value store folder for the VCH. This is the same as if you specified a datastore as the image store.

By specifying the path to a datastore folder in the --image-store option, you can designate the same datastore folder as the image store for multiple VCHs. In this way, vic-machine create creates only one vic folder in the datastore, at the path that you specify. The vic folder contains one vch\_uuid/images folder for each VCH that you deploy. By creating one vch\_uuid/images folder for each VCH, vSphere Integrated Containers Engine limits the potential for conflicts of image use between VCHs, even if you share the same image store folder between multiple hosts.

When container developers create containers, vSphere Integrated Containers Engine stores the files for container VMs at the top level of the image store, in folders that have the same name as the containers.

#### --volume-store

Short name: --vs

The datastore in which to create volumes when container developers use the docker volume create or docker create -v commands. When you specify the volume-store option, you provide the name of the target datastore and a label for the volume store. You can optionally provide a path to a specific folder in the datastore in which to create the volume store. If the folders that you specify in the path do not already exist on the datastore, vic-machine create creates the appropriate folder structure.

The vic-machine create creates command creates the volumes folder independently from the folders for VCH files so that you can share volumes between VCHs. If you delete a VCH, any volumes that the VCH managed will remain available in the volume store unless you specify the --force option when you delete the VCH. You can then assign an existing volume store that already contains data to a newly created VCH.

**IMPORTANT**: If multiple VCHs will use the same datastore for their volume stores, specify a different datastore folder for each VCH. Do not designate the same datastore folder as the volume store for multiple VCHs.

If you are deploying the VCH to a vCenter Server cluster, the datastore that you designate in the volume-store option should be shared by at least two ESXi hosts in the cluster. Using non-shared datastores is possible and vic-machine create succeeds, but it issues a warning that this configuration limits the use of vSphere features such as vSphere vMotion and DRS.

The label that you specify is the volume store name that Docker uses. For example, the volume store label appears in the information for a VCH when container developers run docker info. Container developers specify the volume store label in the docker volume create --opt VolumeStore=volume\_store\_label option when they create a volume.

If you specify an invalid datastore name, vic-machine create fails and suggests valid datastores.

**IMPORTANT** If you do not specify the volume-store option, no volume store is created and container developers cannot use the docker volume create Or docker create -v commands.

If you only require one volume store, you can set the volume store label to default. If you set the volume store label to default, container developers do not need to specify the --opt VolumeStore=volume\_store\_label option when they run docker volume create.

**NOTE**: If container developers intend to use docker create -v to create containers that are attached to anonymous or named volumes, you must create a volume store with a label of default.

```
--volume-store datastore_name:default
```

If you specify the target datastore and the volume store label, vic-machine create creates a folder named vic/volumes at the top level of the target datastore. Any volumes that container developers create will appear in the vic/volumes folder.

```
--volume-store datastore_name:volume_store_label
```

• If you specify the target datastore, a datastore path, and the volume store label, vic-machine create creates a folder named volumes in the location that you specify in the datastore path. Any volumes that container developers create will appear in the path/volumes folder.

```
--volume-store datastore_name/datastore_path:volume_store_label
```

Wrap the datastore name and path in single quotes (') on Mac OS and Linux and in double quotes (") on Windows if they
include spaces. The volume store label cannot include spaces.

```
--volume-store 'datastore name'/'datastore path':volume_store_label
```

You can specify the volume-store option multiple times, to create multiple volume stores for the VCH.

```
--volume-store datastore_name/path:volume_store_label_1
--volume-store datastore_name/path:volume_store_label_2
[...]
--volume-store datastore_name/path:volume_store_label_n
```

# **Networking Options**

The vic-machine create utility allows you to specify different networks for the different types of traffic between containers, the VCH, the external internet, and your vSphere environment. For information about the different networks that VCHs use, see Networks Used by vSphere Integrated Containers Engine.

**IMPORTANT**: A VCH supports a maximum of 3 distinct network interfaces. Because the bridge network requires its own port group, at least two of the public, client, and management networks must share a network interface and therefore a port group. Container networks do not go through the VCH, so they are not subject to this limitation. This limitation will be removed in a future release.

By default, vic-machine create obtains IP addresses for VCH endpoint VMs by using DHCP. For information about how to specify a static IP address for the VCH endpoint VM on the client, public, and management networks, see Specify a Static IP Address for the VCH Endpoint VM in Advanced Options.

If your network access is controlled by a proxy server, see Options to Configure VCHs to Use Proxy Servers in Advanced Options.

When you specify different network interfaces for the different types of traffic, vic-machine create checks that the firewalls on the ESXi hosts allow connections to port 2377 from those networks. If access to port 2377 on one or more ESXi hosts is subject to IP address restrictions, and if those restrictions block access to the network interfaces that you specify, vic-machine create fails with a firewall configuration error:

```
Firewall configuration incorrect due to allowed IP restrictions on hosts: "/ha-datacenter/host/localhost.localdomain/localhost.localdomain"
Firewall must permit dst 2377/tcp outbound to the VCH management interface
```

For information about how to open port 2377, see Open the Required Ports on ESXi Hosts.

## --bridge-network

Short name: -b

Aport group that container VMs use to communicate with each other.

The bridge-network option is **mandatory** if you are deploying a VCH to vCenter Server.

In a vCenter Server environment, before you run vic-machine create, you must create a distributed virtual switch and a port group. You must add the target ESXi host or hosts to the distributed virtual switch, and assign a VLAN ID to the port group, to ensure that the bridge network is isolated. For information about how to create a distributed virtual switch and port group, see the section on vCenter Server Network Requirements in Environment Prerequisites for VCH Deployment.

You pass the name of the port group to the bridge-network option. Each VCH requires its own port group.

#### **IMPORTANT**

- Do not assign the same bridge-network port group to multiple VCHs. Sharing a port group between VCHs might result in multiple container VMs being assigned the same IP address.
- Do not use the bridge-network port group as the target for any of the other vic-machine create networking options.

If you specify an invalid port group name, vic-machine create fails and suggests valid port groups.

The bridge-network option is **optional** when you are deploying a VCH to an ESXi host with no vCenter Server. In this case, if you do not specify bridge-network, vic-machine creates a virtual switch and a port group that each have the same name as the VCH. You can optionally specify this option to assign an existing port group for use as the bridge network for container VMs. You can also optionally specify this option to create a new virtual switch and port group that have a different name to the VCH.

```
--bridge-network port_group_name
```

Wrap the port group name in single quotes (') on Mac OS and Linux and in double quotes (") on Windows if it includes spaces.

```
--bridge-network 'port group name'
```

If you intend to use the --ops-user option to use different user accounts for deployment and operation of the VCH, you must place the bridge network port group in a network folder that has the Read-Only role with propagation enabled. For more information about the requirements when using --ops-user, see Use Different User Accounts for VCH Deployment and Operation.

For information about how to specify a range of IP addresses for additional bridge networks, see <a href="bridge-network-range">bridge-network-range</a> in Advanced Networking Options.

#### --client-network

Short name: --cln

Aport group on which the VCH will make the Docker API available to Docker clients. Docker clients use this network to issue Docker API requests to the VCH.

If not specified, the VCH uses the public network for client traffic. If you specify an invalid port group name, vic-machine create fails and suggests valid port groups.

```
--client-network port_group_name
```

Wrap the port group name in single quotes (') on Mac OS and Linux and in double quotes (") on Windows if it includes spaces.

```
--client-network 'port group name'
```

## --public-network

Short name: --pn

Aport group for containers to use to connect to the Internet. VCHs use the public network to pull container images, for example from https://hub.docker.com/. Containers that use use port mapping expose network services on the public interface.

**NOTE**: vSphere Integrated Containers Engine adds a new capability to Docker that allows you to directly map containers to a network by using the --container-network option. This is the recommended way to deploy container services.

If not specified, containers use the VM Network for public network traffic. If you specify an invalid port group name, vic-machine create fails and suggests valid port groups.

```
--public-network port_group
```

Wrap the network name in single quotes (') on Mac OS and Linux and in double quotes (") on Windows if it includes spaces.

```
--public-network 'port group name'
```

## --management-network

Short name: --mn

Aport group that the VCH uses to communicate with vCenter Server and ESXi hosts. Container VMs use this network to communicate with the VCH.

**IMPORTANT**: Because the management network provides access to your vSphere environment, and because container VMs use this network to communicate with the VCH, always use a secure network for the management network.

When you create a VCH, vic-machine create checks that the firewall on ESXi hosts allows connections to port 2377 from the management network of the VCH. If access to port 2377 on ESXi hosts is subject to IP address restrictions, and if those restrictions block access to the management network interface, vic-machine create fails with a firewall configuration error:

```
Firewall configuration incorrect due to allowed IP restrictions on hosts:

"/ha-datacenter/host/localhost.localdomain/localhost.localdomain"

Firewall must permit dst 2377/tcp outbound to the VCH management interface
```

For information about how to open port 2377, see Open the Required Ports on ESXi Hosts.

**NOTE**: If the management network uses DHCP, vic-machine checks the firewall status of the management network before the VCH receives an IP address. It is therefore not possible to fully assess whether the firewall permits the IP address of the VCH. In this case, vic-machine create issues a warning.

```
Unable to fully verify firewall configuration due to DHCP use on management network VCH management interface IP assigned by DHCP must be permitted by allowed IP settings Firewall allowed IP configuration may prevent required connection on hosts: "/ha-datacenter/host/localhost.localdomain/localhost.localdomain" Firewall must permit dst 2377/tcp outbound to the VCH management interface
```

If not specified, the VCH uses the public network for management traffic. If you specify an invalid port group name, vic-machine create fails and suggests valid port groups.

```
--management-network port_group_name
```

Wrap the network name in single quotes (') on Mac OS and Linux and in double quotes (") on Windows if it includes spaces.

```
--management-network 'port group name'
```

#### --container-network

Short name: --cn

Aport group for container VMs to use for external communication when container developers run docker run or docker create with the --net option.

You can optionally specify one or more container networks. Container networks allow containers to directly attach to a network without having to route through the VCH via network address translation (NAT). Container networks that you add by using the --container-network option appear when you run the docker network 1s command. These networks are available for use by containers. Containers that use these networks are directly attached to the container network, and do not go through the VCH or share the public IP of the VCH.

**IMPORTANT**: For security reasons, whenever possible, use separate port groups for the container network and the management network.

To specify a container network, you provide the name of a port group for the container VMs to use, and an optional descriptive name for the container network for use by Docker. If you do not specify a descriptive name, Docker uses the vSphere network name.

**IMPORTANT**: The descriptive name is optional unless the port group name contains spaces. If the port group name contains spaces, you must specify a descriptive name. The descriptive name cannot contain spaces.

If you specify an invalid port group name, vic-machine create fails and suggests valid port groups.

- You can specify a vSphere network as the container network.
- The port group must exist before you run vic-machine create.
- You cannot use the same port group as you use for the bridge network.
- You can create the port group on the same distributed virtual switch as the port group that you use for the bridge network.
- If the port group that you specify in the container-network option does not support DHCP, see Options for Configuring a Non-DHCP Network for Container Traffic in Advanced Options.
- The descriptive name appears under Networks When you run docker info Or docker network 1s on the deployed VCH.
- Container developers use the descriptive name in the --net option when they run docker run or docker create .

You can specify --container-network multiple times to add multiple vSphere networks to Docker.

If you do not specify --container-network, or if you deploy containers that do not use a container network, the containers' network services are still be available via port mapping through the VCH, by using NAT through the public interface of the VCH.

```
--container-network port_group_name:container_port _group_name
```

Wrap the port group name in single quotes (') on Mac OS and Linux and in double quotes (") on Windows if it includes spaces. The descriptive name cannot include spaces.

```
--container-network 'port group name':container port group name
```

If you intend to use the --ops-user option to use different user accounts for deployment and operation of the VCH, you must place any container network port groups in a network folder that has the Read-Only role with propagation enabled. For more information about the requirements when using --ops-user, see Use Different User Accounts for VCH Deployment and Operation.

# **General Deployment Options**

The vic-machine utility provides options to customize the VCH.

#### --name

Short name: -n

Aname for the VCH. If not specified, vic-machine sets the name of the VCH to virtual-container-host. If a VCH of the same name exists on the ESXi host or in the vCenter Server inventory, or if a folder of the same name exists in the target datastore, vic-machine create creates a folder named vch\_name\_1. If the name that you provide contains unsupported characters, vic-machine create fails with an error.

```
--name vch_name
```

Wrap the name in single quotes (') on Mac OS and Linux and in double quotes (") on Windows if it includes spaces.

```
--name 'vch name'
```

#### --memory

Short name: --mem

Limit the amount of memory that is available for use by the VCH vApp in vCenter Server, or for the VCH resource pool on an ESXi host. This limit also applies to the container VMs that run in the VCH vApp or resource pool. Specify the memory limit value in MB. If not specified, vic-machine create sets the limit to 0 (unlimited).

```
--memory 1024
```

## --cpu

Short name: None

Limit the amount of CPU capacity that is available for use by the VCH vApp in vCenter Server, or for the VCH resource pool on an ESXi host. This limit also applies to the container VMs that run in the VCH vApp or resource pool. Specify the CPU limit value in MHz. If not specified, vic-machine create sets the limit to 0 (unlimited).

```
--cpu 1024
```

#### --force

Short name: -f

Forces vic-machine create to ignore warnings and non-fatal errors and continue with the deployment of a VCH. Errors such as an incorrect compute resource still cause the deployment to fail.

If your vSphere environment uses untrusted, self-signed certificates, you can use the --force option to deploy a VCH without providing the thumbprint of the vCenter Server or ESXi host in the thumbprint option.

**IMPORTANT** Running vic-machine create with the --force option rather than providing the certificate thumbprint is not recommended, because it permits man-in-the-middle attacks to go undetected.

--force

#### --timeout

Short name: none

The timeout period for uploading the vSphere Integrated Containers Engine files and ISOs to the ESXi host, and for powering on the VCH. Specify a value in the format x<sub>mYs</sub> if the default timeout of 3m0s is insufficient.

--timeout 5m0s

# **Advanced Options**

The options in this section are exposed in the vic-machine create help if you run vic-machine create --extended-help, or vic-machine create -x.

# Options for Specifying a Static IP Address for the VCH Endpoint VM

You can specify a static IP address for the VCH endpoint VM on each of the client, public, and management networks. DHCP is used for the endpoint VM for any network on which you do not specify a static IP address.

To specify a static IP address for the endpoint VM on the client, public, or management network, you provide an IP address in the client/public/management-network-ip option. If you set a static IP address, you can optionally provide gateway addresses and specify one or more DNS server addresses.

## --dns-server

Short name: None

ADNS server for the VCH endpoint VM to use on the client, public, or management networks. You can specify dns-server multiple times, to configure multiple DNS servers.

- If you specify dns-server, vic-machine create always uses the --dns-server setting for all three of the client, public, and management networks.
- If you do not specify dns-server and you specify a static IP address for the endpoint VM on all three of the client, public, and management networks, vic-machine create uses the Google public DNS service.
- If you do not specify dns-server and you use a mixture of static IP addresses and DHCP for the client, public, and management networks, vic-machine create uses the DNS servers that DHCP provides.
- If you do not specify dns-server and you use DHCP for all of the client, public, and management networks, vic-machine create uses the DNS servers that DHCP provides.
- --dns-server=172.16.10.10
- --dns-server=172.16.10.11

## --client-network-ip , --public-network-ip , --management-network-ip

Short name: None

Astatic IP address for the VCH endpoint VM on the public, client, or management network.

You specify a static IP address for the endpoint VM on the public, client, or management networks by using the -public/client/management-network-ip options. If you set a static IP address for the endpoint VM on the public network, you must specify a corresponding gateway address by using the --public-network-gateway option. If the management and client networks are L2 adjacent to their gateways, you do not need to specify the gateway for those networks.

- You can only specify one static IP address on a given port group. If more than one of the client, public, or management networks share a port group, you can only specify a static IP address on one of those networks. All of the networks that share that port group use the IP address that you specify.
- If either of the client or management networks shares a port group with the public network, you can only specify a static IP address on the public network.
- If either or both of the client or management networks do not use the same port group as the public network, you can specify a static IP address for the endpoint VM on those networks by using --client-network-ip or --management-network-ip, or both. In this case, you must specify a corresponding gateway address by using client/management-network-gateway.
- If the client and management networks both use the same port group, and the public network does not use that port group, you can set a static IP address for the endpoint VM on either or both of the client and management networks.
- If you assign a static IP address to the VCH endpoint VM on the client network by setting the --client-network-ip option, and you do not specify one of the TLS options, vic-machine create uses this address as the Common Name with which to autogenerate trusted CAcertificates. If you do not specify --tls-cname, --no-tls or --no-tlsverify, two-way TLS authentication with trusted certificates is implemented by default when you deploy the VCH with a static IP address on the client network. If you assign a static IP address to the endpoint VM on the client network, vic-machine create creates the same certificate and environment variable files as described in the --tls-cname option.

**IMPORTANT**: If the client network shares a port group with the public network you cannot set a static IP address for the endpoint VM on the client network. To assign a static IP address to the endpoint VM you must set a static IP address on the public network by using the --public-network-ip option. In this case, vic-machine create uses the public network IP address as the Common Name with which to auto-generate trusted CA certificates, in the same way as it would for the client network.

• If you do not specify an IP address for the endpoint VM on a given network, vic-machine create uses DHCP to obtain an IP address for the endpoint VM on that network.

You specify addresses as IPv4 addresses with a network mask.

```
--public-network-ip 192.168.X.N/24
--management-network-ip 192.168.Y.N/24
--client-network-ip 192.168.Z.N/24
```

You can also specify addresses as resolvable FQDNs.

```
--public-network-ip=vch27-team-a.internal.domain.com
--management-network-ip=vch27-team-b.internal.domain.com
--client-network-ip=vch27-team-c.internal.domain.com
```

# --client-network-gateway, --public-network-gateway, --management-network-gateway

Short name: None

The gateway to use if you use --public/client/management-network-ip to specify a static IP address for the VCH endpoint VM on the public, client, or management networks. If you specify a static IP address on the public network, you must specify a gateway by using the --public-network-gateway option. If the management and client networks are L2 adjacent to their gateways, you do not need to specify the gateway for those networks.

You specify gateway addresses as IP addresses without a network mask.

```
--public-network-gateway 192.168.X.1
```

The default route for the VCH endpoint VM is always on the public network. As a consequence, if you specify a static IP address on either of the management or client networks and those networks are not L2 adjacent to their gateways, you must specify the routing destination for those networks in the --management-network-gateway and --client-network-gateway options. You specify the routing destination or destinations in a comma-separated list, with the address of the gateway separated from the routing destinations by a colon (:).

```
--management-network-gateway routing_destination_1,
routing_destination_2:gateway_address
```

```
--client-network-gateway routing_destination_1,
routing_destination_2:gateway_address
```

In the following example, --management-network-gateway informs the VCH that it can reach all of the vSphere management endoints that are in the ranges 192.168.3.0-255 and 192.168.128.0-192.168.131.255 by sending packets to the gateway at 192.168.2.1. Ensure that the address ranges that you specify include all of the systems that will connect to this VCH instance.

```
--management-network-gateway 192.168.3.0,192.168.128.0:192.168.2.1
```

# Options for Configuring a Non-DHCP Network for Container Traffic

If the network that you specify in the container-network option does not support DHCP, you must specify the container-network-gateway option. You can optionally specify one or more DNS servers and a range of IP addresses for container VMs on the container network.

For information about the container network, see the section on the container-network option.

## --container-network-gateway

Short name: --cng

The gateway for the subnet of the container network. This option is required if the network that you specify in the --container-network option does not support DHCP. Specify the gateway in the format container\_network:subnet . If you specify this option, it is recommended that you also specify the --container-network-dns option.

When you specify the container network gateway, you must use the port group that you specify in the --container-network option. If you specify --container-network option but you do not specify --container-network, or if you specify a different port group to the one that you specify in --container-network, vic-machine create fails with an error.

```
--container-network-gateway port_group_name:gateway_ip_address/subnet_mask
```

Wrap the port group name in single quotes (Linux or Mac OS) or double quotes (Windows) if it includes spaces.

```
--container-network-gateway 'port group name':gateway_ip_address/subnet_mask
```

## --container-network-dns

Short name: --cnd

The address of the DNS server for the container network. This option is recommended if the network that you specify in the \_\_container-network option does not support DHCP.

When you specify the container network DNS server, you must use the port group that you specify in the --container-network option. You can specify --container-network-dns multiple times, to configure multiple DNS servers. If you specify --container-network but you do not specify --container-network , or if you specify a different port group to the one that you specify in --container-network , vic-machine create fails with an error.

```
--container-network-dns port_group_name:8.8.8.8
```

Wrap the port group name in single quotes (Linux or Mac OS) or double quotes (Windows) if it includes spaces.

```
--container-network-dns 'port group name':8.8.8.8
```

## --container-network-ip-range

Short name: --cnr

The range of IP addresses that container VMs can use if the network that you specify in the <code>container-network</code> option does not support DHCP. If you specify --container-network-ip-range, VCHs manage the addresses for containers within that range. The range that you specify must not be used by other computers or VMs on the network. You must also specify --container-network-ip-range if container developers need to deploy containers with static IP addresses. If you specify <code>container-network-gateway</code> but do not specify --container-network-ip-range, the IP range for container VMs is the entire subnet that you specify in --container-network-gateway.

When you specify the container network IP range, you must use the port group that you specify in the --container-network option. If you specify --container-network on if you specify a different port group to the one that you specify in --container-network, vic-machine create fails with an error.

```
--container-network-ip-range port_group_name:192.168.100.2-192.168.100.254
```

You can also specify the IP range as a CIDR.

```
--container-network-ip-range port_group_name:192.168.100.0/24
```

Wrap the port group name in single quotes (Linux or Mac OS) or double quotes (Windows) if it includes spaces.

```
--container-network-ip-range 'port group name':192.168.100.0/24
```

# **Options to Configure VCHs to Use Proxy Servers**

If access to the Internet or to your private image registries requires the use of a proxy server, you must configure a VCH to connect to the proxy server when you deploy it. The proxy is used only when pulling images, and not for any other purpose.

**IMPORTANT**: Configuring a VCH to use a proxy server does not configure proxy support on the containers that this VCH runs. Container developers must configure proxy servers on containers when they create them.

#### --https-proxy

Short name: --sproxy

The address of the HTTPS proxy server through which the VCH accesses image registries when using HTTPS. Specify the address of the proxy server as either an FQDN or an IP address.

```
--https-proxy https://proxy_server_address:port
```

#### --http-proxy

Short name: --hproxy

The address of the HTTP proxy server through which the VCH accesses image registries when using HTTP. Specify the address of the proxy server as either an FQDN or an IP address.

--http-proxy http://proxy\_server\_address:port

# **Advanced Resource Management Options**

You can set limits on the memory and CPU shares and reservations on the VCH. For information about memory and CPU shares and reservations, see Allocate Memory Resources, and Allocate CPU Resources in the vSphere documentation.

## --memory-reservation

Short name: --memr

Reserve a quantity of memory for use by the VCH vApp in vCenter Server, or for the VCH resource pool on an ESXi host. This limit also applies to the container VMs that run in the VCH vApp or resource pool. Specify the memory reservation value in MB. If not specified, vic-machine create sets the reservation to 1.

--memory-reservation 1024

## --memory-shares

Short name: --mems

Set memory shares on the VCH vApp in vCenter Server, or on the VCH resource pool on an ESXi host. This limit also applies to the container VMs that run in the VCH vApp or resource pool. Specify the share value as a level or a number, for example high, normal, low, or 163840. If not specified, vic-machine create sets the share to normal.

--memory-shares low

## --cpu-reservation

Short name: --cpur

Reserve a quantity of CPU capacity for use by the VCH vApp in vCenter Server, or for the VCH resource pool on an ESXi host. This limit also applies to the container VMs that run in the VCH vApp or resource pool. Specify the CPU reservation value in MHz. If not specified, vic-machine create sets the reservation to 1.

--cpu-reservation 1024

## --cpu-shares

Short name: --cpus

Set CPU shares on the VCH vApp in vCenter Server, or on the VCH resource pool on an ESXi host. This limit also applies to the container VMs that run in the VCH vApp or resource pool. Specify the share value as a level or a number, for example high, normal, low, or 163840. If not specified, vic-machine create sets the share to normal.

--cpu-shares low

## --endpoint-cpu

Short name: none

The number of virtual CPUs for the VCH endpoint VM. The default is 1. Set this option to increase the number of CPUs in the VCH endpoint VM.

**NOTE** Always use the --cpu option instead of the --endpoint-cpu option to increase the overall CPU capacity of the VCH vApp, rather than increasing the number of CPUs on the VCH endpoint VM. The --endpoint-cpu option is mainly intended for use by VMware Support.

```
--endpoint-cpu number_of_CPUs
```

## --endpoint-memory

Short name: none

The amount of memory for the VCH endpoint VM. The default is 2048MB. Set this option to increase the amount of memory in the VCH endpoint VM if the VCH will pull large container images.

**NOTE** With the exception of VCHs that pull large container images, always use the --memory option instead of the --endpointmemory option to increase the overall amount of memory for the VCH vApp, rather than on the VCH endpoint VM. Use docker
create -m to set the memory on container VMs. The --endpoint-memory option is mainly intended for use by VMware Support.

```
--endpoint-memory amount_of_memory
```

# **Other Advanced Options**

## --bridge-network-range

Short name: --bnr

The range of IP addresses that additional bridge networks can use when container application developers use docker network create to create new bridge networks. If you do not specify the bridge-network-range option, the IP range for bridge networks is 172.16.0.0/12.

When you specify the bridge network IP range, you specify the IP range as a CIDR. The smallest subnet that you can specify is /16. If you specify an invalid value for --bridge-network-range, vic-machine create fails with an error.

```
--bridge-network-range 192.168.100.0/16
```

## --base-image-size

Short name: None

The size of the base image from which to create other images. You should not normally need to use this option. Specify the size in GB or MB. The default size is 8GB. Images are thin-provisioned, so they do not usually consume 8GB of space.

```
--base-image-size 4GB
```

#### --container-store

Short name: --cs

The container-store option is not enabled. Container VM files are stored in the datastore that you designate as the image store.

## --appliance-iso

Short name: --ai

The path to the ISO image from which the VCH appliance boots. Set this option if you have moved the appliance.iso file to a folder that is not the folder that contains the vic-machine binary or is not the folder from which you are running vic-machine. Include the name of the ISO file in the path.

**NOTE**: Do not use the --appliance-iso option to point vic-machine to an --appliance-iso file that is of a different version to the version of vic-machine that you are running.

```
--appliance-iso path_to_ISO_file/appliance.iso
```

Wrap the folder names in the path in single quotes (Linux or Mac OS) or double quotes (Windows) if they include spaces.

```
--appliance-iso 'path to ISO file'/appliance.iso
```

## --bootstrap-iso

Short name: --bi

The path to the ISO image from which to boot container VMs. Set this option if you have moved the bootstrap.iso file to a folder that is not the folder that contains the vic-machine binary or is not the folder from which you are running vic-machine. Include the name of the ISO file in the path.

**NOTE**: Do not use the --bootstrap-iso option to point vic-machine to a --bootstrap-iso file that is of a different version to the version of vic-machine that you are running.

```
--bootstrap-iso path_to_ISO_file/bootstrap.iso
```

Wrap the folder names in the path in single quotes (Linux or Mac OS) or double quotes (Windows) if they include spaces.

```
--bootstrap-iso 'path to ISO file'/bootstrap.iso
```

#### --use-rp

Short name: none

Deploy the VCH appliance to a resource pool on vCenter Server rather than to a vApp. If you specify this option, vic-machine create creates a resource pool with the same name as the VCH.

```
--use-rp
```

## --debug

Short name: -v

Deploy the VCH with more verbose levels of logging, and optionally modify the behavior of vic-machine for troubleshooting purposes. Specifying the --debug option increases the verbosity of the logging for all aspects of VCH operation, not just deployment. For example, by setting the --debug option, you increase the verbosity of the logging for VCH initialization, VCH services, container VM initialization, and so on. If not specified, the --debug value is set to 0 and verbose logging is disabled.

**NOTE**: Do not confuse the vic-machine create --debug option with the vic-machine debug command, that enables access to the VCH endpoint VM. For information about vic-machine debug, see Debugging the VCH.

When you specify vic-machine create --debug, you set a debugging level of 1, 2, or 3. Setting --debug to 2 or 3 changes the behavior of vic-machine create as well as increasing the level of verbosity of the logs:

- --debug 1 Provides extra verbosity in the logs, with no other changes to vic-machine behavior.
- --debug 2 Exposes servers on more interfaces, launches pprof in container VMs.
- --debug 3 Disables recovery logic and logs sensitive data. Disables the restart of failed components and prevents container VMs from shutting down. Logs environment details for user application, and collects application output in the log

#### bundle.

Additionally, deploying a VCH with a --debug 3 enables SSH access to the VCH endpoint VM console by default, with a root password of password, without requiring you to run the vic-machine debug command. This functionality enables you to perform targeted interactive diagnostics in environments in which a VCH endpoint VM failure occurs consistently and in a fashion that prevents vic-machine debug from functioning.

**IMPORTANT**: There is no provision for persistently changing the default root password. Only use this configuration for debugging in a secured environment.

# **Advanced Examples of Deploying a VCH**

This topic provides examples of the options of the vic-machine create command to use when deploying virtual container hosts (VCHs) in various vSphere configurations.

- General Deployment Examples
  - Deploy to a vCenter Server Cluster with Multiple Datacenters and Datastores
  - Deploy to a Specific Standalone Host in vCenter Server
  - · Deploy to a Resource Pool on an ESXi Host
  - Deploy to a Resource Pool in a vCenter Server Cluster
  - · Set Limits on Resource Use
- Networking Examples
  - Specify Public, Management, Client, and Container Networks
  - Set a Static IP Address for the VCH Endpoint VM on the Different Networks
  - Configure a Non-DHCP Container Network
  - Configure a Proxy Server
- · Specify One or More Volume Stores
- Security Examples
  - Use Auto-Generated Trusted CACertificates
  - Use Custom Server Certificates
  - Combine Custom Server Certificates and Auto-Generated Client Certificates
  - Specify Different User Accounts for VCH Deployment and Operation
- Registry Server Examples
  - Authorize Access to an Insecure Private Registry Server
  - · Authorize Access to Secure Registries and vSphere Integrated Containers Registry

For simplicity, these examples use the --force option to disable the verification of the vCenter Server certificate, so the -thumbprint option is not specified. Similarly, all examples that do not relate explicitly to certificate use specify the --no-tls option.

For detailed descriptions of all of the vic-machine create options, see VCH Deployment Options.

# **General Deployment Examples**

The examples in this section demonstrate the deployment of VCHs in different vSphere environments.

## Deploy to a vCenter Server Cluster with Multiple Datacenters and Datastores

If vCenter Server has more than one datacenter, you specify the datacenter in the --target option.

If vCenter Server manages more than one cluster, you use the --compute-resource option to specify the cluster on which to deploy the VCH.

When deploying a VCH to vCenter Server, you must use the --bridge-network option to specify an existing port group for container VMs to use to communicate with each other. For information about how to create a distributed virtual switch and port group, see the section on vCenter Server Network Requirements in Environment Prerequisites for VCH Deployment.

This example deploys a VCH with the following configuration:

- Provides the vCenter Single Sign-On user and password in the --target option. Note that the user name is wrapped in quotes, because it contains the @ character. Use single quotes if you are using vic-machine on a Linux or Mac OS system and double quotes on a Windows system.
- Deploys a VCH named vch1 to the cluster cluster1 in datacenter dc1.
- Uses a port group named vic-bridge for the bridge network.
- Designates datastore1 as the datastore in which to store container images, the files for the VCH appliance, and container VMs.

vic-machine-operating\_system create

```
--target 'Administrator@vsphere.local':password@vcenter_server_address/dc1
--compute-resource cluster1
--image-store datastore1
--bridge-network vch1-bridge
--name vch1
--force
--no-tls
```

## Deploy to a Specific Standalone Host in vCenter Server

If vCenter Server manages multiple standalone ESXi hosts that are not part of a cluster, you use the --compute-resource option to specify the address of the ESXi host to which to deploy the VCH.

This example deploys a VCH with the following configuration:

- Specifies the user name, password, image store, bridge network, and name for the VCH.
- Deploys the VCH on the ESXi host with the FQDN esxihost1.organization.company.com in the datacenter dc1 . You can also specify an IP address.

```
vic-machine-operating_system create
--target 'Administrator@vsphere.local':password@vcenter_server_address/dc1
--image-store datastore1
--bridge-network vch1-bridge
--compute-resource esxihost1.organization.company.com
--name vch1
--force
--no-tls
```

## Deploy to a Resource Pool on an ESXi Host

To deploy a VCH in a specific resource pool on an ESXI host that is not managed by vCenter Server, you specify the resource pool name in the --compute-resource option.

This example deploys a VCH with the following configuration:

- Specifies the user name and password, image store, and a name for the VCH.
- Designates rp 1 as the resource pool in which to place the VCH. Note that the resource pool name is wrapped in quotes, because it contains a space. Use single quotes if you are using vic-machine on a Linux or Mac OS system and double quotes on a Windows system.

```
vic-machine-operating_system create
--target root:password@esxi_host_address
--compute-resource 'rp 1'
--image-store datastore1
--name vch1
--force
--no-tls
```

## Deploy to a Resource Pool in a vCenter Server Cluster

To deploy a VCH in a resource pool in a vCenter Server cluster, you specify the resource pool in the compute-resource option.

This example deploys a VCH with the following configuration:

- Specifies the user name, password, datacenter, image store, bridge network, and name for the VCH.
- Designates rp 1 as the resource pool in which to place the VCH. In this example, the resource pool name rp 1 is unique across all hosts and clusters, so you only need to specify the resource pool name.

```
vic-machine-operating_system create
--target 'Administrator@vsphere.local':password@vcenter_server_address/dc1
--compute-resource 'rp 1'
--image-store datastore1
--bridge-network vch1-bridge
--name vch1
--force
--no-tls
```

If the name of the resource pool is not unique across all clusters, for example if two clusters each contain a resource pool named rp 1, you must specify the full path to the resource pool in the compute-resource option, in the format cluster\_name/Resources/resource\_pool\_name.

```
vic-machine-operating_system create
--target 'Administrator@vsphere.local':password@vcenter_server_address/dc1
--compute-resource 'cluster 1'/Resources/'rp 1'
--image-store datastore1
--bridge-network vch1-bridge
--name vch1
--force
--no-tls
```

Note that the resource pool and cluster names in these examples are wrapped in quotes, because they contain spaces. Use single quotes if you are using <code>vic-machine</code> on a Linux or Mac OS system and double quotes on a Windows system.

## Set Limits on Resource Use

To limit the amount of system resources that the container VMs in a VCH can use, you can set resource limits on the VCH vApp.

This example deploys a VCH with the following configuration:

- Specifies the user name, password, image store, cluster, bridge network, and name for the VCH.
- $\bullet \quad \text{Sets resource limits on the VCH by imposing memory and CPU reservations, limits, and shares.} \\$

```
vic-machine-operating_system create
--target 'Administrator@vsphere.local':password@vcenter_server_address/dc1
--compute-resource cluster1
--image-store datastore1
--bridge-network vch1-bridge
--memory 1024
--memory-reservation 1024
--memory-shares low
--cpu 1024
--cpu-reservation 1024
--cpu-shares low
--name vch1
--force
--no-tls
```

For more information about setting resource use limitations on VCHs, see the Advanced Deployment Options and Advanced Resource Management Options sections in VCH Deployment Options.

# **Networking Examples**

The examples in this section demonstrate how to direct traffic to and from VCHs and the other elements in your environment, how to set static IPs, how to configure container VM networks, and how to configure a VCH to use a proxy server.

## Specify Public, Management, and Client Networks

In addition to the mandatory bridge network, if your vCenter Server environment includes multiple networks, you can direct different types of traffic to different networks.

- You can direct the traffic between the VCH and the Internet to a specific network by specifying the --public-network option.
   Any container VM traffic that routes through the VCH also uses the public network. If you do not specify the --public-network option, the VCH uses the VM Network for public network traffic.
- You can direct traffic between ESXi hosts, vCenter Server, and the VCH to a specific network by specifying the --management-network option. If you do not specify the --management option, the VCH uses the public network for management traffic
- You can designate a specific network for use by the Docker API by specifying the --client-network option. If you do not specify the --client-network option, the Docker API uses the public network.

**IMPORTANT**: AVCH supports a maximum of 3 distinct network interfaces. Because the bridge network requires its own port group, at least two of the public, client, and management networks must share a network interface and therefore a port group. Container networks do not go through the VCH, so they are not subject to this limitation. This limitation will be removed in a future release.

This example deploys a VCH with the following configuration:

- Specifies the user name, password, datacenter, cluster, image store, bridge network, and name for the VCH.
- Directs public and management traffic to network 1 and Docker API traffic to network 2. Note that the network names are
  wrapped in quotes, because they contain spaces. Use single quotes if you are using vic-machine on a Linux or Mac OS
  system and double quotes on a Windows system.

```
vic-machine-operating_system create
--target 'Administrator@vsphere.local':password@vcenter_server_address/dc1
--compute-resource cluster1
--image-store datastore1
--bridge-network vch1-bridge
--public-network 'network 1'
--management-network 'network 1'
--client-network 'network 2'
--name vch1
--force
--no-tls
```

For more information about the networking options, see the Networking Options section in VCH Deployment Options.

## Set a Static IP Address for the VCH Endpoint VM on the Different Networks

If you specify networks for any or all of the public, management, and client networks, you can deploy the VCH so that the VCH endpoint VM has a static IP address on one or more of those networks.

This example deploys a VCH with the following configuration:

- Specifies the user name, password, datacenter, cluster, image store, bridge network, and name for the VCH.
- Directs public and management traffic to network 1 and Docker API traffic to network 2. Note that the network names are wrapped in quotes, because they contain spaces. Use single quotes if you are using vic-machine on a Linux or Mac OS system and double quotes on a Windows system.
- Sets a DNS server for use by the public, management, and client networks.
- Sets a static IP address and subnet mask for the VCH endpoint VM on the public and client networks. Because the
  management network shares a network with the public network, you only need to specify the public network IP address.
  You cannot specify a management IP address because you are sharing a port group between the management and public
  network.

- Specifies the gateway for the public network. If you set a static IP address on the public network, you must also specify the gateway address.
- Does not specify a gateway for the client network. It is not necessary to specify a gateway on either of the client or management networks if those networks are L2 adjacent to their gateways.
- Because this example specifies a static IP address for the VCH endpoint VM on the client network, vic-machine create uses this address as the Common Name with which to create auto-generated trusted certificates. Full TLS authentication is implemented by default, so no TLS options are specified.

```
vic-machine-operating_system create
--target 'Administrator@vsphere.local':password@vcenter_server_address/dc1
--compute-resource cluster1
--image-store datastore1
--bridge-network vch1-bridge
--public-network 'network 1'
--public-network-ip 192.168.1.10/24
--public-network-gateway 192.168.1.1
--management-network 'network 1'
--client-network 'network 2'
--client-network-ip 192.168.3.10/24
--dns-server dns_server_address
--force
--name vch1
```

For more information about setting static IP addresses, see the Options for Specifying a Static IP Address for the VCH Endpoint VM in VCH Deployment Options.

## Configure a Non-DHCP Network for Container VMs

You can designate a specific network for container VMs to use by specifying the --container-network option. Containers use this network if the container developer runs docker run or docker create specifying the --net option with one of the specified container networks when they run or create a container. This option requires a port group that must exist before you run vic-machine create. You cannot use the same port group that you use for the bridge network. You can provide a descriptive name for the network, for use by Docker. If you do not specify a descriptive name, Docker uses the vSphere network name. For example, the descriptive name appears as an available network in the output of docker info and docker network 1s.

If the network that you designate as the container network in the --container-network option does not support DHCP, you can configure the gateway, DNS server, and a range of IP addresses for container VMs to use. You must specify --container-network-ip-range if container developers need to deploy containers with static IP addresses.

This example deploys a VCH with the following configuration:

- Specifies the user name, password, datacenter, cluster, image store, bridge network, and name for the VCH.
- Uses the VM Network for the public, management, and client networks.
- Designates a port group named vic-containers for use by container VMs that are run with the --net option.
- Gives the container network the name <code>vic-container-network</code> , for use by Docker.
- Specifies the gateway, two DNS servers, and a range of IP addresses on the container network for container VMs to use.

```
vic-machine-operating_system create
--target 'Administrator@vsphere.local':password@vcenter_server_address/dc1
--compute-resource cluster1
--image-store datastore1
--bridge-network vch1-bridge
--container-network vic-containers:vic-container-network
--container-network-gateway vic-containers:gateway_ip_address/24
--container-network-dns vic-containers:dns1_ip_address
--container-network-dns vic-containers:dns2_ip_address
--container-network-ip-range vic-containers:192.168.100.0/24
```

```
--name vch1
--force
--no-tls
```

For more information about the container network options, see the --container-network and Options for Configuring a Non-DHCP Network for Container Traffic sections in VCH Deployment Options.

## Configure a Proxy Server

If your network access is controlled by a proxy server, you must configure a VCH to connect to the proxy server when you deploy it, so that it can pull images from external sources.

This example deploys a VCH with the following configuration:

- Specifies the user name, password, image store, cluster, bridge network, and name for the VCH.
- Configures the VCH to access the network via an HTTPS proxy server.

```
vic-machine-operating_system create
--target 'Administrator@vsphere.local':password@vcenter_server_address/dc1
--compute-resource cluster1
--image-store datastore1
--bridge-network vch1-bridge
--https-proxy https://proxy_server_address:port
--name vch1
--force
--no-tls
```

# **Specify Volume Stores**

If container application developers will use the docker volume create command to create containers that use volumes, you must create volume stores when you deploy VCHs. You specify volume stores in the --volume-store option. You can specify --volume-store multiple times to create multiple volume stores.

When you create a volume store, you specify the name of the datastore to use and an optional path to a folder on that datastore. You also specify a descriptive name for that volume store for use by Docker.

This example deploys a VCH with the following configuration:

- Specifies the user name, password, datacenter, cluster, bridge network, and name for the VCH.
- Specifies the volumes folder on datastore 1 as the default volume store. Creating a volume store named default allows container application developers to create anonymous or named volumes by using docker create -v.
- Specifies a second volume store named volume\_store\_2 in the volumes folder on datastore 2.
- Note that the datastore names are wrapped in quotes, because they contain spaces. Use single quotes if you are using vic-machine on a Linux or Mac OS system and double quotes on a Windows system.

```
vic-machine-operating_system create
--target 'Administrator@vsphere.local':password@vcenter_server_address/dc1
--compute-resource cluster1
--bridge-network vch1-bridge
--image-store 'datastore 1'
--volume-store 'datastore 1'/volumes:default
--volume-store 'datastore 2'/volumes:volume_store_2
--name vch1
--force
--no-tls
```

For more information about volume stores, see the volume-store section in VCH Deployment Options.

# **Security Examples**

The examples in this section demonstrate how to configure a VCH to use Certificate Authority (CA) certificates to enable TLSVERIFY in your Docker environment, and to allow access to insecure registries of Docker images.

#### **Use Auto-Generated Trusted CA Certificates**

You can deploy a VCH that implements two-way authentication with trusted auto-generated TLS certificates that are signed by a

To automatically generate a server certificate that can pass client verification, you must specify the Common Name (CN) for the certificate by using the --tls-cname option. The CN should be the FQDN or IP address of the server, or a domain with a wildcard. The CN value must match the name or address that clients will use to connect to the server. You can use the --organization option to add basic descriptive information to the server certificate. This information is visible to clients if they inspect the server certificate.

If you specify an existing CAfile with which to validate clients, you must also provide an existing server certificate that is compatible with the --tls-cname value or the IP address of the client interface.

This example deploys a VCH with the following configuration:

- · Specifies the user, password, datacenter, image store, cluster, bridge network, and name for the VCH.
- Provides a wildcard domain \*.example.org as the FQDN for the VCH, for use as the Common Name in the certificate. This
  assumes that there is a DHCP server offering IP addresses on VM Network, and that those addresses have corresponding
  DNS entries such as dhcp-a-b-c.example.com.
- Specifies a folder in which to store the auto-generated certificates.

```
vic-machine-operating_system create
--target 'Administrator@vsphere.local':password@vcenter_server_address/dc1
--compute-resource cluster1
--image-store datastore1
--bridge-network vch1-bridge
--tls-cname *.example.org
--cert-path path_to_cert_folder
--force
--name vch1
```

The Docker API for this VCH will be accessible at https://dhcp-a-b-c.example.com:2376 .

For more information about using auto-generated CA certificates, see the section Restrict Access to the Docker API with Auto-Generated Certificates in VCH Deployment Options.

#### **Use Custom Server Certificates**

You can create a VCH that uses a custom server certificate, for example a server certificate that has been signed by Verisign or another public root. You use the --cert and --key options to provide the paths to a custom X.509 certificate and its key when you deploy a VCH. The paths to the certificate and key files must be relative to the location from which you are running vic-machine create.

This example deploys a VCH with the following configuration:

- Specifies the user name, password, image store, cluster, bridge network, and name for the VCH.
- Provides the paths relative to the current location of the \*.pem files for the custom server certificate and key files.

```
vic-machine-operating_system create
--target 'Administrator@vsphere.local':password@vcenter_server_address/dc1
--compute-resource cluster1
--image-store datastore1
--bridge-network vch1-bridge
```

```
--cert ../some/relative/path/certificate_file.pem
--key ../some/relative/path/key_file.pem
--name vch1
--force
```

For more information about using custom server certificates, see the section Restrict Access to the Docker API with Custom Certificates in VCH Deployment Options.

## **Combine Custom Server Certificates and Auto-Generated Client Certificates**

You can create a VCH with a custom server certificate by specifying the paths to custom server-cert.pem and server-key.pem files in the --cert and --key options. The key should be un-encrypted. Specifying the --cert and --key options for the server certificate does not affect the automatic generation of client certificates. If you specify the --tls-cname option to match the common name value of the server certificate, vic-machine create generates self-signed certificates for Docker client authentication and deployment of the VCH succeeds.

This example deploys a VCH with the following configuration:

- Specifies the user name, password, image store, cluster, bridge network, and name for the VCH.
- Provides the paths relative to the current location of the \*.pem files for the custom server certificate and key files.
- Specifies the common name from the server certificate in the --tls-cname option. The --tls-cname option is used in this case to ensure that the certificate is valid for the resulting VCH, given the network configuration.

```
vic-machine-operating_system create
--target 'Administrator@vsphere.local':password@vcenter_server_address/dc1
--compute-resource cluster1
--image-store datastore1
--bridge-network vch1-bridge
--cert ../some/relative/path/certificate_file.pem
--key ../some/relative/path/key_file.pem
--tls-cname cname_from_server_cert
--name vch1
--force
```

## Specify Different User Accounts for VCH Deployment and Operation

When you deploy a VCH, you can use different vSphere user accounts for deployment and for operation. This allows you to run VCHs with lower levels of privileges than are required for deployment.

This example deploys a VCH with the following configuration:

- Specifies the image store and name for the VCH.
- Specifies *vsphere\_admin* in the --target option, to identify the user account with *v*Sphere Administrator privileges with which to deploy the VCH.
- Specifies vsphere\_user and its password in the --ops-user and --ops-password options, to identify the user account with which the VCH runs. The user account that you specify in --ops-user must is different to the vSphere Administrator account that you use for deployment, and must exist before you deploy the VCH.
- Specifies a resource pool in which to deploy the VCH in the --compute-resource option.
- Specifies the VCH port groups in the --bridge-network and --container-network options.

```
vic-machine-operating_system create
--target vsphere_admin:vsphere_admin_password@vcenter_server_address/dc1
--compute-resource cluster1/VCH_pool
--image-store datastore1
--bridge-network vch1-bridge
--container-network vic-containers:vic-container-network
--name vch1
```

```
--ops-user vsphere_user
--ops-password vsphere_user_password
--force
--no-tls
```

For information about the permissions that the --ops-user account requires, and the permissions to set on the resource pool for the VCH and on the network folders, see Use Different User Accounts for VCH Deployment and Operation.

# **Registry Server Examples**

The examples in this section demonstrate how to configure a VCH to use a private registry server, for example vSphere Integrated Containers Registry.

## **Authorize Access to an Insecure Private Registry Server**

To authorize connections from a VCH to a private registry server without verifying the certificate of that registry, set the insecure-registry option. If you authorize a VCH to connect to an insecure private registry server, the VCH attempts to access the registry server via HTTP if access via HTTPS fails. VCHs always use HTTPS when connecting to registry servers for which you have not authorized insecure access. You can specify insecure-registry multiple times to allow connections from the VCH to multiple insecure private registry servers.

This example deploys a VCH with the following configuration:

- Specifies the user name, password, image store, cluster, bridge network, and name for the VCH.
- Authorizes the VCH to pull Docker images from the insecure private registry servers located at the URLs registry\_URL\_1
  and registry\_URL\_2.
- The registry server at registry\_URL\_2 listens for connections on port 5000.

```
vic-machine-operating_system create
--target 'Administrator@vsphere.local':password@vcenter_server_address/dc1
--compute-resource cluster1
--image-store datastore1
--bridge-network vch1-bridge
--insecure-registry registry_URL_1
--insecure-registry registry_URL_2:5000
--name vch1
--force
--no-tls
```

For more information about configuring VCHs to allow connections to insecure private registry servers, see the section on the <a href="insecure-registry">insecure-registry</a> option in VCH Deployment Options.

## Authorize Access to Secure Registries and vSphere Integrated Containers Registry

For an example of how to use --registry-ca to authorize access to vSphere Integrated Containers Registry or to another secure registry, see Deploy a VCH for Use with vSphere Integrated Containers Registry.

# Deploy a VCH for Use with vSphere Integrated Containers Registry

To use vSphere Integrated Containers Engine with vSphere Integrated Containers Registry, you must obtain the registry certificate and pass it to a virtual container host (VCH) when you create that VCH.

If you did not provide a custom server certificate and private key for the registry to the OVAinstaller when you deployed the vSphere Integrated Containers appliance, vSphere Integrated Containers Registry auto-generates a Certificate Authority (CA) certificate, a server certificate, and a server private key. You can download the auto-generated CAcertificates from the vSphere Integrated Containers Registry interface.

### **Prerequisites**

- You selected the option to deploy vSphere Integrated Containers Registry when you deployed the vSphere Integrated Containers appliance.
- You downloaded the vSphere Integrated Containers Engine bundle from the appliance.

#### **Procedure**

- 1. Obtain the CAcertificate of the registry instance or instances to use with this VCH.
  - If you deployed the registry with custom certificates, obtain the certificate from your certificate manager.
  - If you deployed the registry with auto-generated certificates, log in to the vSphere Integrated Containers Registry interface as admin user, click the admin drop-down menu and click **Download Root Cert**.
  - You can also obtain the certificate by using SCP to copy the certificate file from | /data/harbor/cert | in the vSphere | Integrated Containers appliance VM.

```
scp root@vic_appliance_address:/data/harbor/cert/ca.crt ./destination_path
```

2. Use vic-machine create to deploy a VCH, specifying the registry's CAcertificate by using the --registry-ca option.

You can configure the VCH to connect to multiple registries by specifying --registry-ca multiple times.

For simplicity, this example deploys a VCH with the \_--no-tls flag, so that container application developers do not need to use a TLS certificate to connect a Docker client to the VCH. However, the connection between the VCH and the registry still requires certificate authentication.

```
vic-machine-operating_system create
--target 'Administrator@vsphere.local':password@vcenter_server_address/dc1
--compute-resource cluster1
--image-store datastore1
--bridge-network vch1-bridge
--name vch_registry
--force
--no-tlsverify
--registry-ca=cert_path/ca.crt
```

### Result

The VCH has a copy of the registry certificate and can connect to this vSphere Integrated Containers Registry instance.

# Use Different User Accounts for VCH Deployment and Operation

Avirtual container host (VCH) appliance requires the appropriate permissions in vSphere to perform various tasks during VCH operation

During deployment of a VCH, vic-machine uses the vSphere account that you specify in either of the vic-machine create --user or --target options for all deployment operations. Deployment of a VCH requires a user account with vSphere Administrator privileges.

Day-to-day operation of a VCH requires fewer permissions than deployment. You can configure a VCH so that it uses different user accounts for deployment and for operation by using the vic-machine create --ops-user and --ops-password options when you deploy the VCH. By specifying --ops-user, you can limit the post-deployment permissions of the VCH to only those vSphere operations that it needs. If you do not specify --ops-user, the VCH runs with full vSphere Administrator privileges.

After deployment, a VCH must have permission to perform the following operations:

- · Create, modify, and delete VMs within its resource pool
- Reconfigure the endpoint VM
- · Validate host firewall configuration and system licenses

When you deploy a VCH, a user account that you specify in --ops-user must have the correct privileges to allow the VCH to perform these operations. vSphere Integrated Containers Engine does not currently create the required roles, so to assign privileges to the --ops-user user account, you must manually create user roles in vSphere before you deploy the VCH. You assign privileges to those roles, and assign the roles to the user account to use in --ops-user.

### **Procedure**

1. In the vSphere Web Client, create a user group, for example vic ops users, and add the appropriate user accounts to the user group.

The best practice when assigning roles in vSphere is to assign the roles to user groups and then to add users to those groups, rather than assigning roles to the users directly.

2. Go to Administration > Roles and create one role for each type of inventory object that VCHs need to access.

It is possible to create a single role, but by creating multiple roles you keep the privileges of the VCH as granular as possible.

Role to Create	Required Permissions
VCH - vcenter	Datastore > Configure datastore
VCH - datacenter	Datastore > Configure datastore Datastore > Low level file operations
VCH - datastore	Datastore > AllocateSpace Datastore > Browse datastore Datastore > Configure datastore Datastore > Remove file Datastore > Low level file operations Host > Configuration > System management
VCH - network	Network > Assign network
	dvPort group > Modify dvPort group > Policy operation dvPort group > Scope operation vApp > Add virtual machine VirtualMachine > Configuration > Add existing disk VirtualMachine > Configuration > Add new disk VirtualMachine > Configuration > Add or remove device VirtualMachine > Configuration > Advanced VirtualMachine > Configuration > Modify device settings VirtualMachine > Configuration > Remove disk

VirtualMachine > Configuration > Rename
VirtualMachine > Guest operations > Guest operation program execution
VirtualMachine > Interaction > Device connection
VirtualMachine > Interaction > Power off
VirtualMachine > Interaction > Power on
VirtualMachine > Inventory > Create new
VirtualMachine > Inventory > Remove
VirtualMachine > Inventory > Register
VirtualMachine > Inventory > Unregister

For information about how to create vSphere roles, see vSphere Permissions and User Management Tasks in the vSphere documentation.

3. Go to **Networking**, create a network folder, and place the distributed virtual switches that the VCHs will use for the bridge network and any container networks into that folder.

The parent object of distributed virtual switches that the VCH uses as the bridge network and container networks must be set to Read-Only, with **Propagate to Children** enabled. By placing distributed virtual switches in a network folder, you avoid setting an entire datacenter to Read-Only. This restriction only applies to the bridge network and container networks. When you specify the vic-machine create --bridge-network and --container-network options, include the full inventory path to the networks in the following format:

datacenter/network/network\_folder/port\_group\_name

4. (Optional) Go to Hosts and Clusters and create a resource pool in which to deploy VCHs.

By creating a resource pool for VCHs, you can set the correct permissions on just that resource pool rather than on an entire host or cluster. You specify this resource pool in the vic-machine create --compute-resource option when you deploy the VCH. For a more granular application of privileges, you can also apply the permissions directly to VCH vApps after deployment, rather than to a resource pool.

5. In each of the **Hosts and Clusters**, **Storage**, and **Networking** views, select inventory objects and assign the user group and the appropriate role to each one.

Inventory Object	Role to Assign	Propagate
Top-level vCenter Server instance	VCH - vcenter	No
Datacenters	VCH - datacenter	No
Clusters. All datastores in the cluster inherit permissions from the cluster.	VCH - datastore	Yes
Standalone VMware vSAN datastores	VCH - datastore	No
Standalone datastores	VCH - datastore	No
Network folders	Read-only	Yes
Port groups	VCH - network	No
Resource pools for VCHs	VCH - endpoint	Yes
VCH vApps, for a very granular application of privileges	VCH - endpoint	Yes

For information about how to assign permissions to objects in the vSphere Inventory, see Add a Permission to an Inventory Object in the vSphere documentation.

### What to do next

Use vic-machine create --ops-user=<user\_account> to deploy VCHs that operate with restricted privileges. Ensure that the various vSphere inventory objects that you specify as arguments have the user group with the appropriate role. For an example of a vic-machine command with the --ops-user option, see the section Specify Different User Accounts for VCH Deployment and Operation Advanced Examples of Deploying a VCH.

# **Upgrading vSphere Integrated Containers**

If you have an existing deployment of vSphere Integrated Containers, you can upgrade its components to a 1.1.x release.

- You can upgrade the vSphere Integrated Containers appliance from version 1.1.x to a later 1.1.y update release. Upgrading the appliance upgrades both vSphere Integrated Containers Registry and vSphere Integrated Containers Management portal, and allows you to download the new version of vSphere Integrated Containers Engine.
- To upgrade vSphere Integrated Containers Engine from 0.8 or later to a 1.1.x release, you upgrade the virtual container hosts (VCHs) individually.
- You can upgrade vSphere Integrated Containers Registry from version 0.5 to version 1.1.x.
- You can upgrade the HTML5 vSphere Client plug-in from version 1.1.x to a later 1.1.y update release.
- vSphere Integrated Containers 1.0 did not officially support vSphere Integrated Containers Management Portal. You cannot upgrade an instance of vSphere Integrated Containers Management Portal (Admiral) that predates version 1.1.0 to version 1.1.x.

**NOTE**: No new development work is planned for the plug-in for the Flex-based vSphere Web Client. In this and future releases, only the HTML5 vSphere Client will be updated. This release adds no new features to the Flex plug-in. If you installed the Flex plug-in with a previous release of vSphere Integrated Containers, there is no upgrade to perform.

- Upgrade the vSphere Integrated Containers Appliance
- Upgrade a VCH
- Upgrade the HTML5 vSphere Client Plug-In on vCenter Server for Windows
- Upgrade the HTML5 vSphere Client Plug-In on a vCenter Server Appliance
- Upgrade vSphere Integrated Containers Registry 0.5 to 1.1.x

## **Upgrade the vSphere Integrated Containers Appliance**

If you deployed a 1.1.x version of the vSphere Integrated Containers appliance, you can upgrade your existing installation to a later 1.1.y update release.

To upgrade an instance of vSphere Integrated Containers Registry 0.5 (Harbor) that you deployed with vSphere Integrated Containers 1.0, see Upgrade vSphere Integrated Containers Registry 0.5 to 1.1.x.

### **Prerequisites**

- You have an existing vSphere Integrated Containers 1.1.x appliance that you deployed by using the official OVA installer.
- Back up the previous appliance by using your usual backup tools.
- Deploy the new version of the vSphere Integrated Containers appliance to a location in which it can access the VMDK files
  of the previous appliance. For information about using the OVA installer, see Deploy the vSphere Integrated Containers
  Appliance.

**IMPORTANT**: In the **Registry Configuration** section of the installer, make sure that you provide the same passwords in the **Registry Admin Password** and **Database Password** as the previous appliance uses.

• Log in to a vSphere Web Client instance from which you can access both versions of the vSphere Integrated Containers appliance. If you use vSphere 6.5, log in to the Flex-based vSphere Web Client, not the HTML5 vSphere Client.

#### Procedure

1. Shut down both of the previous and new vSphere Integrated Containers appliances by selecting Shut Down Guest OS.

IMPORTANT: Do not select Power Off.

- 2. Right-click the previous vSphere Integrated Containers appliance, and select Edit Settings.
- 3. Hover your mouse over Hard disk 2, click the Remove button, and click OK.

Hard disk 2 is the larger of the two disks.

IMPORTANT: Do not check the Delete files from this datastore checkbox.

- 4. Right-click the new vSphere Integrated Containers appliance, and select Edit Settings.
- 5. Hover your mouse over Hard disk 2, click the Remove button, and check the Delete files from this datastore checkbox.
- 6. Click the New device drop-down menu at the bottom of the Edit Settings wizard, select Existing Hard Disk, and click Add.
- 7. Navigate to the VDMK files of the previous appliance, select the VMDK file with the file name that ends in \_1 , and click **OK**.
- 8. Click  $\mathbf{OK}$  again to update the VM settings.
- 9. Power on the new appliance to complete the upgrade.

### What to Do Next

Log into the new versions of vSphere Integrated Containers Registry and vSphere Integrated Containers Management Portal to verify that the data from your previous vSphere Integrated Containers installation has migrated successfully.

### **Upgrade a VCH**

You upgrade virtual container hosts (VCHs) by downloading a new version of vSphere Integrated Containers Engine and running the vic-machine upgrade command.

You can use vic-machine upgrade to upgrade VCHs from version 0.8 and above. You can run vic-machine upgrade on VCHs that are either running or powered off. When you upgrade a running VCH, the VCH goes temporarily offline, but container workloads continue as normal during the upgrade process. Upgrading a VCH does not affect any mapped container networks that you defined by setting the vic-machine create --container-network option. The following operations are not available during upgrade:

- You cannot access container logs
- You cannot attach to a container
- · NAT based port forwarding is unavailable

**IMPORTANT**: Upgrading a VCH does not upgrade any existing container VMs that the VCH manages. For container VMs to boot from the latest version of <code>bootstrap.iso</code>, container developers must recreate them.

For descriptions of the options that vic-machine upgrade includes in addition to the Common vic-machine Options, see VCH Upgrade Options.

### **Prerequisites**

- You deployed one or more VCHs with an older version of the vic-machine create command.
- You downloaded a new version of the vSphere Integrated Containers Engine bundle.
- Run the vic-machine 1s command by using the new version of vic-machine to see the upgrade status of all of the VCHs that are running on a vCenter Server instance or ESXi host. For information about running vic-machine 1s, see List VCHs and Obtain Their IDs.
- Optionally note the IDs of the VCHs.

### **Procedure**

- 1. On the system on which you run vic-machine, navigate to the directory that contains the new version of the vic-machine utility.
- 2. Run the vic-machine upgrade command.

The following example includes the options required to upgrade a VCH in a simple vCenter Server environment.

- You must specify the username and optionally the password, either in the target option or separately in the --user and --password options.
- If the VCH has a name other than the default name, virtual-container-host, you must specify the --name or --id option.
- If multiple compute resources exist in the datacenter, you must specify the --compute-resource or --id option.
- If your vSphere environment uses untrusted, self-signed certificates, you must also specify the thumbprint of the vCenter Server instance or ESXi host in the --thumbprint option. To obtain the thumbprint of the vCenter Server or ESXi host certificate, run vic-machine without the specifying the --thumbprint or --force options. The upgrade of the VCH fails, but the resulting error message includes the required certificate thumbprint. You can copy the thumbprint from the error message and run vic-machine again, including the --thumbprint option.

**NOTE**: If you obtain the thumbprint by other means, use upper-case letters and colon delimitation in the thumbprint. Do not use space delimitation.

```
$ vic-machine-operating_system upgrade
--target vcenter_server_username:password@vcenter_server_address
--thumbprint certificate_thumbprint
--name vch_name
```

3. If the upgrade operation fails with error messages, run vic-machine upgrade again, specifying a timeout longer than 3 minutes in the --timeout option.

```
$ vic-machine-operating_system upgrade
--target vcenter_server_username:password@vcenter_server_address
--thumbprint certificate_thumbprint
--name vch_name
--timeout 5m0s
```

4. If the upgrade operation continues to fail with error messages, run vic-machine upgrade again with the --force option.

If your vSphere environment uses untrusted, self-signed certificates, running vic-machine upgrade with the --force option allows you to omit the --thumbprint option.

```
$ vic-machine-operating_system upgrade
--target vcenter_server_username:password@vcenter_server_address
--name vch_name
--timeout 5m0s
--force
```

5. (Optional) To roll back an upgraded VCH to the previous version, or to revert a VCH that failed to upgrade, run vic-machine upgrade again with the --rollback option.

```
$ vic-machine-operating_system upgrade
--target vcenter_server_username:password@vcenter_server_address
--name vch_name
--force
--rollback
```

### Result

During the upgrade process, vic-machine upgrade performs the following operations:

- Validates whether the configuration of the existing VCH is compatible with the new version. If not, the upgrade fails.
- Uploads the new versions of the appliance.iso and bootstrap.iso files to the VCH. There is no timeout for this stage of the upgrade process, so that the ISO files can upload over slow connections.
- Creates a snapshot of the VCH endpoint VM, to use in case the upgrade fails and has to roll back.
- Boots the VCH by using the new version of the appliance.iso file.
- $\bullet \;\;$  Deletes the snapshot of the VCH endpoint VM once the upgrade has succeeded.
- After you upgrade a VCH, any new container VMs will boot from the new version of the bootstrap.iso file.
- If the upgrade times out while waiting for the VCH service to start, the upgrade fails and rolls back to the previous version.

### What to Do Next

Upgrade the HTML5 vSphere Client plug-in:

- Upgrade the HTML5 vSphere Client Plug-In on vCenter Server for Windows
- Upgrade the HTML5 vSphere Client Plug-In on a vCenter Server Appliance

## **VCH Upgrade Options**

The command line utility for vSphere Integrated Containers Engine, vic-machine, provides an upgrade command that allows you to upgrade virtual container hosts (VCHs) to a newer version.

The vic-machine upgrade command includes the following options in addition to the common options described in Common vic-machine Options.

### --appliance-iso

Short name: --ai

The path to the new version of the ISO image from which to upgrade the VCH appliance. Set this option if you have moved the appliance.iso file to a folder that is not the folder that contains the vic-machine binary or is not the folder from which you are running vic-machine. Include the name of the ISO file in the path.

**NOTE**: Do not use the --appliance-iso option to point vic-machine to an --appliance-iso file that is of a different version to the version of vic-machine that you are running.

```
--appliance-iso path_to_ISO_file/ISO_file_name.iso
```

Wrap the folder names in the path in single quotes (Linux or Mac OS) or double quotes (Windows) if they include spaces.

```
--appliance-iso 'path to ISO file'/appliance.iso
```

### --bootstrap-iso

Short name: --bi

The path to the new version of the ISO image from which to upgrade the container VMs that the VCH manages. Set this option if you have moved the bootstrap.iso file to a folder that is not the folder that contains the vic-machine binary or is not the folder from which you are running vic-machine. Include the name of the ISO file in the path.

**NOTE**: Do not use the --bootstrap-iso option to point vic-machine to a --bootstrap-iso file that is of a different version to the version of vic-machine that you are running.

```
--bootstrap-iso path_to_ISO_file/bootstrap.iso
```

Wrap the folder names in the path in single quotes (Linux or Mac OS) or double quotes (Windows) if they include spaces.

```
--bootstrap-iso 'path to ISO file'/ISO_file_name.iso
```

### --force

Short name: -f

Forces vic-machine upgrade to ignore warnings and continue with the upgrade of a VCH. Errors such as an incorrect compute resource still cause the upgrade to fail.

If your vSphere environment uses untrusted, self-signed certificates, you can use the --force option to upgrade a VCH without providing the thumbprint of the vCenter Server or ESXi host in the thumbprint option.

```
--force
```

### --rollback

### Short name: None

Rolls a VCH back to its previous version, for example if upgrade failed. Before starting the upgrade process, vic-machine upgrade takes a snapshot of the existing VCH. The upgrade process deletes older snapshots from any previous upgrades. The -rollback option reverts an upgraded VCH to the snapshot of the previous deployment. Because vic-machine upgrade only retains one snapshot, you can only use --rollback to revert the VCH to the version that immediately precedes the most recent upgrade.

--rollback

# Upgrade the HTML5 vSphere Client Plug-In on vCenter Server for Windows

If you have a previous 1.1.x installation of the HTML5 vSphere Client plug-in for vSphere Integrated Containers and you download a newer 1.1.y version of vSphere Integrated Containers, you must upgrade the HTML5 plug-in. This procedure describes how to upgrade an existing HTML5 plug-in for vCenter Server on Windows.

**NOTE**: No new development work is planned for the plug-in for the Flex-based vSphere Web Client. In this and future releases, only the HTML5 vSphere Client will be updated. This release adds no new features to the Flex plug-in. If you installed the Flex plug-in with a previous release of vSphere Integrated Containers, there is no upgrade to perform.

### **Prerequisites**

- You are upgrading the HTML5 plug-in on a vCenter Server instance that runs on Windows. If you are running a vCenter Server appliance instance, see Upgrade the HTML5 vSphere Client Plug-In on a vCenter Server Appliance.
- You deployed an older version of the vSphere Integrated Containers plug-in for the HTML5 vSphere Client with a previous
  version of vSphere Integrated Containers 1.1.x. For information about installing the HTML5 plug-in for the first time, see
  Install the Client Plug-Ins on vCenter Server for Windows.
- You upgraded an existing vSphere Integrated Containers 1.1.x appliance to a newer 1.1.y version. For information about upgrading the vSphere Integrated Containers appliance, see Upgrade the vSphere Integrated Containers Appliance.
- Log in to the Windows system on which vCenter Server is running. You must perform all of the steps in this procedure on this Windows system.
- Go to https://upgraded\_vic\_appliance\_address:9443 in a Web browser, download the new version of the vSphere Integrated Containers Engine package, vic\_1.1.y.tar.gz, and unpack it on the Desktop.

**NOTE**: If the upgraded vSphere Integrated Containers appliance uses a different port for the file server, replace 9443 with the appropriate port in the prerequisites above and in the procedure below.

### Procedure

1. Open a command prompt as Administrator and run the following command to obtain the SHA-1 thumprint of the file server that is running in the upgraded vSphere Integrated Containers appliance.

```
echo | "%VMWARE_OPENSSL_BIN%" s_client -connect upgraded_vic_appliance_address:9443 | "%VMWARE_OPENSSL_BIN%" x509 -fingerprint -sha1 -noout
```

2. Open the new version of the \vic\ui\vCenterForWindows\configs file in a text editor.

```
notepad %USERPROFILE%\Desktop\vic\ui\vCenterForWindows\configs
```

3. Enter the IPv4 address or FQDN of the vCenter Server instance on which to upgrade the plug-in.

```
SET target_vcenter_ip=vcenter_server_address
```

4. Enter the URL of the file server in the upgraded vSphere Integrated Containers appliance.

```
SET vic_ui_host_url=https://upgraded_vic_appliance_address:9443/
```

5. Copy the SHA-1 thumbprint of the file server that you obtained in step 1 and paste it into the configs file.

```
SET vic_ui_host_thumbprint=thumbprint
```

**NOTE**: Use colon delimitation in the thumbprint. Do not use space delimitation.

- 6. Save the configs file.
- 7. Run the upgrade script, entering the user name and password for the vCenter Server administrator account when prompted.

%USERPROFILE%\Desktop\vic\ui\vCenterForWindows\upgrade.bat

8. When the upgrade finishes, stop and restart the HTML5 vSphere Client service.

"C:\Program Files\VMware\vCenter Server\bin\service-control" --stop vsphere-ui

"C:\Program Files\VMware\vCenter Server\bin\service-control" --start vsphere-ui

### What to Do Next

Log in to the vSphere Client, go to the vSphere Integrated Containers view, and verify that the version number reflects the upgrade.

# Upgrade HTML5 vSphere Client Plug-In on a vCenter Server Appliance

If you have a previous 1.1.x installation of the HTML5 vSphere Client plug-in for vSphere Integrated Containers and you download a newer 1.1.y version of vSphere Integrated Containers, you must upgrade the HTML5 plug-in. This procedure describes how to upgrade an existing HTML5 plug-in for a vCenter Server Appliance.

**NOTE**: No new development work is planned for the plug-in for the Flex-based vSphere Web Client. In this and future releases, only the HTML5 vSphere Client will be updated. This release adds no new features to the Flex plug-in. If you installed the Flex plug-in with a previous release of vSphere Integrated Containers, there is no upgrade to perform.

### **Prerequisites**

- You are upgrading the HTML5 plug-in on a vCenter Server appliance instance. If you are running vCenter Server on Windows, see Upgrade the HTML5 vSphere Client Plug-In on vCenter Server for Windows.
- You deployed an older version of the vSphere Integrated Containers plug-in for the HTML5 vSphere Client with a previous
  version of vSphere Integrated Containers 1.1.x. For information about installing the HTML5 plug-in for the first time, see
  Install the Client Plug-Ins on a vCenter Server Appliance.
- You upgraded an existing vSphere Integrated Containers 1.1.x appliance to a newer 1.1.y version. For information about upgrading the vSphere Integrated Containers appliance, see Upgrade the vSphere Integrated Containers Appliance.
- Go to the vCenter Server Appliance Management Interface (VAMI) at https://vcsa\_address:5480, click **Access**, and make sure that Bash Shell is enabled.

**NOTE**: If the upgraded vSphere Integrated Containers appliance uses a different port for the file server, replace 9443 with the appropriate port in the procedure below.

### **Procedure**

1. Connect as root user to the vCenter Server Appliance by using SSH.

```
ssh root@vcsa_address
```

2. Use curl to copy the new vSphere Integrated Containers Engine binaries from the file server in the upgraded vSphere Integrated Containers appliance to the vCenter Server Appliance.

```
curl -k https://upgraded_vic_appliance_address:9443/vic_1.1.x.tar.gz -o vic_1.1.x.tar.gz
```

NOTE: Update vic\_1.1.x to the appropriate version in the command above and in the next step.

3. Unpack the vSphere Integrated Containers binaries.

```
tar -zxf vic_1.1.x.tar.gz
```

4. Use a text editor to set the vCenter Server address in the /vic/ui/VCSA/configs file.

```
VCENTER_IP="vcsa_address"
```

Alternatively, you can use a utility such as sed to update the configs file:

```
sed -i 's#^\(VCENTER_IP=\).*$#\1"vcsa_address"#' ~/vic/ui/*/configs
```

5. Set the address of the upgraded vSphere Integrated Containers appliance in the /vic/ui/vcsa/configs file.

```
VIC_UI_HOST_URL="https://upgraded_vic_appliance_address:9443/"
```

Alternatively, you can use sed:

```
sed -i 's#^\(VIC_UI_HOST_URL=\).*$#\1"https://upgraded_vic_appliance_address:9443"#'
~/vic/ui/*/configs
```

6. Obtain the thumbprint of the upgraded vSphere Integrated Containers appliance file server certificate.

```
echo | openssl s_client -connect upgraded\_vic\_appliance\_address:9443 | openssl x509 - fingerprint -shal -noout
```

7. Set the certificate thumbprint in the /vic/ui/vcsA/configs file, replacing *thumbprint* with the output of the command from the preceding step.

```
VIC_UI_HOST_THUMBPRINT="thumbprint"
```

Alternatively, you can use sed:

```
sed -i 's#^\(VIC_UI_HOST_THUMBPRINT=\).*$#\1"thumbprint"#' ~/vic/ui/*/configs
```

8. Navigate to /vic/ui/vcsA , and run the upgrade script, entering the user name and password for the vCenter Server administrator account when prompted.

```
cd vic/ui/VCSA
```

```
./upgrade.sh
```

9. When the upgrade finishes, stop and restart the HTML5 vSphere Client service.

```
service-control --stop vsphere-ui
```

```
service-control --start vsphere-ui
```

### What to Do Next

Log in to the vSphere Client, go to the vSphere Integrated Containers view, and verify that the version number reflects the upgrade.

## Upgrade vSphere Integrated Containers Registry 0.5 to 1.1.x

If you deployed version 0.5 of vSphere Integrated Containers Registry (Harbor) with vSphere Integrated Containers 1.0, you can upgrade your existing installation to version 1.1.x.

### **Prerequisites**

- You have a vSphere Integrated Containers Registry 0.5 installation that you deployed by using the official OVAinstaller from vSphere Integrated Containers 1.0.
- Back up the previous appliance by using your usual backup tools.
- Deploy the new vSphere Integrated Containers 1.1 appliance by using the OVAinstaller. For information about using the OVAinstaller, see Deploy the vSphere Integrated Containers Appliance.
  - Deploy the 1.1 appliance in a location in which it can access the VMDK files of the 0.5 appliance.
  - In the Appliance Security section of the Customize template page of the installer, do not disable SSH access to the 1.1 appliance.
  - In the **Registry Configuration** section of the installer, make sure that you provide the same passwords in the **Registry Admin Password** and **Database Password** as the 0.5 appliance uses.
- Log in to a vSphere Web Client instance from which you can access both of the vSphere Integrated Containers Registry 0.5 and 1.1 vSphere Integrated Containers appliances.
- If you use vSphere 6.5, log in to the Flex-based vSphere Web Client, not the HTML5 vSphere Client.

### Procedure

1. Shut down the vSphere Integrated Containers Registry 0.5 appliance by selecting Shut Down Guest OS.

IMPORTANT: Do not select Power Off.

- 2. Right-click the new vSphere Integrated Containers 1.1 appliance, and select Edit Settings.
- 3. Click the New device drop-down menu at the bottom of the Edit Settings wizard, select Existing Hard Disk, and click Add.
- 4. Navigate to the VDMK files of the 0.5 appliance, select one of the VMDK files, and click OK.

You can select either VMDK file. The order of selection is not important.

- 5. Expand the entry for New Hark disk and make sure that the new disk is attached as Virtual Device Node scs1(0:2).
- 6. Click Existing Hard Disk > Add again, select the other VMDK file, and click OK.
- 7. Make sure that the new disk is attached as Virtual Device Node scs1(0:3) and click OK to close the Edit Settings window.
- 8. Power on the vSphere Integrated Containers 1.1 appliance, then use SSH to connect to it as root user.

```
\$ \  \, \mathsf{ssh} \  \, \mathsf{root} @\mathit{vic\_appliance\_address}
```

- 9. Run the upgrade script and respond to the prompts until you see confirmation that the upgrade is complete.
  - \$ /etc/vmware/harbor/upgrade\_from\_0.5.sh
- 10. Shut down the vSphere Integrated Containers 1.1 appliance, and edit its settings to detach the two VDMK files that you attached above.
- 11. Power on the vSphere Integrated Containers 1.1 appliance to complete the upgrade.

### What to Do Next

Log into the new version of vSphere Integrated Containers Registry at https://vic\_1.1\_appliance\_address:443 to verify that the data from your vSphere Integrated Containers Registry 0.5 installation has migrated successfully.

# Manage the vSphere Integrated Containers Appliance

This section provides information about how to manage your vSphere Integrated Containers appliance.

- Reconfigure the vSphere Integrated Containers Appliance
- Check the Status of the vSphere Integrated Containers Services
- Restart the vSphere Integrated Containers Services

## Reconfigure the vSphere Integrated Containers Appliance

After you have deployed the vSphere Integrated Containers appliance, you can reconfigure the settings that you provided to the OVAinstaller during deployment. You can also reconfigure the appliance VM itself, for example to expand the amount of storage for vSphere Integrated Containers Registry, or to increase memory and processing power.

### **Prerequisites**

- Log in to a vSphere Web Client instance for the vCenter Server instance on which the vSphere Integrated Containers
  appliance is running.
- If you use vSphere 6.5, log in to the Flex-based vSphere Web Client, not the HTML5 vSphere Client.

### **Procedure**

1. Shut down the vSphere Integrated Containers appliance by selecting Shut Down Guest OS.

IMPORTANT: Do not select Power Off.

- 2. Right-click the new vSphere Integrated Containers appliance, and select Edit Settings.
- 3. In the Virtual Hardware tab, reconfigure the appliance VM as necessary.
  - Increase the number of CPUs
  - Increase the amount of RAM
  - o Increase the size of hard disk 2 to expand the storage for vSphere Integrated Containers Registry
- 4. Click vApp Options to modify the settings that you provided when you used the OVA installer to deploy the appliance.
  - In Appliance Security, update the password for the appliance root account, enable or disable SSH log in.
  - Reconfigure Networking Properties to set a static IP address, update the network configuration, or remove all settings to enable DHCP.
  - Reconfigure Registry Configuration to enable or disable vSphere Integrated Containers Registry, change the ports on
    which the registry publishes services, update the admin and database passwords, enable or disable garbage
    collection, or update the certificate and key.
  - Reconfigure **Management Portal Configuration** to enable or disable vSphere Integrated Containers Management Portal, change the port on which the portal publishes services, or update the certificate and key.
  - Reconfigure File Server Configuration to change the port on which the file server publishes the vSphere Integrated Containers Engine download, or update the certificate and key.

 $\textbf{NOTE} : It is not recommended to modify the \textbf{Deployment} \ and \ \textbf{Authoring} \ settings.$ 

- 5. Click  $\mathbf{OK}$  to close the Edit Settings window.
- 6. Power on the vSphere Integrated Containers appliance to complete the reconfiguration.

### Result

When the appliance powers on, the new settings are automatically applied.

# **Check the Status of the vSphere Integrated Containers Services**

You can check the status of the vSphere Integrated Containers Registry and vSphere Integrated Containers Management Portal services, and the file server that runs in the appliance, by logging in to the vSphere Integrated Containers appliance.

### **Prerequisites**

You deployed the vSphere Integrated Containers appliance

#### **Procedure**

- 1. Connect to the vSphere Integrated Containers appliance by using SSH.
- 2. Run one of the following commands to check the status of one of the vSphere Integrated Containers services:
  - vSphere Integrated Containers Registry: systemct1 status harbor
  - VSphere Integrated Containers Management Portal services: systemctl status admiral
  - Embedded file server: systemctl status fileserver

### Result

The output shows the status of the service that you specified, as well as the most recent log entries.

Status	Description
active (running)	The service is running correctly.
inactive (failed)	The service failed to start.
inactive (dead)	The service is not responding.

### What to Do Next

If the status is inactive (failed) Or inactive (dead), see Restart the vSphere Integrated Containers Services.

# Restart the vSphere Integrated Containers Services

You can restart the vSphere Integrated Containers Registry and vSphere Integrated Containers Management Portal services and the file server that run in the appliance by logging in to the vSphere Integrated Containers appliance.

### **Prerequisites**

You deployed the vSphere Integrated Containers appliance.

### **Procedure**

- 1. Connect to the vSphere Integrated Containers appliance by using SSH.
- 2. Run one of the following commands to restart one of the vSphere Integrated Containers services:
  - vSphere Integrated Containers Registry: systemctl restart harbor
  - vSphere Integrated Containers Management Portal services: systemctl restart admiral
  - Embedded file server: systemctl restart fileserver

# **Managing Virtual Container Hosts**

The vic-machine utility provides commands that allow you to manage existing virtual container hosts (VCHs). vSphere Integrated Containers also provides an administration portal for VCHs.

- Obtain vic-machine Version Information
- Common vic-machine Options
- List VCHs and Obtain their IDs
- Obtain Information About a VCH
- Delete a VCH
- Debugging the VCH
- Access the VCH Admin Portal
- Access Log Bundles

## Obtain vic-machine Version Information

You can obtain information about the version of vic-machine by using the vic-machine version command.

### Prerequisites

You have downloaded and unpacked the vSphere Integrated Containers Engine binaries.

#### Procedure

- 1. On the system on which you downloaded the binaries, navigate to the directory that contains the vic-machine utility.
- 2. Run the vic-machine version command.

The vic-machine version command has no arguments.

\$ vic-machine-operating\_system version

### Result

The vic-machine utility displays the version of the instance of vic-machine that you are using.

vic-machine-operating\_system
version vic\_machine\_version-vic\_machine\_build-git\_commit

- vic\_machine\_version is the version number of this release of vSphere Integrated Containers Engine.
- vic\_machine\_build is the build number of this release.
- tag is the short git commit checksum for the latest commit for this build.

## Common vic-machine Options

This section describes the options that are common to all vic-machine commands. The common options that vic-machine requires relate to the vSphere environment in which you deployed the virtual container host (VCH), and to the VCH itself.

### --target

Short name: -t

The IPv4 address, fully qualified domain name (FQDN), or URL of the ESXi host or vCenter Server instance on which you deployed the VCH. This option is always **mandatory**.

• If the target ESXi host is not managed by vCenter Server, provide the address of the host.

```
--target esxi_host_address
```

 If the target ESXi host is managed by vCenter Server, or if you deployed the VCH to a cluster, provide the address of vCenter Server.

```
--target vcenter_server_address
```

• You can include the user name and password in the target URL.

```
--target vcenter_or_esxi_username:password@vcenter_or_esxi_address
```

Wrap the user name or password in single quotes (Linux or Mac OS) or double quotes (Windows) if they include special characters.

```
'vcenter_or_esxi_usern@me':'p@ssword'@vcenter_or_esxi_address
```

If you do not include the user name in the target URL, you must specify the user option. If you do not specify the password option or include the password in the target URL, vic-machine prompts you to enter the password.

• If you deployed the VCH on a vCenter Server instance that includes more than one datacenter, include the datacenter name in the target URL. If you include an invalid datacenter name, vic-machine fails and suggests the available datacenters that you can specify.

```
--target vcenter_server_address/datacenter_name
```

### --user

Short name: -u

The username for the ESXi host or vCenter Server instance on which you deployed the VCH. This option is mandatory if you do not specify the username in the target option.

```
--user esxi_or_vcenter_server_username
```

Wrap the user name in single quotes (Linux or Mac OS) or double quotes (Windows) if it includes special characters.

```
--user 'esxi_or_vcenter_server_usern@me'
```

### --password

Short name: -p

The password for the user account on the vCenter Server on which you deployed the VCH, or the password for the ESXi host if you deployed directly to an ESXi host. If not specified, vic-machine prompts you to enter the password.

```
--password esxi_host_or_vcenter_server_password
```

Wrap the password in single quotation marks (') on Mac OS and Linux and in double quotation (") marks on Windows if it includes special characters.

```
--password 'esxi_host_or_vcenter_server_p@ssword'
```

### --thumbprint

Short name: None

The thumbprint of the vCenter Server or ESXi host certificate. Specify this option if your vSphere environment uses untrusted, self-signed certificates. Alternatively, specifying the --force option allows you to omit the --thumbprint option. If your vSphere environment uses trusted certificates that are signed by a known Certificate Authority (CA), you do not need to specify the thumbprint option.

To obtain the thumbprint of the vCenter Server or ESXI host certificate, run vic-machine without the specifying the --thumbprint or --force options. The operation fails, but the resulting error message includes the required certificate thumbprint. You can copy the thumbprint from the error message and run vic-machine again, including the thumbprint option.

**NOTE**: If you obtain the thumbprint by other means, use upper-case letters and colon delimitation in the thumbprint. Do not use space delimitation.

```
--thumbprint certificate_thumbprint
```

### --compute-resource

Short name: -r

The relative path to the host, cluster, or resource pool in which you deployed the VCH. Specify --compute-resource with exactly the same value that you used when you ran vic-machine create. You specify the compute-resource option in the following circumstances:

- vCenter Server includes multiple instances of standalone hosts or clusters, or a mixture of standalone hosts and clusters.
- You deployed the VCH in a specific resource pool in your environment.

If you specify the id option, you do not need to specify the compute-resource option.

If you do not specify the compute-resource or id options and multiple possible resources exist, vic-machine fails and suggests valid targets for compute-resource in the failure message.

• If the VCH is in a specific resource pool on an ESXi host, specify the name of the resource pool:

```
--compute-resource resource_pool_name
```

If the VCH is on a vCenter Server instance that has more than one standalone host but no clusters, specify the IPv4
address or fully qualified domain name (FQDN) of the target host:

```
--compute-resource host_address
```

• If the VCH is on a vCenter Server with more than one cluster, specify the name of the target cluster:

```
--compute-resource cluster_name
```

• If the VCH is in a specific resource pool on a standalone host that is managed by vCenter Server, specify the IPv4 address or FQDN of the target host and name of the resource pool:

- --compute-resource host\_name/resource\_pool\_name
- If the VCH is in a specific resource pool in a cluster, specify the names of the target cluster and the resource pool:
  - --compute-resource cluster\_name/resource\_pool\_name
- Wrap the resource names in single quotes (Linux or Mac OS) or double quotes (Windows) if they include spaces:
  - --compute-resource 'cluster name'/'resource pool name'

### --name

Short name: -n

The name of the VCH. This option is mandatory if the VCH has a name other than the default name, virtual-container-host, or if you do not use the <code>id</code> option. Specify --name with exactly the same value that you used when you ran <code>vic-machine create</code>. This option is not used by <code>vic-machine ls</code>.

```
--name vch_appliance_name
```

Wrap the appliance name in single quotes (Linux or Mac OS) or double quotes (Windows) if it includes spaces.

```
--name 'vch appliance name'
```

### --id

Short name: None

The vSphere Managed Object Reference, or moref, of the VCH, for example vm-100. You obtain the ID of a VCH by running  $vic_{machine\ 1s}$ . If you specify the id option, you do not need to specify the --name or  $--compute_{resource}$  options. This option is not used by  $vic_{machine\ create}$  or  $vic_{machine\ version}$ .

```
--id vch_id
```

### --timeout

Short name: none

The timeout period for performing operations on the VCH. Specify a value in the format xmYs if the default timeout is insufficient.

```
--timeout 5m0s
```

### List VCHs and Obtain Their IDs

You can obtain a list of the virtual container hosts (VCHs) that are running in vCenter Server or on an ESXi host by using the vic-machine 1s command.

The vic-machine 1s command lists VCHs with their IDs, names, and versions. The vic-machine 1s command does not include any options in addition to the common options described in Common vic-machine Options.

### **Prerequisites**

You have deployed a VCH. If you have not deployed a VCH, vic-machine 1s returns an empty list.

#### Procedure

- 1. On the system on which you run vic-machine, navigate to the directory that contains the vic-machine utility.
- 2. Run the vic-machine 1s command.
  - To obtain a list of all VCHs that are running on an ESXi host or vCenter Server instance, you must provide the address of the target ESXi host or vCenter Server.
  - You must specify the username and optionally the password, either in the --target option or separately in the --user and --password options.
  - If your vSphere environment uses untrusted, self-signed certificates, you must also specify the thumbprint of the vCenter Server instance or ESXi host in the --thumbprint option. To obtain the thumbprint of the vCenter Server or ESXi host certificate, run vic-machine without the specifying the --thumbprint option. The listing of the VCHs fails, but the resulting error message includes the required certificate thumbprint. You can copy the thumbprint from the error message and run vic-machine again, including the --thumbprint option.

**NOTE**: If you obtain the thumbprint by other means, use upper-case letters and colon delimitation in the thumbprint. Do not use space delimitation.

```
$ vic-machine-operating_system ls
--target esxi_host_address
--user root
--password esxi_host_password
--thumbprint certificate_thumbprint
```

```
$ vic-machine-operating_system ls
--target vcenter_server_username:password@vcenter_server_address
--thumbprint certificate_thumbprint
```

### Result

The vic-machine 1s command lists the VCHs that are running on the ESXi host or vCenter Server instance that you specified.

```
PATH
                                         UPGRADE STATUS
TD
                    NAME
                            VERSION
vm-101
           path
                    vch_1
                            version
                                         Upgradeable to version
vm-102
           path
                    vch_2 version
                                         Up to date
[\ldots]
                                         Up to date
vm-n
           path
                    vch_n
                            version
```

- The IDs are the vSphere Managed Object References, or morefs, for the VCH endpoint VMs. You can use VCH IDs when you run the vic-machine inspect, debug, upgrade, and delete commands. Using VCH IDs reduces the number of options that you need to specify when you run those commands.
- The PATH value depends on where the VCH is deployed:
  - · ESXi host that is not managed by vCenter Server:

```
/ha-datacenter/host/host_name/Resources
```

• Standalone host that is managed by vCenter Server:

/datacenter/host/host\_address/Resources

vCenter Server cluster:

/datacenter/host/cluster\_name/Resources

If VCHs are deployed in resource pools on hosts or clusters, the resource pool names appear after Resources in the path. You can use the information in PATH in the --compute-resource option of vic-machine commands.

- The version value shows the version of vic-machine that was used to create the VCH. It includes the release version, the build number and the short Git commit checksum, in the format vch\_version-vch\_build-git\_commit .
- The upgrade status reflects whether the current version of vic-machine that you are using is the same as the one that you used to deploy a VCH. If the version or build number of the VCH does not match that of vic-machine, upgrade status is Upgradeable to vch\_version-vch\_build-git\_commit.

### **Obtain Information About a VCH**

You can obtain information about a virtual container host (VCH) by using the vic-machine inspect command.

The vic-machine inspect command does not include any options in addition to the common options described in Common vic-machine Options.

### **Prerequisites**

You have deployed a VCH.

#### **Procedure**

- 1. On the system on which you run vic-machine, navigate to the directory that contains the vic-machine utility.
- 2. Run the vic-machine inspect command.

The following example includes the options required to obtain information about a named instance of a VCH from a simple vCenter Server environment.

- You must specify the username and optionally the password, either in the --target option or separately in the --user and --password options.
- If the VCH has a name other than the default name, virtual-container-host, you must specify the --name or --id option.
- If multiple compute resources exist in the datacenter, you must specify the --compute-resource or --id option.
- If your vSphere environment uses untrusted, self-signed certificates, you must also specify the thumbprint of the vCenter Server instance or ESXi host in the --thumbprint option. To obtain the thumbprint of the vCenter Server or ESXi host certificate, run vic-machine without the specifying the --thumbprint option. The inspection of the VCH fails, but the resulting error message includes the required certificate thumbprint. You can copy the thumbprint from the error message and run vic-machine again, including the --thumbprint option.

**NOTE**: If you obtain the thumbprint by other means, use upper-case letters and colon delimitation in the thumbprint. Do not use space delimitation.

```
$ vic-machine-operating_system inspect
--target vcenter_server_username:password@vcenter_server_address
--thumbprint certificate_thumbprint
--name vch_name
```

### Result

The vic-machine inspect command displays information about the VCH:

The VCH ID:

```
VCH ID: VirtualMachine:vm-101
```

The vSphere Managed Object Reference, or moref, of the VCH. You can use VCH ID when you run the vic-machine delete or debug commands. Using a VCH ID reduces the number of options that you need to specify when you run those commands.

• The version of the vic-machine utility and the version of the VCH that you are inspecting.

```
Installer version: vic_machine_version-vic_machine_build-git_commit
VCH version: vch_version-vch_build-git_commit
```

• The upgrade status of the VCH:

```
VCH upgrade status:
Installer has same version as VCH
```

No upgrade available with this installer version

If vic-machine inspect reports a difference between the version or build number of vic-machine and the version or build number of the VCH, the upgrade status is Upgrade available.

• The address of the VCH Admin portal for the VCH.

VCH Admin Portal: https://vch\_address:2378

• The address at which the VCH publishes ports.

vch\_address

- The Docker environment variables that container developers can use when connecting to this VCH.
  - VCH with full TLS authentication with trusted Certificate Authority certificates:

DOCKER\_TLS\_VERIFY=1

DOCKER\_CERT\_PATH=path\_to\_certificates

DOCKER\_HOST=vch\_address:2376

• VCH with TLS authentication with untrusted self-signed certificates:

 ${\tt DOCKER\_HOST=} vch\_address{:}2376$ 

VCH with no TLS authentication:

DOCKER\_HOST=vch\_address:2375

- The Docker command to use to connect to the Docker endpoint.
  - VCH with full TLS authentication with trusted Certificate Authority certificates:

docker -H vch\_address:2376 --tlsverify info

VCH with TLS authentication with untrusted self-signed certificates:

docker -H vch\_address:2376 --tls info

VCH with no TLS authentication:

docker -H vch\_address:2375 info

### **Delete a VCH**

You delete virtual container hosts (VCHs) by using the vic-machine delete command.

For descriptions of the options that vic-machine delete includes in addition to the Common vic-machine Options, see VCH Delete Options.

When you delete a VCH that uses TLS authentication with trusted Certificate Authority (CA) certificates, vic-machine delete does not delete the certificates or the certificate folder, even if you specify the --force option. Because vic-machine delete does not delete the certificates, you can delete VCHs and create new ones that reuse the same certificates. This is useful if you have already distributed the client certificates for VCHs that you need to recreate.

### **Prerequisites**

You have deployed a VCH that you no longer require.

#### **Procedure**

- 1. On the system on which you run vic-machine, navigate to the directory that contains the vic-machine utility.
- 2. Run the vic-machine delete command.

The following example includes the options required to remove a VCH from a simple vCenter Server environment.

- You must specify the username and optionally the password, either in the --target option or separately in the --user and --password options.
- If the VCH has a name other than the default name, virtual-container-host, you must specify the --name or --id option.
- If multiple compute resources exist in the datacenter, you must specify the --compute-resource or --id option.
- If your vSphere environment uses untrusted, self-signed certificates, you must also specify the thumbprint of the vCenter Server instance or ESXi host in the --thumbprint option. To obtain the thumbprint of the vCenter Server or ESXi host certificate, run vic-machine without the specifying the --thumbprint or --force options. The deletion of the VCH fails, but the resulting error message includes the required certificate thumbprint. You can copy the thumbprint from the error message and run vic-machine again, including the --thumbprint option.

**NOTE**: If you obtain the thumbprint by other means, use upper-case letters and colon delimitation in the thumbprint. Do not use space delimitation.

```
$ vic-machine-operating_system delete
--target vcenter_server_username:password@vcenter_server_address
--thumbprint certificate_thumbprint
--name vch_name
```

3. If the delete operation fails with a message about container VMs that are powered on, run docker stop on the containers and run vic-machine delete. Alternatively, run vic-machine delete with the --force option.

**CAUTION** Running vic-machine delete with the --force option removes all running container VMs that the VCH manages, as well as any associated volumes and volume stores. It is not recommended to use the --force option to remove running containers.

If your vSphere environment uses untrusted, self-signed certificates, running vic-machine delete with the --force option allows you to omit the --thumbprint option.

```
$ vic-machine-operating_system delete
--target vcenter_server_username:password@vcenter_server_address
--name vch_name
--force
```

### What to Do Next

The vic-machine delete command does not modify the firewall. If you do not need to deploy or run further VCHs on the ESXi host
or cluster, run vic-machine update firewalldeny to close port 2377 on the host or hosts.

## **VCH Delete Options**

The command line utility for vSphere Integrated Containers Engine, vic-machine, provides a delete command that allows you to cleanly remove virtual container hosts (VCHs).

The vic-machine delete command includes one option in addition to the common options described in Common vic-machine Options.

### --force

Short name: -f

Forces vic-machine delete to ignore warnings and continue with the deletion of a VCH. Any running container VMs and any volume stores associated with the VCH are deleted. Errors such as an incorrect compute resource still cause the deletion to fail.

- If you do not specify --force and the VCH contains running container VMs, the deletion fails with a warning.
- If you do not specify --force and the VCH has volume stores, the deletion of the VCH succeeds without deleting the volume stores. The list of volume stores appears in the vic-machine delete success message for reference and optional manual removal.

If your vSphere environment uses untrusted, self-signed certificates, you can use the --force option to delete a VCH without providing the thumbprint of the vCenter Server or ESXi host in the --thumbprint option.

--force

# **Debugging the VCH**

By default, all shell access to the virtual container host (VCH) endpoint VM is disabled. Login shells for all users are set to <code>/bin/false</code>. The <code>vic-machine</code> utility provides a <code>debug</code> command that allows you to enable shell access to the VCH endpoint VM, either by using the VM console or via SSH.

**NOTE**: Do not confuse the vic-machine debug command with the vic-machine create --debug option. The vic-machine debug command allows you to log into and debug a VCH endpoint VM that you have already deployed. The vic-machine create --debug option deploys a new VCH that has increased levels of logging and other modifications, to allow you to debug the environment in which you deploy VCHs. For information about the vic-machine create --debug option, see the section on --debug in VCH Deployment Options.

- Enable Shell Access to the VCH Endpoint VM
- Authorize SSH Access to the VCH Endpoint VM
- VCH Debug Options

# Enable shell access to the VCH Endpoint VM

You can use the vic-machine debug command to enable shell access to a virtual container host (VCH) endpoint VM by setting a root password on the VM. Setting a root password enables access to the VCH endpoint VM via the VM console only. If you require SSH access to the VCH endoint VM, rather than just shell access, see Authorize SSH Access to the VCH Endpoint VM.

**IMPORTANT**: Any changes that you make to a VCH by using vic-machine debug are non-persistent and are discarded if the VCH endpoint VM reboots.

For descriptions of the options that vic-machine debug includes in addition to the Common vic-machine Options, and for information about password expiry periods, see VCH Debug Options.

### **Prerequisites**

You deployed a VCH.

### **Procedure**

- 1. On the system on which you run vic-machine, navigate to the directory that contains the vic-machine utility.
- 2. Run the vic-machine debug command.
  - Specify the vSphere target and its credentials, either in the --target option or separately in the --user and --password options.

The credentials that you provide must have the following privilege on the endpoint VM:

```
Virtual machine.Guest Operations.Guest Operation Program Execution
```

- Specify the ID or name of the VCH to debug.
- Potentially provide the thumbprint of the vCenter Server or ESXi host certificate. Use upper-case letters and colon delimitation in the thumbprint. Do not use space delimitation.
- Provide a password for the root user on the VCH endpoint VM by specifying the --rootpw option. Wrap the password in single quotes (Linux or Mac OS) or double quotes (Windows) if it includes shell characters such as \$ , ! or % .

```
$ vic-machine-operating_system debug
--target vcenter_server_or_esxi_host_address
--user vcenter_server_or_esxi_host_username
--password vcenter_server_or_esxi_host_password
--id vch_id
--thumbprint certificate_thumbprint
--rootpw 'new_p@ssword'
```

### Result

The output of the vic-machine debug command includes confirmation that SSH access is enabled:

```
### Configuring VCH for debug ####
[...]
SSH to appliance:
ssh root@vch_address
[...]
Completed successfully
```

### Authorize SSH Access to the VCH Endpoint VM

You can use the vic-machine debug command to enable shell access to a virtual container host (VCH) endpoint VM by setting a root password on the VM. Setting a root password enables access to the VCH endpoint VM via the VM console. You can also use debug to authorize SSH access to the VCH endpoint VM. You can optionally upload a key file for public key authentication when accessing the endpoint VM by using SSH.

**IMPORTANT**: Any changes that you make to a VCH by using vic-machine debug are non-persistent and are discarded if the VCH endpoint VM reboots.

For descriptions of the options that vic-machine debug includes in addition to the Common vic-machine Options, and for information about password expiry periods, see VCH Debug Options.

### **Prerequisites**

You deployed a VCH.

#### **Procedure**

- 1. On the system on which you run vic-machine, navigate to the directory that contains the vic-machine utility.
- 2. Run the vic-machine debug command.
  - Specify the vSphere target and its credentials, either in the --target option or separately in the --user and --password options.

The credentials that you provide must have the following privilege on the endpoint VM:

```
Virtual machine.Guest Operations.Guest Operation Program Execution
```

- Specify the ID or name of the VCH to debug.
- Potentially provide the thumbprint of the vCenter Server or ESXi host certificate. Use upper-case letters and colon delimitation in the thumbprint. Do not use space delimitation.
- Specify the --rootpw option. Wrap the password in single quotes (Linux or Mac OS) or double quotes (Windows) if it includes shell characters such as \$ , ! or % .
- Authorize SSH access by specifying --enable-ssh .
- Optionally, specify the --authorized-key option to upload a public key file to /root/.ssh/authorized\_keys folder in the endpoint VM. Include the name of the \*.pub file in the path.

```
$ vic-machine-operating_system debug
--target vcenter_server_or_esxi_host_address
--user vcenter_server_or_esxi_host_username
--password vcenter_server_or_esxi_host_password
--id vch_id
--thumbprint certificate_thumbprint
--enable-ssh
--rootpw 'new_p@ssword'
--authorized-key path_to_public_key_file/key_file.pub
```

### Result

The output of the vic-machine debug command includes confirmation that SSH access is enabled:

```
### Configuring VCH for debug ####
[...]
SSH to appliance:
ssh root@vch_address
[...]
Completed successfully
```

### **VCH Debug Options**

The command line utility for vSphere Integrated Containers Engine, vic-machine, provides a debug command that allows you to enable VM console or SSH access to the virtual container host (VCH) endpoint VM, set a password for the root user account, and upload a key file for automatic public key authentication.

If you authorize SSH access to the VCH endpoint VM, you can edit system configuration files that you cannot edit by running vic-machine commands.

IMPORTANT: If you set a password or enable shell access on a VCH endpoint VM, these changes do not persist if you reboot the VM. You must run vic-machine debug to reenable access and reset the password each time that the VCH endpoint VM reboots

The vic-machine debug command includes the following options in addition to the common options described in Common vic-machine Options.

### --rootpw

Short name: --pw

Set a new password for the root user account on the VCH endpoint VM. Setting a password on the VCH allows you to access the VCH by using the VM console. If you also set the --enable-ssh option, you can use this password to connect to the VCH by using SSH.

When you use the password to log in to a VCH, you see the message that the password will expire in 0 days. To obtain a longer expiration period, use the Linux password command in the endpoint VM to set a new password. If the password expires, the VCH does not revert to the default security configuration from before you ran vic-machine debug. If you attempt to log in using an interactive password via the terminal or SSH, you see a prompt to change the password. If you are using an SSH key, you cannot log in until you either change the password or run vic-machine debug again.

Wrap the password in single quotes (Linux or Mac OS) or double quotes (Windows) if it includes shell characters such as \$ , . .

```
--rootpw 'new_p@ssword'
```

### --enable-ssh

Short name: --ssh

Enable an SSH server in the VCH endpoint VM. The sshd service runs until the VCH endpoint VM reboots. The --enable-ssh takes no arguments.

If you have already enabled SSH access but the password that you set has expired, and you then rerun --enable-ssh without specifying --rootpw, the password expiry is set to 1 day in the future and the password is preserved.

```
--enable-ssh
```

### --authorized-key

Short name: --key

Upload a public key file to <code>/root/.ssh/authorized\_keys</code> to enable SSH key authentication for the <code>root</code> user. Include the name of the \*.pub file in the path.

```
--authorized-key path_to_public_key_file.pub
```

#### Access the VCH Administration Portal

vSphere Integrated Containers Engine provides a Web-based administration portal for virtual container hosts (VCHs), called VCH Admin.

If you deployed the VCH with --no-tls or --no-tlsverify, you can only log in to VCH Admin by specifying the username and password of the ESXi host or vCenter Server on which you deployed the VCH. If you deployed the VCH with client and server authentication by using --tls-cname or by specifying a static IP address on the client network, you can use the generated \*.pfx certificate to authenticate with the VCH Admin portal. For information about using the \*.pfx certificate to log into VCH admin, see Browser-Based Certificate Login and Command Line Certificate Login.

#### Prerequisites

- You deployed a VCH.
- Obtain the address of the VCH:
  - Copy the address from the output of vic-machine create or vic-machine inspect .
  - If you deployed the VCH to vCenter Server, copy the address from the Summary tab for the endpoint VM in the vSphere
  - If you deployed the VCH to an ESXi host, copy the address from the **Summary** tab for the endpoint VM in the desktop vSphere Client.

#### **Procedure**

1. Go to https://vch\_address:2378.

If prompted about an insecure or not private connection, click Advanced and follow the prompts to proceed to the portal.

2. Enter the username and password for the vCenter Server instance or ESXi host.

#### Result

The VCH Admin portal displays information about the VCH and the environment in which is running:

- Status information about the VCH, registry and Internet connections, firewall configuration, and license. For information about these statuses and how to remedy error states, see the VCH Status Reference.
- The address of the Docker endpoint.
- The system time of the VCH. This is useful to know because clock skews between VCHs and client systems can cause TLS authentication to fail. For information about clock skews, see Connections Fail with Certificate Errors when Using Full TLS Authentication with Trusted Certificates.
- The remaining capacity of the datastore that you designated as the image store. If the VCH is unable to connect to vSphere, the datastore information is not displayed.
- Live logs and log bundles for different aspects of the VCH. For information about the logs, see Access vSphere Integrated Containers Engine Log Bundles.

## **Browser-Based Certificate Login**

If you deployed the VCH with client and server authentication by using --tls-cname or by specifying a static IP address on the client network, you can use browser-based certificate authentication to access the VCH Admin Portal. In this way, you do not need to provide the vSphere credentials each time that you log in to VCH Admin.

#### **Prerequisites**

- You deployed a VCH with --tls-cname or a static IP address for the VCH on the client network.
- Use Firefox. Currently, this feature is only supported with Firefox.
- Locate the file named cert.pfx on the system on which you ran vic-machine create . The cert.pfx is located in either of the following locations:
  - In the folder with the same name as the VCH, in the directory from which you ran vic-machine create .
  - In a folder that you specified in the vic-machine create --cert-path option.

#### **Procedure**

- 1. In Firefox, select Tools > Options and select Advanced.
- 2. Click View Certificates .
- 3. Click Import .
- 4. Browse to the cert.pfx file and click Open .
- 5. Click ok .

Do not enter a password when prompted.

#### Result

You see a message stating that the certificate was successfully installed. With the VCH certificate installed in your browser, you can navigate to https://vch\_address:2378/ or to one of the log pages without having to enter the vSphere credentials.

## **Command Line Certificate Login**

You can use certificate-based authentication with tools such as curl or wget to access the VCH Admin log server.

#### With TLS Client Authentication

-If you deployed the VCH with client authentication by using --tls-cname or by specifying a static IP address on the client network, you can point curl to the cert.pem and key.pem files for the VCH. The following example authenticates connections to the port-layer.log file.

```
curl https://vch_address:2378/logs/port-layer.log
--key ./cert_folder/key.pem
--certificate ./cert_folder/cert.pem
```

NOTE: If your certificates are self-signed, you might also need to specify the curl -k flag.

In the example above, *cert\_folder* is either of the following locations:

- The folder with the same name as the VCH, in the directory from which you ran vic-machine create .
- Afolder that you specified in the vic-machine create --cert-path option.

#### Without Client Authentication

If you deployed the VCH without client authentication by using either of --no-tls or --no-tlsverify, you can use curl to access the logs but you must first authenticate connections to VCH Admin by using the vSphere username and password.

1. Log in to VCH Admin to gather an authentication cookie for subsequent access:

```
curl -sk https://vch_address:2378/authentication
-XPOST -F username=vsphere_username
-F password=vsphere_password
-D cookies_file
```

2. Use the cookie from Step 1 in a  $\ensuremath{\text{curl}}$  command to access the logs.

```
curl -sk https://vch_address:2378/logs/port-layer.log
-b cookies_file
```

## **VCH Admin Status Reference**

The Web-based administration portal for virtual container hosts (VCHs), VCH Admin, presents status information about a VCH.

If the vSphere environment in which you are deploying a VCH does not meet the requirements, the deployment does not succeed. However, a successfully deployed VCH can stop functioning if the vSphere environment changes after the deployment. If environment changes adversely affect the VCH, the status of the affected component changes from green to yellow.

## **Virtual Container Host (VCH)**

VCH Admin checks the status of the processes that the VCH runs:

- The port layer server, that presents an API of low-level container primitive operations, and implements those container operations via the vSphere APIs.
- VCH Admin server, that runs the VCH Admin portal.
- The vSphere Integrated Containers Engine initialization service and watchdog service for the other components.
- The Docker engine server, that exposes the Docker API and semantics, translating those composite operations into port layer primitives.

#### **Error**

- The VCH status is yellow.
- The VCH status is yellow and an error message informs you that the VCH cannot connect to vSphere.

#### Cause

- One or more of the VCH processes is not running correctly, or the VCH is unable to connect to vSphere.
- The management network connection is down and the VCH endpoint VM cannot connect to vSphere.

#### Solution

- 1. (Optional) If you see the error that the VCH is unable to connect to vSphere, check the VCH management network.
- 2. In the VCH Admin portal for the VCH, click the link for the VCH Admin Server log.
- 3. Search the log for references to the different VCH processes.

The different processes are identified in the log by the following names:

- o port-layer-server
- o vicadmin
- o vic-init
- o docker-engine-server
- 4. Identify the process or processes that are not running correctly and attempt to remediate the issues as required.

## **Registry and Internet Connectivity**

VCH Admin checks connectivity on the public network by attempting to connect from the VCH to docker.io and google.com. VCH Admin only checks the public network connection. It does not check other networks, for example the bridge, management, client, or container networks.

#### Error

The Registry and Internet Connectivity status is yellow.

#### Cause

The public network connection is down.

#### **Solution**

Check the **VCH Admin Server** log for references to network issues. Use the vSphere Web Client to remediate the management network issues as required.

#### **Firewall**

VCH Admin checks that the firewall is correctly configured on an ESXi host on which the VCH is running. If the VCH is running in a cluster, VCH Admin checks the firewall configuration on all of the hosts in the cluster.

#### **Error**

- The Firewall status is unavailable.
- The Firewall status is yellow and shows the error Firewall must permit 2377/tcp outbound to use VIC .

#### Cause

- The management network connection is down and the VCH endpoint VM cannot connect to vSphere.
- The firewall on the ESXi host on which the VCH is running no longer allows outbound connections on port 2377.
  - The firewall was switched off when the VCH was deployed. The firewall has been switched on since the deployment of the VCH.
  - Afirewall ruleset was applied manually to the ESXi host to allow outbound connections on port 2377. The ESXi host has been rebooted since the deployment of the VCH. Firewall rulesets are not retained when an ESXi host reboots.

#### Solution

- If the Firewall status is unavailable:
  - Check the VCH Admin Server log for references to network issues.
  - Use the vSphere Web Client to remediate the management network issues as required.
- If you see the error about port 2377, run the vic-machine update firewall command on the ESXi host or hosts to allow outbound connections on port 2377. For information about how to run vic-machine update firewall, see Open the Required Ports on ESXi Hosts.

#### License

VCH Admin checks that the ESXi hosts on which you deploy VCHs have the appropriate licenses.

#### **Error**

- ullet The **License** status is yellow and shows the error License does not meet minimum requirements to use VIC .
- The License status is unavailable.

#### Cause

- The license for the ESXi host or for one or more of the hosts in a vCenter Server cluster on which the VCH is deployed has been removed, downgraded, or has expired since the deployment of the VCH.
- The management network is down, or the VCH endpoint VM is unable to connect to vSphere.

#### **Solution**

- If the license does not meet the requirements:
  - If the VCH is running on an ESXi host that is not managed by vCenter Server, replace the ESXi host license with a valid vSphere Enterprise license.

- If the VCH is running on a standalone ESXi host in vCenter Server, replace the ESXi host license with a valid vSphere Enterprise Plus license.
- If the VCH is running in a vCenter Server cluster, check that all of the hosts in the cluster have a valid vSphere Enterprise Plus license, and replace any licenses that have been removed, downgraded, or have expired.
- If the **License** status is unavailable:
  - Check the VCH Admin Server log for references to network issues.
  - Use the vSphere Web Client to remediate the management network issues as required.

## **Access vSphere Integrated Containers Engine Log Bundles**

vSphere Integrated Containers Engine provides log bundles that you can download from the VCH Admin portal for a virtual container host (VCH).

You access the VCH Admin Portal at https://vch\_address:2378. For more information about the VCH Admin portal, see Access the VCH Administration Portal.

To aid in troubleshooting errors, you can download different log bundles:

- Log Bundle contains logs that relate specifically to the VCH that you created.
- Log Bundle with container logs contains the logs for the VCH and also includes the logs regarding the containers that the VCH manages.

**NOTE**: If the VCH is unable to connect to vSphere, logs that require a vSphere connection are disabled, and you see an error message. For information about accessing logs manually, see Collecting Logs Manually below.

- Live logs (tail files) allow you to view the current status of how components are running.
  - **Docker Personality** is the interface to Docker. When configured with client certificate security, it reports unauthorized access attempts to the Docker server web page.
  - o Port Layer Service is the interface to vSphere.
  - o Initialization & watchdog reports:
    - Network configuration
    - Component launch status for the other components
    - Reports component failures and restart counts

At higher debug levels, the component output is duplicated in the log files for those components, so init.log includes a superset of the log data.

**Note:** This log file is duplicated on the datastore in a file in the endpoint VM folder named tether.debug , to allow the debugging of early stage initialization and network configuration issues.

Admin Server includes logs for the VCH admin server, may contain processes that failed, and network issues. When
configured with client certificate security, it reports unauthorized access attempts to the admin server web page.

Live logs can help you to see information about current commands and changes as you make them. For example, when you are troubleshooting an issue, you can see whether your command worked or failed by looking at the live logs.

You can share the non-live version of the logs with administrators or VMware Support to help you to resolve issues.

Logs also include the vic-machine commands used during VCH deployment to help you resolve issues.

## **Collecting Logs Manually**

If the VCH Admin portal is offline, use vic-machine debug to enable SSH on the VCH and use scp -r to capture the logs from /var/log/vic/.

## **Setting the Log Size Cap**

The log size cap is set at 20MB. If the size exceeds 20 MB, vSphere Integrated Containers Engine compresses the files and saves a history of the last two rotations. The following files are rotated:

/var/log/vic/port-layer.log
/var/log/vic/init.log
/var/log/vic/docker-personality.log
/var/log/vic/vicadmin.log

vSphere Integrated Containers Engine logs any errors that occur during log rotation.

## **Troubleshooting vSphere Integrated Containers**

This section provides solutions for common problems that you might encounter during operation.

- VCH Deployment Times Out
- VCH Deployment Fails with a Certificate Verification Error
- VCH Deployment Fails with Missing Common Name Error Even When TLS Options Are Specified Correctly
- VCH Deployment Fails with Firewall Validation Error
- VCH Deployment Fails with Certificate cname Mismatch
- VCH Deployment Fails with Docker API Endpoint Check Failed Error
- VCH Deployment Fails with Error About No Single Host Being Able to Access All Datastores
- Plug-In Does Not Appear
- Deleting or Inspecting a VCH Fails with an Error
- Connections Fail with Certificate Errors when Using Full TLS Authentication with Trusted Certificates

## **VCH Deployment Times Out**

When you use vic-machine create to deploy a virtual container host (VCH), the operation times out.

#### **Problem**

Deployment fails with a timeout error that states that the context deadline has been exceeded.

```
Failed to power on appliance context deadline exceeded. Exiting... vic-machine-linux failed: Create timed out: if slow connection, increase timeout with --timeout
```

#### Causes

This error can have different causes:

- The connection between the system on which you are running vic-machine and vCenter Server is slow. The upload of the ISO files exceeds the default 3 minute timeout.
- The upload of the ISO files succeeds but the VCH fails to obtain an IP address.
- The VCH obtained an IP address, but the VCH service does not start or the VCH cannot connect to the Docker API.

#### **Solutions**

1. Set the vic-machine --timeout option to allow more time for the ISOs to upload.

```
For example, set --timeout 10m or --timeout 20m.
```

- 2. If the ISO upload succeeds with a longer timeout period but the operation still times out, check the DHCP service to make sure than an IP address is available for the VCH.
- 3. If the DHCP service is working and the operation still times out, see VCH Deployment Fails with Docker API Endpoint Check Failed Error

## VCH Deployment Fails with a Certificate Verification Error

When you use vic-machine create to deploy a virtual container host (VCH), the deployment fails with a certificate verification error, noting that it failed to create validator.

#### **Problem**

Deployment of the VCH fails during the validation of the configuration that you provided:

```
Failed to verify certificate for target=vcenter_server_or_esxi_host
(thumbprint=vc_or_esxi_cert_thumbprint)
Create cannot continue: failed to create validator
vic-machine-platform.exe failed: x509: certificate signed by unknown authority
```

#### Cause

The certificate on the vCenter Server or ESXi host that you specified in the --target option cannot be validated on the client system.

#### Solution

If the certificate was signed by a certificate authority (CA), add that CA to the trusted roots for the client system.

If the CAshould not be generally trusted, or the certificate is self-signed:

- If the server is trusted and you did not specify the certificate thumbprint when you ran vic-machine create, specify the --thumbprint option, using the thumbprint from the error message.
- If the thumbprint that you specified in --thumbprint does not match the server certificate reported in the error message:
  - 1. Remove the thumbprint from the vic-machine create command. **WARNING**: Athumbprint mismatch could mean the server you have connected to is not the intended target and might have be spoofed.
  - 2. Validate that the change in server certificate is legitimate
  - 3. Re-run vic-machine create, specifying the new thumbprint in the --thumbprint option.

NOTE: Use upper-case letters and colon delimitation in the thumbprint. Do not use space delimitation.

## VCH Deployment Fails with Missing Common Name Error Even When TLS Options Are Specified Correctly

If you deploy a virtual container host (VCH) and you have specified one of the vic-machine create --tls-cname, --no-tlsverify, or -no-tls options, or you set a static IP address on the client network, the deployment fails with an error about the certificate Common Name being missing.

#### **Problem**

Deployment fails during the validation of the configuration that you provided, even if you did specify a TLS option or you set a static IP address on the client network. For example:

If you include a TLS option at the beginning of the vic-machine create command rather than the end, you see the following error:

#### Cause

String values that you provided for certain options contain spaces or special characters that you did not escape with quotations marks. The vic-machine create input validator validates the arguments that you provide only as far as the argument that includes the space or special character. If you specify the TLS option before the argument with the space or special character, vic-machine create throws the correct error message. However, if you specify the TLS option after the argument that includes the space or special character, the vic-machine create validator stops before it reaches the TLS option, and so throws the error about the missing Common Name.

#### Solution

Wrap any arguments that contain spaces or special characters in single quotation marks (') on Mac OS and Linux and in double quotation marks (") on Windows.

Option arguments that might require quotation marks include the following:

- User names and passwords in --target , or in --user and --password
- Datacenter names in --target
- VCH names in --name
- Datastore names and paths in --image-store and --volume-store
- Network and port group names in all networking options.
- Cluster and resource pool names in --compute-resource
- Folder names in the paths for --cert-path , --cert , --key , --appliance-iso , and --bootstrap-iso

For information about when to use quotation marks for different options, see the descriptions of those options in VCH Deployment Options.

## VCH Deployment Fails with Firewall Validation Error

When you use vic-machine create to deploy a virtual container host (VCH), deployment fails because firewall port 2377 is not open on the target ESXi host or hosts.

#### **Problem**

Deployment fails with a firewall error during the validation phase:

Firewall must permit dst 2377/tcp outbound to the VCH management interface

#### Cause

ESXi hosts communicate with the VCHs through port 2377 via Serial Over LAN. For deployment of a VCH to succeed, port 2377 must be open for outgoing connections on all ESXi hosts before you run vic-machine create. Opening port 2377 for outgoing connections on ESXi hosts opens port 2377 for inbound connections on the VCHs.

#### **Solution**

The vic-machine utility includes an update firewall command, that you can use to modify the firewall on the ESXi host or the ESXi hosts in a cluster. For information about how to use the update firewall command, see Open the Required Ports on ESXi Hosts.

## VCH Deployment Fails with Certificate cname Mismatch

When you use vic-machine create to deploy a virtual container host (VCH), the deployment fails with an error about the certificate cname value.

#### **Problem**

Deployment fails during the validation of the configuration that you provided:

Provided cname does not match that in existing server certificate: cname
Unable to load certificates: cname option doesn't match existing server certificate
in certificate path path\_to\_certificate

#### Cause

vic-machine create attempts to re-use certificates that it finds in --cert-path. The default value of --cert-path derives from the value that you specify in --name. If you are deploying a VCH from the same location and with the same name as a previous VCH, vic-machine create reuses the old certificates. This behavior is intentional, to allow you to easily redeploy a VCH without requiring you to re-issue client certificates to users.

Before reusing the existing certificates, vic-machine confirms that the existing certificate is valid given the options supplied for the new deployment. The options that influence this in order of priority are:

- --tls-cname if specified, or
- --client-ip-address , Or
- --public-ip-address if the client and public network roles share an interface.

The error message means that the existing certificate has a Common Name attribute that differs from the value derived from the options detailed above.

#### Solution

- To reuse the certificates directly, change --tls-cname, --client-ip-address, or --public-ip-address to match the Common Name in the existing certificate.
- If you want to reuse the Certificate Authority so that client certificates remain valid, but you need to provide a different IP address:
  - 1. Manually generate the server certificates by using openss1, signing them with the existing CA.
  - 2. Use the --cert and --key options to pass the newly generated certificates to vic-machine create.
- If you do not want to reuse the certificates, choose one of the following options:
  - Change the location from which you run vic-machine. This alters the default --cert-path.
  - Change the value of --name . This alters the default --cert-path .
  - Specify --cert-path explicitly.
  - Delete the existing certificates from --cert-path

## VCH Deployment Fails with Docker API Endpoint Check Failed Error

When you use vic-machine create to deploy a virtual container host (VCH), deployment fails because vic-machine cannot contact the Docker API endpoint.

#### **Problem**

Deployment fails with with the error:

```
Docker API endpoint check failed:

API may be slow to start - try to connect to API after a few minutes:

Run docker -H 192.168.218.160:2376 --tls info

If command succeeds, VCH is started. If command fails, VCH failed to install - see documentation for troubleshooting.
```

#### Cause

During deployment, vic-machine checks that the endpoint VM is reachable from Docker clients. If this check fails, vic-machine create fails with an error. This error can be caused by the Docker API being slow to start or because it has failed to start.

#### Solution

The solution to choose depends on whether the API is slow to start or whether it failed to start.

#### **Docker API is Slow to Start**

Wait for a few minutes, then run the docker info command to test the responsiveness of the Docker API.

If docker info succeeds, it shows information about the VCH, including confirmation that the storage driver is vSphere Integrated Containers.

```
Storage Driver: vSphere Integrated Containers version Backend Engine
```

This output means that the VCH is running correctly and can now accept Docker commands.

If docker info times out, it means that the Docker API did not start.

#### **Docker API Did Not Start**

If the Docker API was not responsive when you ran docker info, download the VCH log bundle and examine the logs to determine why the deployment failed. Collecting the vSphere log bundle might also be useful for troubleshooting.

- For information about how to download VCH logs by using the VCH Admin Portal, see Access the VCH Admin Portal in *vSphere Integrated Containers Engine Administration*.
- For information about how to collect VCH logs manually, see Access vSphere Integrated Containers Engine Log Bundles in vSphere Integrated Containers Engine Administration.

# VCH Deployment with a Shared NFS Datastore Fails with an Error About No Single Host Being Able to Access All Datastores

Deploying a virtual container host (VCH) to a cluster, and specifying a shared NFS datastore as the image store, fails with the error No single host can access all of the requested datastores.

#### **Problem**

This error occurs even if all of the hosts in the cluster do appear to have access to the shared NFS datastore.

#### Cause

VCHs require datastores to be writable. The shared NFS datastore is possibly mounted as read-only.

#### Solution

To see whether a datastore is writable or read-only, consult mountInfo in the Managed Object Browser (MOB) of the vCenter Server instance to which you are deploying the VCH.

- 1. Go to https://vcenter\_server\_address/mob/.
- 2. Click content.
- 3. Click group-xx (Datacenters) in the rootFolder row.
- 4. Click the managed object reference (MoRef) of your datacenter in the childEntity row.
- 5. Click the MoRef of the shared NFS datastore in the datastore row.
- 6. Click the DatastoreHostMount link in the host row.
- 7. Click mountInfo and check the accessMode value.
- 8. If the accessMode value is readonly, unmount the datastore from vCenter Server and remount it with readWrite permissions.

## vSphere Integrated Containers Plug-In Does Not Appear

After you have installed either of the HTML5 or Flex-based plug-ins for vSphere Integrated Containers, the plug-ins do not appear in the HTML5 vSphere Client or the Flex-based vSphere Web Client.

#### **Problem**

The UI plug-in installer reported success, but the plug-ins do not appear in the client. Logging out of the client and logging back in again does not resolve the issue.

#### Cause

- If a previous attempt at installing the vSphere Integrated Containers plug-ins failed, the failed installation state is retained in the client cache.
- You installed a new version of the vSphere Integrated Containers plug-ins that has the same version number as the previous version, for example a hot patch.

#### Solution

Restart the client service.

#### Restart the HTML5 Client on vCenter Server on Windows

- 1. Log into the Windows system on which vCenter Server is running.
- 2. Open a command prompt as Administrator.
- 3. Use the service-control command-line utility to stop and then restart the vSphere Client service.

"C:\Program Files\VMware\vCenter Server\bin\service-control" --stop vsphere-ui

"C:\Program Files\VMware\vCenter Server\bin\service-control" --start vsphere-ui

#### Restart the Flex Client on vCenter Server on Windows

- 1. Log into the Windows system on which vCenter Server is running.
- 2. Open a command prompt as Administrator.
- ${\it 3. Use the } \ \ {\it service-control} \ \ command-line \ \ utility \ to \ stop \ and \ then \ restart \ the \ vSphere \ Client \ service.$

"C:\Program Files\VMware\vCenter Server\bin\service-control" --stop vspherewebclientsvc

"C:\Program Files\VMware\vCenter Server\bin\service-control" --start vspherewebclientsvc

#### Restart the HTML5 Client on a vCenter Server Appliance

- 1. Use SSH to log in to the vCenter Server Appliance as root.
- 2. Use the service-control command-line utility to stop the vSphere Client service.

service-control --stop vsphere-ui

3. Restart the vSphere Client service.

service-control --start vsphere-ui

## Restart the Flex Client on a vCenter Server Appliance

- 1. Use SSH to log in to the vCenter Server Appliance as root .
- 2. Use the service-control command-line utility to stop the vSphere Web Client service.

service vsphere-client stop

3. Restart the vSphere Web Client service.

service-control --start vsphere-client

## Deleting or Inspecting a VCH Fails with a Not a VCH or Resource Pool Not Found Error

When you use vic-machine delete or vic-machine inspect to delete or inspect a virtual container host (VCH) and you specify the address of an ESXi host in the target option, the operation fails with "an error stating that the target is not a VCH or that the resource pool cannot be found".

#### **Problem**

Deleting or inspecting a VCH fails with one of the following error messages:

```
### Inspecting VCH ####
Not a VCH
Failed to get Virtual Container Host vch_name
Not a VCH
-----
vic-machine-os failed: inspect failed
```

```
### Removing VCH ####
Not a VCH
Failed to get Virtual Container Host vch_name
Not a VCH
-----
vic-machine-os failed: delete failed
```

#### Cause

You set the target option to the address of an ESXi host that is managed by a vCenter Server instance. If there are multiple ESXi hosts in a cluster, the error that you see depends on the host that you specify in the target option.

- If you set the target option to the ESXi host on which the VCH is running, you see the error Not a VCH, Failed to get Virtual Container Host .
- If you set the target option to an ESXi host in the cluster that is not the one on which the VCH is running, you see the error

  Not a VCH, Failed to get VCH resource pool.

## Solution

1. Run vic-machine 1s with the target option set to the same ESXi host.

The vic-machine 1s operation fails but informs you of the address of the vCenter Server instance that manages the ESXi host.

2. Run vic-machine delete or vic-machine inspect again, setting the target option to the address of the vCenter Server instance that was returned by vic-machine 1s.

## Connections Fail with Certificate Errors when Using Full TLS Authentication with Trusted Certificates

Connections to a virtual container host (VCH) that uses full TLS authentication with trusted Certificate Authority (CA) certificates fail with certificate errors.

#### **Problem**

• vic-machine operations on a VCH result in a "bad certificate" error:

```
Connection failed with TLS error "bad certificate" check for clock skew on the host Collecting host-227 hostd.log vic-machine-windows.exe failed: tls: bad certificate
```

NOTE: vic-machine tolerates a 1 day skew. Askew of 1 day might result in a different certificate error than time skew.

- Connections to the VCH Admin portal for the VCH fail with an ERR\_CERT\_DATE\_INVALID error.
- Connections to the VCH from Docker clients fail with a bad certificate error.

#### Cause

There is potentially a clock skew between the VCH and the system from which you are connecting to the VCH.

#### Solution

- 1. Go to the VCH Admin portal for the VCH at https://vch\_address:2378 and check the System Time under VCH Info.
- 2. If the system time of the VCH is wrong, run vic-machine debug to enable SSH access to the VCH.

For information about enabling SSH on a VCH, see Authorize SSH Access to the VCH Endpoint VM.

- 3. Connect to the VCH endpoit VM by using SSH.
- 4. Use the date --set Linux command to set the system clock to the correct date and time.

The two most common date formats are the following:

- Unix Time Stamp: date --set='@1480969133'
- O YYYYMMDD HH:MM format: date --set="20161205 14:31"

To prevent this issue recurring on VCHs that you deploy in the future, verify that the host time is correct on the ESXi host on which you deploy VCHs. For information about verifying time synchronization on ESXi hosts, see VMware KB 1003736.

## vSphere Integrated Containers Security Reference

The Security Reference provides information to allow you to secure your vSphere Integrated Containers implementation.

- Network Security
- External Interfaces, Ports, and Services
- Service Accounts and Privileges
- Apply Security Updates and Patches
- Security Related Log Messages
- Sensitive Data

### **Network Security**

VMware highly recommends using a secure management network for vSphere Integrated Containers Engine. The container VMs communicate with the endpoint VM over the management network when an interactive shell is required. While the communication is encrypted, the public keys are not validated, which leaves scope for man-in-the-middle attacks. This connection is only used for the interactive console when enabled (stdin/out/err), and not for any other purpose.

### **External Interfaces, Ports, and Services**

The following ports must be open on the VCH appliance.

#### **Endpoint VM**

#### Client interface:

- 2375 insecure port for Docker API access if deployed with --no-tls
- 2376 for TLS secured port for Docker API access
- 22 SSH when enabled with vic-machine debug
- 2378 VIC admin server health and log access (HTTPS)
- 6060 pprof debug data when enabled with --debug levels

#### Management interface:

- 2377 incoming connections from container VMs
- 443 outgoing connections established to vSphere target
- 443 outgoing connections established to ESX hosts

#### Bridge interface:

• 53 DNS server for container name resolution

#### Public interface:

• any port not listed as used elsewhere can be forwarded to a container VM

#### **Container VM**

- 6060 pprof debug data when enabled with --debug levels
- vSphere Integrated Containers Engine does not use ports when not configured for debug

## **Service Accounts and Privileges**

vSphere Integrated Containers Engine does not create service accounts and does not assign privileges. The --ops-user and -ops-password options allow a VCH to operate with less-privileged credentials than those that are required for deploying a new
VCH. For information about the --ops-user option and the permissions that it requires, see the descriptions of --ops-user in

VCH Deployment Options and Advanced Examples of Deploying a VCH, and the section Use Different User Accounts for VCH Deployment and Operation.

## **Apply Security Updates and Patches**

Download a new version of vSphere Integrated Containers Engine and upgrade your existing VCHs.

## **Security Related Log Messages**

Security-related information for vSphere Integrated Containers Engine appears in docker-personality.log and vicadmin.log, that you can access from the VCH Admin portal for a VCH.

#### **Sensitive Data**

The VMX file of the VCH endpoint VM stores vSphere Integrated Containers Engine configuration information, which allows most of the configuration to be read-only by the guest. The container VMs might hold sensitive application data, such as environment variables for processes, command arguments, and so on.