X-Swap

Revision History

Date	Contents	Author
2020.03.07	First version	Snow
2020.03.11	Revision	Snow

Summary

X-Swap is designed to facilitate bi-directional swaps of stablecoin including USDx / USDT / USDC / TUSD / DAI / PAX, and etc. The administrator maintains exchange rate and a small amount of fee will be charged to each transaction. Stablecoin reserves will be supplied to Lendf.Me (lending protocol of dForce Network) for interest-generation.

Glossary

- Stablecoin: Tokens pegged to cryptocurrency, fiat money, or to exchange-traded commodities, including but not restricted to, USDx / USDT / USDC, and etc.
- Exchange: Trading pairs available on X-Swap, with pre-determined exchange rate and service fees.
- Lendf.Me: A decentralized money market protocol and an ecosystem project of dForce Network, with stablecoin saving and lending capabilities.

Swap


User deposits one type of stablecoin supported by X-Swap, into the contract in exchange for another type of stablecoin. The contract will perform an automatic calculation based on pre-determined exchange rate, as well as associated service fees. Let's assume A & B are two different types of stablecoins involved in such an exchange, with four scenarios described as follow:

a) Both A & B have been supplied for yielding to Lendf.Me: User deposits amount x of A into the contract of X-Swap, the contract will automatically supply amount x of A into Lendf.Me and withdraw corresponding amount of B from Lendf.Me to complete the

trade with the user.

- b) Only A has been lent-out to Lendf.Me, while B is not: User deposits amount x of A into the contract of X-Swap, the contract will automatically supply amount x of A into Lendf.Me and send corresponding amount of B to the user to complete the trade.
- c) A is not, while B, on the contrary, has been lent-out to Lendf.Me: User deposits amount x of A into the contract of X-Swap, the contract will automatically withdraw corresponding amount of B from Lendf.Me to complete the trade with the user.
- d) Both A and B are not lent-out: User deposits amount x of A into the contract of X-Swap, the contract will send corresponding amount of B to the user to complete the trade.

(P.S.: User should expect a small variation in amount of B received due to exchange rate and service fee associated).



flow chart

Functions

For Users

- a) Stablecoin Swap
 - i. User must accept a one-off approving for tokens to be traded for the first time.
 - ii. User sends amount x of token A into the contract by calling function 'trade', and then pick another type of token to receive.
 - iii. User gets amount y of token B, and should expect a small variation in amount compared to token A, due to exchange rate and service fee associated.

• For Admin

a) Create Exchange

- i. Exchange refers to a trading pair between two different types of stablecoins.
- ii. Set exchange rate between token A and token B, which employs an 18-digit precision, for example, 1,001,000,000,000,000,000 represents an exchange from 1 A for 1.001 B.
- iii. Set service fee at an 18-digit precision, for example, 1,000,000,000,000,000 represents an exchange fee of 0.1%.

b) Set Fee

i. Update of exchange fees for trading pairs.

c) Set Rate

i. Update of exchange rate for trading pairs.

d) Enable/Disable Lending

- i. Enable or disable stablecoin for lending.
- ii. Upon enabling, all balances of the designated stablecoin will be supplied from X-Swap contract to Lendf.Me.
- iii. Upon disabling, all balances of the designated stablecoin will be withdrew from Lendf.Me to X-Swap contract.

e) Stop/Start

i. Stop or start the trading function.

f) TransferIn


- i. User supplies some stablecoins to the contract of X-Swap as liquidity reserves.
- ii. All balances of stablecoin reserves (applicable to types integrated by Lendf.Me)

will be supplied to the contract of Lendf.Me to earn yield.



g) TransferOut

- i. In the event stablecoin supplied to X-Swap as reserve has also been integrated by Lendf.Me, then withdraw the requested amount by user from Lendf.Me first.
- ii. Send the requested amount of stablecoin to the user.
- iii. Withdrawal of remaining balances supported.




Prototype

User Interface



Admin Interface



Emergency

Start/Stop xSwap