

SENTRIQ Console: access, roles and permissions

1. Roles

SENTRIQ ships five built-in roles. They are not customisable in 4.2; custom roles arrive in 4.3.

Role	Can view	Can change	Typical holder
viewer	Dashboards, alerts	Nothing	Management, auditors
noc-operator	Alerts, endpoint health, runbook links	Acknowledge alerts, retire endpoints	NOC tier 1
soc-analyst	Everything noc-operator sees, plus raw telemetry and detection detail	Alert triage state, false-positive marking	SOC tier 2
engineer	Everything	Policy, exclusions, detection rules	Product engineering
admin	Everything	Everything, including roles	Platform team

noc-operator cannot read raw telemetry. This is deliberate and is the most frequent source of confusion during handover: an operator following a runbook step that says “check the process tree” will see an empty panel rather than an error. The step requires soc-analyst.

2. Session behaviour

Console sessions are held in the session store, not in the browser.

Setting	Default	Notes
Idle timeout	30 minutes	Not configurable in 4.2
Absolute session lifetime	12 hours	Re-authentication required after
Concurrent sessions per user	3	Fourth login evicts the oldest

2.1 SQ-4002 — session store unavailable

If the session store is unreachable the Console returns SQ-4002 and **every user is logged out simultaneously**. This looks like a total outage and is usually mistaken for one.

Confirm before escalating:

```
sentriqctl console session-store-health
```

The alert clears on its own once the store returns. Detection and telemetry collection are **unaffected** — only the user interface is down. Endpoints continue to be protected throughout, and this is the single most useful fact to state when the incident is reported.

3. Authentication

SAML and LDAP are supported. Local accounts exist only for the initial admin and should be disabled after the identity provider is connected.

Group-to-role mapping is configured under **Console → Settings → Identity → Role mapping**. Mappings are evaluated top to bottom and **the first match wins** — a user in both the NOC and SOC groups receives whichever role is listed higher, not the more permissive of the two.

4. Access review

Export the current role assignments:

```
sentriqctl console roles export --format csv
```

Review quarterly. The export includes last-login timestamps, which is the practical way to find accounts belonging to people who have left.

5. Common access problems

Symptom	Cause	Resolution
User sees empty panels, no error	Role lacks the permission for that data	Check role against §1
All users logged out at once	SQ-4002 — session store	§2.1; no action needed at the endpoint
User has the wrong role after a group change	First-match-wins mapping	Reorder mappings, §3

Symptom	Cause	Resolution
Login loop after SAML change	Clock skew over 5 minutes	Verify NTP on the Console host

Component owner: **Lê Hoàng Nam** (SRE).