# Linux Fault-injection Documentation

The kernel development community

# **CONTENTS**

1	Fault injection capabilities infrastructure	1
2	Notifier error injection	11
3	NVMe Fault Injection	15
4	Provoking crashes with Linux Kernel Dump Test Module (LKDTM)	19

### **FAULT INJECTION CAPABILITIES INFRASTRUCTURE**

See also drivers/md/md-faulty.c and "every nth" module option for scsi debug.

# 1.1 Available fault injection capabilities

failslab

injects slab allocation failures. (kmalloc(), kmem\_cache\_alloc(), ···)

· fail page alloc

injects page allocation failures. (alloc pages(), get free pages(), ...)

fail usercopy

injects failures in user memory access functions. (copy\_from\_user(), get user(),  $\cdots$ )

fail futex

injects futex deadlock and uaddr fault errors.

• fail make request

injects disk IO errors on devices permitted by setting /sys/block/<device>/make-it-fail or /sys/block/<device>/<partition>/make-it-fail. (submit bio noacct())

• fail mmc request

injects MMC data errors on devices permitted by setting debugfs entries under /sys/kernel/debug/mmc0/fail mmc request

• fail function

injects error return on specific functions, which are marked by AL-LOW\_ERROR\_INJECTION() macro, by setting debugfs entries under /sys/kernel/debug/fail\_function. No boot option supported.

• NVMe fault injection

inject NVMe status code and retry flag on devices permitted by setting debugfs entries under /sys/kernel/debug/nvme\*/fault\_inject. The default status code is NVME\_SC\_INVALID\_OPCODE with no retry. The status code and retry flag can be set via the debugfs.

### 1.2 Configure fault-injection capabilities behavior

#### 1.2.1 debugfs entries

fault-inject-debugfs kernel module provides some debugfs entries for runtime configuration of fault-injection capabilities.

• /sys/kernel/debug/fail\*/probability:

likelihood of failure injection, in percent.

Format: <percent>

Note that one-failure-per-hundred is a very high error rate for some testcases. Consider setting probability=100 and configure /sys/kernel/debug/fail\*/interval for such testcases.

• /sys/kernel/debug/fail\*/interval:

specifies the interval between failures, for calls to should\_fail() that pass all the other tests.

Note that if you enable this, by setting interval>1, you will probably want to set probability=100.

• /sys/kernel/debug/fail\*/times:

specifies how many times failures may happen at most. A value of -1 means "no limit" .

• /sys/kernel/debug/fail\*/space:

specifies an initial resource "budget", decremented by "size" on each call to should\_fail(,size). Failure injection is suppressed until "space" reaches zero.

/sys/kernel/debug/fail\*/verbose

```
Format: \{ 0 | 1 | 2 \}
```

specifies the verbosity of the messages when failure is injected. '0' means no messages; '1' will print only a single log line per failure; '2' will print a call trace too – useful to debug the problems revealed by fault injection.

• /sys/kernel/debug/fail\*/task-filter:

```
Format: { 'Y' | 'N' }
```

A value of 'N' disables filtering by process (default). Any positive value limits failures to only processes indicated by /proc/<pid>/make-it-fail==1.

• /sys/kernel/debug/fail\*/require-start, /sys/kernel/debug/fail\*/require-end, /sys/kernel/debug/fail\*/reject-start, /sys/kernel/debug/fail\*/reject-end:

specifies the range of virtual addresses tested during stacktrace walking. Failure is injected only if some caller in the walked stacktrace lies within the required range, and none lies within the rejected

range. Default required range is [0,ULONG\_MAX) (whole of virtual address space). Default rejected range is [0,0).

• /sys/kernel/debug/fail\*/stacktrace-depth:

specifies the maximum stacktrace depth walked during search for a caller within [require-start,require-end) OR [reject-start,reject-end).

• /sys/kernel/debug/fail\_page\_alloc/ignore-gfp-highmem:

```
Format: { 'Y' | 'N' }
```

default is 'N', setting it to 'Y' won't inject failures into highmem/user allocations.

- /sys/kernel/debug/failslab/ignore-gfp-wait:
- /sys/kernel/debug/fail\_page\_alloc/ignore-gfp-wait:

```
Format: { 'Y' | 'N' }
```

default is 'N', setting it to 'Y' will inject failures only into non-sleep allocations (GFP ATOMIC allocations).

/sys/kernel/debug/fail\_page\_alloc/min-order:

specifies the minimum page allocation order to be injected failures.

• /sys/kernel/debug/fail futex/ignore-private:

```
Format: { 'Y' | 'N' }
```

default is 'N', setting it to 'Y' will disable failure injections when dealing with private (address space) futexes.

• /sys/kernel/debug/fail function/inject:

```
Format: { 'function-name' | '!function-name' | ' }
```

specifies the target function of error injection by name. If the function name leads '!' prefix, given function is removed from injection list. If nothing specified ( ° ) injection list is cleared.

• /sys/kernel/debug/fail function/injectable:

(read only) shows error injectable functions and what type of error values can be specified. The error type will be one of below; - NULL: retval must be 0. - ERRNO: retval must be -1 to -MAX\_ERRNO (-4096). - ERR NULL: retval must be 0 or -1 to -MAX ERRNO (-4096).

• /sys/kernel/debug/fail function/<function-name>/retval:

specifies the "error" return value to inject to the given function. This will be created when the user specifies a new injection entry. Note that this file only accepts unsigned values. So, if you want to use a negative errno, you better use 'printf' instead of 'echo', e.g.: printf "printf" instead of 'echo', e.g.: printf" printf" printf" printf" printf" printf" printf" printf "printf" printf" pri

#### 1.2.2 Boot option

In order to inject faults while debugfs is not available (early boot time), use the boot option:

```
failslab=
fail_page_alloc=
fail_usercopy=
fail_make_request=
fail_futex=
mmc_core.fail_request=<interval>,,,<space>,<times>
```

#### 1.2.3 proc entries

• /proc/<pid>/fail-nth, /proc/self/task/<tid>/fail-nth:

Write to this file of integer N makes N-th call in the task fail. Read from this file returns a integer value. A value of '0' indicates that the fault setup with a previous write to this file was injected. A positive integer N indicates that the fault wasn't yet injected. Note that this file enables all types of faults (slab, futex, etc). This setting takes precedence over all other generic debugfs settings like probability, interval, times, etc. But per-capability settings (e.g. fail futex/ignore-private) take precedence over it.

This feature is intended for systematic testing of faults in a single system call. See an example below.

# 1.3 How to add new fault injection capability

- #include linux/fault-inject.h>
- · define the fault attributes

```
DECLARE FAULT ATTR(name);
```

Please see the definition of struct fault attr in fault-inject.h for details.

- provide a way to configure fault attributes
- boot option

If you need to enable the fault injection capability from boot time, you can provide boot option to configure it. There is a helper function for it:

```
setup fault attr(attr, str);
```

debugfs entries

failslab, fail\_page\_alloc, fail\_usercopy, and fail\_make\_request use this way. Helper functions:

fault\_create\_debugfs\_attr(name, parent, attr);

• module parameters

If the scope of the fault injection capability is limited to a single kernel module, it is better to provide module parameters to configure the fault attributes.

add a hook to insert failures

Upon should fail() returning true, client code should inject a failure: should fail(attr, size);

### 1.4 Application Examples

• Inject slab allocation failures into module init/exit code:

```
#!/bin/bash
FAILTYPE=failslab
echo Y > /sys/kernel/debug/$FAILTYPE/task-filter
echo 10 > /sys/kernel/debug/$FAILTYPE/probability
echo 100 > /sys/kernel/debug/$FAILTYPE/interval
echo -1 > /sys/kernel/debug/$FAILTYPE/times
echo 0 > /sys/kernel/debug/$FAILTYPE/space
echo 2 > /sys/kernel/debug/$FAILTYPE/verbose
echo 1 > /sys/kernel/debug/$FAILTYPE/ignore-gfp-wait
faulty system()
{
    bash -c "echo 1 > /proc/self/make-it-fail && exec $*"
}
if [ $# -eq 0 ]
then
    echo "Usage: $0 modulename [ modulename ... ]"
   exit 1
fi
for m in $*
do
    echo inserting $m...
    faulty system modprobe $m
    echo removing $m...
    faulty_system modprobe -r $m
done
```

• Inject page allocation failures only for a specific module:

```
#!/bin/bash
```

```
FAILTYPE=fail page alloc
module=$1
if [ -z $module ]
then
    echo "Usage: $0 <modulename>"
    exit 1
fi
modprobe $module
if [ ! -d /sys/module/$module/sections ]
    echo Module $module is not loaded
   exit 1
fi
cat /sys/module/$module/sections/.text > /sys/kernel/debug/
→$FAILTYPE/require-start
cat /sys/module/$module/sections/.data > /sys/kernel/debug/
→$FAILTYPE/require-end
echo N > /sys/kernel/debug/$FAILTYPE/task-filter
echo 10 > /sys/kernel/debug/$FAILTYPE/probability
echo 100 > /sys/kernel/debug/$FAILTYPE/interval
echo -1 > /sys/kernel/debug/$FAILTYPE/times
echo 0 > /sys/kernel/debug/$FAILTYPE/space
echo 2 > /sys/kernel/debug/$FAILTYPE/verbose
echo 1 > /sys/kernel/debug/$FAILTYPE/ignore-gfp-wait
echo 1 > /sys/kernel/debug/$FAILTYPE/ignore-afp-highmem
echo 10 > /sys/kernel/debug/$FAILTYPE/stacktrace-depth
trap "echo 0 > /sys/kernel/debug/$FAILTYPE/probability" SIGINT.
→SIGTERM EXIT
echo "Injecting errors into the module $module... (interrupt to,
⊸stop)"
sleep 1000000
```

• Inject open ctree error while btrfs mount:

```
#!/bin/bash

rm -f testfile.img
dd if=/dev/zero of=testfile.img bs=1M seek=1000 count=1
DEVICE=$(losetup --show -f testfile.img)
mkfs.btrfs -f $DEVICE
mkdir -p tmpmnt
```

```
FAILTYPE=fail function
FAILFUNC=open ctree
echo $FAILFUNC > /sys/kernel/debug/$FAILTYPE/inject
printf %#x -12 > /sys/kernel/debug/$FAILTYPE/$FAILFUNC/retval
echo N > /sys/kernel/debug/$FAILTYPE/task-filter
echo 100 > /sys/kernel/debug/$FAILTYPE/probability
echo 0 > /sys/kernel/debug/$FAILTYPE/interval
echo -1 > /sys/kernel/debug/$FAILTYPE/times
echo 0 > /sys/kernel/debug/$FAILTYPE/space
echo 1 > /sys/kernel/debug/$FAILTYPE/verbose
mount -t btrfs $DEVICE tmpmnt
if [ $? -ne 0 ]
then
    echo "SUCCESS!"
else
    echo "FAILED!"
    umount tmpmnt
fi
echo > /sys/kernel/debug/$FAILTYPE/inject
rmdir tmpmnt
losetup -d $DEVICE
rm testfile.img
```

# 1.5 Tool to run command with failslab or fail\_page\_alloc

In order to make it easier to accomplish the tasks mentioned above, we can use tools/testing/fault-injection/failcmd.sh. Please run a command "./tools/testing/fault-injection/failcmd.sh -help" for more information and see the following examples.

#### Examples:

Run a command "make -C tools/testing/selftests/ run\_tests" with injecting slab allocation failure:

```
# ./tools/testing/fault-injection/failcmd.sh \
    -- make -C tools/testing/selftests/ run_tests
```

Same as above except to specify 100 times failures at most instead of one time at most by default:

Same as above except to inject page allocation failure instead of slab allocation failure:

# 1.6 Systematic faults using fail-nth

The following code systematically faults 0-th, 1-st, 2-nd and so on capabilities in the socketpair() system call:

```
#include <sys/types.h>
#include <sys/stat.h>
#include <sys/socket.h>
#include <sys/syscall.h>
#include <fcntl.h>
#include <unistd.h>
#include <string.h>
#include <stdlib.h>
#include <stdio.h>
#include <errno.h>
int main()
{
      int i, err, res, fail nth, fds[2];
      char buf[128];
      system("echo N > /sys/kernel/debug/failslab/ignore-gfp-wait");
      sprintf(buf, "/proc/self/task/%ld/fail-nth", syscall(SYS
→gettid));
      fail nth = open(buf, 0 RDWR);
      for (i = 1; i++) {
              sprintf(buf, "%d", i);
              write(fail nth, buf, strlen(buf));
              res = socketpair(AF LOCAL, SOCK STREAM, 0, fds);
              err = errno;
              pread(fail nth, buf, sizeof(buf), 0);
              if (res == 0) {
                      close(fds[0]);
                      close(fds[1]);
              printf("%d-th fault %c: res=%d/%d\n", i, atoi(buf) ?
\rightarrow 'N' : 'Y',
                       res, err);
              if (atoi(buf))
                      break;
      }
      return 0;
}
```

An example output:

```
1-th fault Y: res=-1/23
2-th fault Y: res=-1/23
3-th fault Y: res=-1/12
4-th fault Y: res=-1/12
5-th fault Y: res=-1/23
6-th fault Y: res=-1/23
7-th fault Y: res=-1/23
8-th fault Y: res=-1/12
9-th fault Y: res=-1/12
10-th fault Y: res=-1/12
11-th fault Y: res=-1/12
12-th fault Y: res=-1/12
13-th fault Y: res=-1/12
14-th fault Y: res=-1/12
15-th fault Y: res=-1/12
16-th fault N: res=0/12
```

Linux Fault-injection Documentation						

#### **NOTIFIER ERROR INJECTION**

Notifier error injection provides the ability to inject artificial errors to specified notifier chain callbacks. It is useful to test the error handling of notifier call chain failures which is rarely executed. There are kernel modules that can be used to test the following notifiers.

- PM notifier
- Memory hotplug notifier
- powerpc pSeries reconfig notifier
- · Netdevice notifier

# 2.1 PM notifier error injection module

This feature is controlled through debugfs interface

/sys/kernel/debug/notifier-error-inject/pm/actions/<notifier event>/error

Possible PM notifier events to be failed are:

- PM HIBERNATION PREPARE
- PM SUSPEND PREPARE
- PM RESTORE PREPARE

Example: Inject PM suspend error (-12 = -ENOMEM):

```
# cd /sys/kernel/debug/notifier-error-inject/pm/
# echo -12 > actions/PM_SUSPEND_PREPARE/error
# echo mem > /sys/power/state
bash: echo: write error: Cannot allocate memory
```

### 2.2 Memory hotplug notifier error injection module

This feature is controlled through debugfs interface

/sys/kernel/debug/notifier-error-inject/memory/actions/<notifier event>/error

Possible memory notifier events to be failed are:

- MEM GOING ONLINE
- MEM GOING OFFLINE

Example: Inject memory hotplug offline error (-12 == -ENOMEM):

```
# cd /sys/kernel/debug/notifier-error-inject/memory
# echo -12 > actions/MEM_GOING_OFFLINE/error
# echo offline > /sys/devices/system/memory/memoryXXX/state
bash: echo: write error: Cannot allocate memory
```

# 2.3 powerpc pSeries reconfig notifier error injection module

This feature is controlled through debugfs interface

/sys/kernel/debug/notifier-error-inject/pSeriesreconfig/actions/<notifier event>/error

Possible pSeries reconfig notifier events to be failed are:

- PSERIES RECONFIG ADD
- PSERIES RECONFIG REMOVE
- PSERIES DRCONF MEM ADD
- PSERIES DRCONF MEM REMOVE

# 2.4 Netdevice notifier error injection module

This feature is controlled through debugfs interface

/sys/kernel/debug/notifier-error-inject/netdev/actions/<notifier event>/error

Netdevice notifier events which can be failed are:

- NETDEV REGISTER
- NETDEV CHANGEMTU
- NETDEV CHANGENAME
- NETDEV\_PRE\_UP
- NETDEV PRE TYPE CHANGE

- NETDEV POST INIT
- NETDEV PRECHANGEMTU
- NETDEV PRECHANGEUPPER
- NETDEV\_CHANGEUPPER

Example: Inject netdevice mtu change error (-22 == -EINVAL):

```
# cd /sys/kernel/debug/notifier-error-inject/netdev
# echo -22 > actions/NETDEV_CHANGEMTU/error
# ip link set eth0 mtu 1024
RTNETLINK answers: Invalid argument
```

# 2.5 For more usage examples

There are tools/testing/selftests using the notifier error injection features for CPU and memory notifiers.

- tools/testing/selftests/cpu-hotplug/on-off-test.sh
- tools/testing/selftests/memory-hotplug/on-off-test.sh

These scripts first do simple online and offline tests and then do fault injection tests if notifier error injection module is available.

<b>Linux Fault-in</b>	jection	<b>Documental</b>	tion
-----------------------	---------	-------------------	------

#### **NVME FAULT INJECTION**

Linux's fault injection framework provides a systematic way to support error injection via debugfs in the /sys/kernel/debug directory. When enabled, the default NVME\_SC\_INVALID\_OPCODE with no retry will be injected into the nvme\_try\_complete\_req. Users can change the default status code and no retry flag via the debugfs. The list of Generic Command Status can be found in include/linux/nvme.h

Following examples show how to inject an error into the nvme.

First, enable CONFIG\_FAULT\_INJECTION\_DEBUG\_FS kernel config, recompile the kernel. After booting up the kernel, do the following.

# 3.1 Example 1: Inject default status code with no retry

```
mount /dev/nvme0n1 /mnt
echo 1 > /sys/kernel/debug/nvme0n1/fault_inject/times
echo 100 > /sys/kernel/debug/nvme0n1/fault_inject/probability
cp a.file /mnt
```

**Expected Result:** 

```
cp: cannot stat '/mnt/a.file': Input/output error
```

Message from dmesg:

```
FAULT_INJECTION: forcing a failure.
name fault_inject, interval 1, probability 100, space 0, times 1
CPU: 0 PID: 0 Comm: swapper/0 Not tainted 4.15.0-rc8+ #2
Hardware name: innotek GmbH VirtualBox/VirtualBox,
BIOS VirtualBox 12/01/2006
Call Trace:
        <IRQ>
            dump_stack+0x5c/0x7d
            should_fail+0x148/0x170
            nvme_should_fail+0x2f/0x50 [nvme_core]
            nvme_process_cq+0xe7/0x1d0 [nvme]
            nvme_irq+0x1e/0x40 [nvme]
            _handle_irq_event_percpu+0x3a/0x190
```

```
handle irg event percpu+0x30/0x70
  handle irg event+0x36/0x60
  handle fasteoi irq+0x78/0x120
  handle irq+0xa7/0x130
  ? tick irg enter+0xa8/0xc0
 do IR0+0 \times 43/0 \times c0
  common interrupt+0xa2/0xa2
 </IRQ>
RIP: 0010:native safe halt+0x2/0x10
RSP: 0018:fffffff82003e90 EFLAGS: 00000246 ORIG RAX:
→fffffffffffdd
RAX: ffffffff817a10c0 RBX: ffffffff82012480 RCX: 0000000000000000
RDX: 000000000000000 RSI: 0000000000000 RDI: 00000000000000
R10: 000000000000000 R11: 0000000000000 R12: fffffff82012480
R13: ffffffff82012480 R14: 00000000000000 R15: 000000000000000
  ? sched text end+0x4/0x4
 default idle+0x18/0xf0
 do idle+0 \times 150/0 \times 1d0
  cpu startup entry+0x6f/0x80
  start kernel+0x4c4/0x4e4
  ? set init arg+0x55/0x55
 secondary_startup_64+0xa5/0xb0
  print reg error: I/O error, dev nvmeOn1, sector 9240
EXT4-fs error (device nvme0n1): ext4 find entry:1436:
inode #2: comm cp: reading directory lblock 0
```

# 3.2 Example 2: Inject default status code with retry

```
mount /dev/nvme0n1 /mnt
echo 1 > /sys/kernel/debug/nvme0n1/fault_inject/times
echo 100 > /sys/kernel/debug/nvme0n1/fault_inject/probability
echo 1 > /sys/kernel/debug/nvme0n1/fault_inject/status
echo 0 > /sys/kernel/debug/nvme0n1/fault_inject/dont_retry

cp a.file /mnt
```

**Expected Result:** 

```
command success without error
```

Message from dmesg:

```
Call Trace:
  <IR0>
  dump stack+0x5c/0x7d
  should fail+0x148/0x170
  nvme should fail+0x30/0x60 [nvme core]
  nvme loop queue response+0x84/0x110 [nvme loop]
  nvmet reg complete+0x11/0x40 [nvmet]
  nvmet bio done+0x28/0x40 [nvmet]
  blk update request+0xb0/0x310
  blk mg end request+0x18/0x60
  flush smp call function queue+0x3d/0xf0
  smp call function single interrupt+0x2c/0xc0
  call_function_single interrupt+0xa2/0xb0
  </IR0>
RIP: 0010:native safe halt+0x2/0x10
RSP: 0018:ffffc9000068bec0 EFLAGS: 00000246 ORIG RAX:
→ffffffffffff64
RAX: ffffffff817a10c0 RBX: ffff88011a3c9680 RCX: 0000000000000000
RDX: 000000000000000 RSI: 0000000000000 RDI: 00000000000000
RBP: 00000000000001 R08: 000000008e38c131 R09: 0000000000000000
R10: 000000000000000 R11: 0000000000000 R12: ffff88011a3c9680
R13: ffff88011a3c9680 R14: 00000000000000 R15: 000000000000000
  ? sched text end+0x4/0x4
  default idle+0x18/0xf0
  do idle+0 \times 150/0 \times 1d0
  cpu startup entry+0x6f/0x80
  start secondary+0x187/0x1e0
  secondary startup 64+0xa5/0xb0
```

# 3.3 Example 3: Inject an error into the 10th admin command

```
echo 100 > /sys/kernel/debug/nvme0/fault_inject/probability
echo 10 > /sys/kernel/debug/nvme0/fault_inject/space
echo 1 > /sys/kernel/debug/nvme0/fault_inject/times
nvme reset /dev/nvme0
```

#### **Expected Result:**

```
After NVMe controller reset, the reinitialization may or may not 

→succeed.

It depends on which admin command is actually forced to fail.
```

#### Message from dmesg:

```
name fault inject, interval 1, probability 100, space 1, times 1
CPU: 0 PID: 0 Comm: swapper/0 Not tainted 5.2.0-rc2+ #2
Hardware name: MSI MS-7A45/B150M MORTAR ARCTIC (MS-7A45), BIOS 1.50
→04/25/2017
Call Trace:
 <IR0>
dump stack+0x63/0x85
 should fail+0x14a/0x170
 nvme should fail+0x38/0x80 [nvme core]
 nvme irg+0x129/0x280 [nvme]
 ? blk mq end request+0xb3/0x120
  handle irq event percpu+0x84/0x1a0
 handle irg event percpu+0x32/0x80
 handle irq event+0x3b/0x60
 handle edge irg+0x7f/0x1a0
 handle irq+0x20/0x30
do IR0+0x4e/0xe0
 common_interrupt+0xf/0xf
 </IR0>
RIP: 0010:cpuidle enter state+0xc5/0x460
Code: ff e8 8f 5f 86 ff 80 7d c7 00 74 17 9c 58 0f 1f 44 00 00 f6...
→c4 02 0f 85 69 03 00 00 31 ff e8 62 aa 8c ff fb 66 0f 1f 44 00 00
\rightarrow<45> 85 ed 0f 88 37 03 00 00 4c 8b 45 d0 4c 2b 45 b8 48 ba cf f7...
→53
RSP: 0018:fffffff88c03dd0 EFLAGS: 00000246 ORIG_RAX:
→ffffffffffffdc
RAX: ffff9dac25a2ac80 RBX: ffffffff88d53760 RCX: 000000000000001f
RDX: 000000000000000 RSI: 000000002d958403 RDI: 0000000000000000
RBP: ffffffff88c03e18 R08: ffffffff75e35ffb7 R09: 00000a49a56c0b48
R10: ffffffff88c03da0 R11: 000000000001b0c R12: ffff9dac25a34d00
R13: 000000000000000 R14: 0000000000000 R15: fffffff88d53760
 cpuidle enter+0x2e/0x40
 call cpuidle+0x23/0x40
 do idle+0\times201/0\times280
 cpu startup entry+0x1d/0x20
 rest init+0xaa/0xb0
 arch call rest init+0xe/0x1b
 start kernel+0x51c/0x53b
x86 64 start reservations+0x24/0x26
x86 64 start kernel+0x74/0x77
 secondary_startup_64+0xa4/0xb0
nvme nvme0: Could not set queue count (16385)
nvme nvme0: IO queues not created
```

# PROVOKING CRASHES WITH LINUX KERNEL DUMP TEST MODULE (LKDTM)

The lkdtm module provides an interface to disrupt (and usually crash) the kernel at predefined code locations to evaluate the reliability of the kernel's exception handling and to test crash dumps obtained using different dumping solutions. The module uses KPROBEs to instrument the trigger location, but can also trigger the kernel directly without KPROBE support via debugfs.

You can select the location of the trigger ("crash point name") and the type of action ("crash point type") either through module arguments when inserting the module, or through the debugfs interface.

#### Usage:

#### recur count

Recursion level for the stack overflow test. By default this is dynamically calculated based on kernel configuration, with the goal of being just large enough to exhaust the kernel stack. The value can be seen at /sys/module/lkdtm/parameters/recur\_count.

#### cpoint name

Where in the kernel to trigger the action. It can be one of INT\_HARDWARE\_ENTRY, INT\_HW\_IRQ\_EN, INT\_TASKLET\_ENTRY, FS\_DEVRW, MEM\_SWAPOUT, TIMERADD, SCSI\_QUEUE\_RQ, IDE\_CORE\_CP, or DIRECT

#### cpoint type

Indicates the action to be taken on hitting the crash point. These are numerous, and best queried directly from debugfs. Some of the common ones are PANIC, BUG, EXCEPTION, LOOP, and OVERFLOW. See the contents of /sys/kernel/debug/provoke-crash/DIRECT for a complete list.

#### cpoint count

Indicates the number of times the crash point is to be hit before triggering the action. The default is 10 (except for DIRECT, which always fires immediately).

You can also induce failures by mounting debugfs and writing the type to <debugfs>/provoke-crash/<crashpoint>. E.g.:

#### **Linux Fault-injection Documentation**

```
mount -t debugfs debugfs /sys/kernel/debug
echo EXCEPTION > /sys/kernel/debug/provoke-crash/INT HARDWARE ENTRY
```

The special file *DIRECT* will induce the action directly without KPROBE instrumentation. This mode is the only one available when the module is built for a kernel without KPROBEs support:

# Instead of having a BUG kill your shell, have it kill "cat":
cat <(echo WRITE\_R0) >/sys/kernel/debug/provoke-crash/DIRECT