
1. 安装Socat

在线安装依赖环境:

```
yum install gcc
yum install socat
```

2. 安装Erlang



```
mkdir /rabbitmq && cd /rabbitmq

# 上传 erlang-22.0.7-1.el7.x86_64.rpm 安装包上传

# 安装
rpm -ivh erlang-22.0.7-1.el7.x86_64.rpm
```

3. 安装RabbitMQ

```
cd /rabbitmq

# 上传 rabbitmq-server-3.7.17-1.el7.noarch.rpm 安装包
上传

# 安装
rpm -ivh rabbitmq-server-3.7.17-1.el7.noarch.rpm
```

4. 开启管理界面及配置

```
# 开启管理界面
rabbitmq-plugins enable rabbitmq_management

# 配置远程可使用guest登录mq
cd /usr/share/doc/rabbitmq-server-3.7.17

cp rabbitmq.config.example /etc/rabbitmq/rabbitmq.config

# 修改配置文件
vi /etc/rabbitmq/rabbitmq.config
```

```
[root@itcast rabbitmq]# rabbitmq-plugins enable rabbitmq_management
Enabling plugins on node rabbit@itcast:
rabbitmq_management
The following plugins have been configured:
   rabbitmq_management
   rabbitmq_management
   rabbitmq_management_agent
   rabbitmq_web_dispatch
Applying plugin configuration to rabbit@itcast...
```

修改 /etc/rabbitmq/rabbitmq.config 配置文件:

```
📙 rabbitmq.config 🛚
 54
        %% The default "guest" user is only permitted to access the server
 56
        %% via a loopback interface (e.g. localhost).
        %% {loopback users, [<<"guest">>]},
 58
        용용
 59
        %% Uncomment the following line if you want to allow access to the
        %% guest user from anywhere on the network.
 60
 61
        %% {loopback users, []},
                                           修改之前
 62
 63
 64
        %% TLS configuration.
 65
        용용
 66
        %% Related doc guide: https://www.rabbitmq.com/ssl.html.
 67
```

```
📙 rabbitmq.config 🛚
        %% The default "guest" user is only permitted to access the server
        %% via a loopback interface (e.g. localhost).
 57
        %% {loopback_users, [<<"guest">>]},
 58
       용용
 59
        %% Uncomment the following line if you want to allow access to the
        %% quest user from anywhere on the network.
 60
61
        {loopback users, []}
                                                修改之后,不要忘记删除后面的那个,
 63
 64
       %% TLS configuration.
 65
       용용
       %% Related doc guide: https://www.rabbitmg.com/ssl.html.
 66
```

5. 启动

```
centos6用这个命令:
/sbin/service rabbitmq-server restart

centos7用这个命令:
systemctl start rabbitmq-server
```

6. 配置虚拟主机及用户

6.1. 用户角色

RabbitMQ在安装好后,可以访问 http://ip地址:15672 ; 其自带了guest/guest的用户名和密码; 如果需要创建自定义用户; 那么也可以登录管理界面后, 如下操作:



Overvie	ew Conn	ections	Channels	Exchanges	Queues	Admin					Cluster rabbit@itcast User guest Log out
Users	5										Users
▼ All us	r All users									Virtual Hosts	
Filter:			Regex ?						1 item, page size up to	100	Feature Flags
Name	Tags		s virtual hosts	Has password							Policies
guest	administrato	r	/	•							T Officials
?											Limits
▼ Add a	HEAT										Cluster
		ma ち		*							
Passwor	d: 🔻 •••	4		*							
		3		* (confirm)							
	Tags: adm	inistrato:		?							
	Set Admin Monitoring Policymaker										
	Management Impersonator None										
Add user	0	点记 Admin	1 之后会自动在	E Tags 中输入 a	dministrato						

角色说明:

1、超级管理员(administrator)

可登陆管理控制台,可查看所有的信息,并且可以对用户,策略(policy)进行操作。

2、 监控者(monitoring)

可登陆管理控制台,同时可以查看rabbitmg节点的相关信息(进程数,内存使用情况,磁盘使用情况等)

3、策略制定者(policymaker)

可登陆管理控制台,同时可以对policy进行管理。但无法查看节点的相关信息(上图红框标识的部分)。

4、普通管理者(management)

仅可登陆管理控制台,无法看到节点信息,也无法对策略进行管理。

5、其他

无法登陆管理控制台,通常就是普通的生产者和消费者。

6.2. Virtual Hosts配置

像mysql拥有数据库的概念并且可以指定用户对库和表等操作的权限。RabbitMQ也有类似的权限管理;在RabbitMQ中可以虚拟消息服务器Virtual Host,每个Virtual Hosts相当于一个相对独立的RabbitMQ服务器,每个VirtualHost之间是相互隔离的。exchange、queue、message不能互通。相当于mysql的db。Virtual Name一般以/开头。

6.2.1. 创建Virtual Hosts



6.2.2. 设置Virtual Hosts权限

