WAY4TECH SOLUTIONS


Live demos
garage-demo.way4tech.com
garage-pro.way4tech.com
w4demo / Demo2026 · Odoo 19

COMPLETE GUIDE · SETUP, EVERY SCREEN AND EVERY STEP

Garage Management for Odoo 19

Job cards with the customer's authority, red amber green health checks, flat rate against clocked hours, bays, quality checks, reminders, courtesy cars and the money, plus the Enterprise add-on for plans, claims, rate cards and the boards. Shown step by step on a live demo.

BASE | ENTERPRISE ADD-ON



START

About this guide

A workshop lives or dies on one sheet of paper: the job card. This guide follows a vehicle from the moment it is booked in to the moment the invoice goes out, then covers everything around it: the vehicle's history, the health check that sells the extra work, reminders, courtesy cars and the reports. You do not need to have used Odoo before.

Who it is for

The owner or service manager setting the workshop up, the service advisor at the front desk, the technician on the ramp, and anyone being shown the system for the first time.

How to read it

Front to back the first time. Each part opens with what you will learn and a short thing to try on the live demo, then walks every screen with a numbered step for each action.

The live demo

Al Quoz Auto Care, a worked example workshop in Dubai with four ramps, four technicians, a month of jobs at every stage, health checks, plans and claims already on it.

Two modules, two badges

BASE

Garage Management (w4t_garage_management). Job cards, vehicles, inspections, reminders, certificates, courtesy cars, time and the reports. Everything a workshop needs to run.

ENTERPRISE ADD-ON

Garage Management Enterprise (w4t_garage_enterprise). Installs on top of the base. Rate cards, service plans, insurance and warranty claims with split invoices, sublet work, technician commission, statements, renewals and the two boards. It is a module name, it runs on Odoo Community.

Every heading, step and menu entry in this guide carries one of the two badges, so you can see at a glance what the base module does on its own and what needs the add-on.

HOW IT WORKS

The demo workshops

Base and add-on	**garage-pro.way4tech.com**
Second copy	**garage-demo.way4tech.com**
Sign in	**w4demo** / **Demo2026** (the same on both)
Workshop	Al Quoz Auto Care, Dubai · four ramps, a test lane, prices in AED with 5% VAT
Runs on	Odoo 19, Community edition

Both demos are shared and reset from time to time, so anything you change may be changed back or seen by the next visitor. Treat them as a workshop to walk around, not your own books. The screens in this guide were taken on garage-pro, which has the Enterprise add-on installed.

What is in the guide

PART 1	How a workshop job runs	PART 2	The garage at a glance
PART 3	Open the demo and sign in	PART 4	Set the workshop up from zero
PART 5	Vehicles and their history	PART 6	Book the car in and price the job

PART 7	The estimate and the customer's authority	PART 8	On the ramp: clocking, parts and the board
PART 9	Quality check, ready and the invoice	PART 10	Warranty work and comebacks
PART 11	The vehicle health check	PART 12	Service reminders and test certificates
PART 13	Courtesy cars	PART 14	Reports
PART 15	Printed documents and emails	PART 16	Rate cards: what each account pays
PART 17	Service plans, AMCs and extended warranties	PART 18	Insurance and warranty claims, and the split bill
PART 19	Sublet work	PART 20	Technician commission
PART 21	Account statements and the two boards	PART 22	Scheduled jobs and access rights
PART 23	A 15 minute demo	PART 24	Questions people ask
PART 25	Menu map		

PART 1 How a workshop job runs

Before any screen, the trade. A garage sells time by the book, parts off the shelf and the customer's trust that the bill matches what they agreed. The module is built around four habits that good workshops already have.


IN THIS PART YOU WILL LEARN

- The eight stages a job card moves through, and why it cannot skip one
- Why the customer authorises an amount, not just a job
- Flat rate hours against clocked hours: efficiency and recovery
- How a red, amber, green health check turns into sold work
- What the Enterprise add-on changes: who pays

The job card is the spine BASE

Every piece of work is a job card. It is opened as an **estimate**, sent to the customer, **approved** with a recorded authority, put **in progress** on a ramp, handed to a **quality check**, signed off as **ready**, and **invoiced** when the car goes home. A job can also be **cancelled** and brought back as an estimate. The stage moves only by the buttons on the card. Dragging a card on the board or writing the stage directly is refused, because the stage is what says the customer agreed and the work passed a check.

The life of a job card BASE



The customer authorises an amount BASE

When the customer says yes, they say yes to a figure. The job card stores it as **Authorised Up To**. If more work is found and the job grows past that figure, **Start Work** refuses to run until somebody rings the customer and raises the authority. The awkward call happens before the spanner comes out, not at the counter when the bill is a surprise.

Flat rate hours against clocked hours BASE

The customer pays for the hours the book says a job takes, the **flat rate**, at the workshop labour rate. The technician clocks on and off, which gives the hours it really took. The module keeps both and works out two numbers the service manager runs the floor on:

FIGURE	HOW IT IS WORKED OUT	WHAT IT TELLS YOU
Efficiency	Sold hours divided by clocked hours	Over 100 the work beat the book; under, it took longer
Recovery	Sold hours divided by attended hours (contracted hours a week, times four)	How much of the week you paid for was actually sold
Gross profit	Labour sold less labour cost, plus parts sold less parts cost, plus sundries	What the job left behind

The health check sells the work BASE

While the car is on the ramp, the technician runs a check sheet: brakes, tyres, fluids, lights and the rest, each marked **green**, **amber** or **red** with a measurement. An amber or red item carries the operation that fixes it, priced at your

labour rate. The customer accepts the items they want and one button turns them into labour on the open job.

Who pays ENTERPRISE ADD-ON

With the Enterprise add-on, a job also says who is paying for it: **the customer**, **a service plan** the customer already bought, or **an insurer or warranty** company. That changes how the job is invoiced. A plan job is not billed again, and an approved claim raises two invoices, one to the insurer and one to the owner for the excess.

PART 2 The garage at a glance

The module adds one app, Garage, with up to nine menus. This part is the map, and who is allowed to see what.

Who sees what BASE

ROLE	WHAT THEY DO	WHAT THEY CANNOT DO
Technician	Works their own job cards, clocks on and off, fills in check sheets. Sees only the jobs they lead or have clocked on to, their own time logs and their own sheets.	See prices, costs or other technicians' work. Take the customer's authority. Invoice.
Service Advisor	Books work in, quotes it, takes the authority, hands the vehicle back and invoices it. Sees every job, odometer readings, reminders and courtesy cars.	See cost prices or gross profit. Open Reporting or Configuration.
Workshop Manager	Everything above, plus cost prices, gross profit, technician recovery, the reports and the configuration.	Change Settings unless also an Odoo administrator.
Plans and Claims ENTERPRISE ADD-ON	Sells service plans, raises claims and sublet work, sees the two boards. A Workshop Manager gets it automatically.	-

> On the live demo you are signed in as **w4demo**, a user who can see every menu, so you can follow the whole guide from one login. In a real workshop a technician would see only Workshop and Inspections.

The menus

Dashboards

Workshop Floor ENTERPRISE ADD-ON	Open jobs, approvals, ramps, ready, late, bays and hours
Trading ENTERPRISE ADD-ON	Revenue, margin, average invoice, plans and claims

Workshop

Job Cards BASE	Every job from estimate to invoice
Workshop Board BASE	The same jobs as cards by stage
Time Logs BASE	Every clock on and clock off

Inspections

Check Sheets BASE	Red, amber and green health checks
Advised Work BASE	Every red or amber item and whether it was sold

Plans and Claims

Service Plans ENTERPRISE ADD-ON	Packages, AMCs and extended warranties
Claims ENTERPRISE ADD-ON	Insurance and warranty claims with the shortfall
Sublet Work ENTERPRISE ADD-ON	Outwork sent to a specialist and sold on
Account Statement ENTERPRISE ADD-ON	A period of work for one account on one sheet
Technician Commission ENTERPRISE ADD-ON	One line per technician per month

Vehicles

Vehicles BASE	Every vehicle with its history
Odometer Readings BASE	Every reading, from every source
Roadworthiness Tests BASE	Test certificates and their expiry
Service Reminders BASE	What is due, by date or by reading

Courtesy Cars

Loans BASE	Who has which loan car and until when
Courtesy Fleet BASE	The loan cars, rates and cover

Reporting

Gross Profit BASE	Labour and parts profit per job
Labour Recovery BASE	Sold against clocked, per line
Parts Used BASE	Every part fitted
Inspection Conversion BASE	Advised against accepted
Comebacks and Rework BASE	Rework by reason

Configuration


Settings BASE	The eleven workshop rules
Workshops BASE	Rates, products, journal, hours
Bays BASE	Lifts, test lanes, weight limits
Labour Operations BASE	Your flat rate book
Technicians BASE	Grades, sign off, cost, hours
Check Sheets BASE	Inspection templates
Makes / Models BASE	The vehicle lists
Rate Cards ENTERPRISE ADD-ON	What each kind of account pays
Commission Rules ENTERPRISE ADD-ON	How technicians are paid on output

PART 3 Open the demo and sign in

Everything in this guide can be followed on the live demo. It is a real Odoo 19 database with a workshop, its vehicles and a month of work already on it.

TRY IT YOURSELF ON THE DEMO

1. Open garage-pro.way4tech.com in any browser
2. Sign in with w4demo and Demo2026
3. Click Garage in the app menu, then Workshop, then Job Cards
4. Switch to the kanban view to see the jobs by stage




1 BASE

Go to the workshop

Open **garage-pro.way4tech.com**. The sign-in screen is the standard Odoo one. Enter `w4demo` and `Demo2026` and press Log in.

The same login works on garage-demo.way4tech.com, a second copy of the same workshop.




2 BASE ENTERPRISE ADD-ON

The two modules

In Apps, search for Garage. **Garage Management** is the base and **Garage Management Enterprise** is the add-on. Installing the base brings Inventory and Invoicing with it, because a part is stock and a job ends in an invoice.

The add-on depends only on the base. Install it at any time; nothing in the base changes until you do.



3 BASE

Find the job cards

Open **Garage** from the app menu. It lands on **Workshop > Job Cards**, filtered to open work. Each row shows the number, when it was booked in, the registration, the customer, the kind of work, the lead technician, the promised time, the total and the stage.

Job numbers start with the workshop's code, AQ here, so a group with several sites reads the branch off the number.

PART 4 Set the workshop up from zero

BASE

What a new workshop does on day one, before the first car comes in: the eleven settings, the workshop with its rates, the bays, the labour book, the technicians and the check sheets. On the demo this is already done, so read it to see what each setting means and where it lives.

IN THIS PART YOU WILL LEARN


- The eleven workshop rules in Settings and a sensible value for each
- The workshop record: labour rate, cost rate, sundries, journal, parts store and hours
- Bays: lifts, approved test lanes and weight limits, and what they refuse
- The flat rate labour book: operations, categories, skill levels and intervals
- Technicians: grade, sign off rights, tester licence, cost and contracted hours
- Check sheets, makes and models

TRY IT YOURSELF ON THE DEMO

1. Open Garage > Configuration > Workshops and open Al Quoz Auto Care
2. Look at the labour rate and the sundries percentage
3. Open Labour Operations and find an operation that needs a lift
4. Open Technicians and compare the grades and who can sign off

Settings: the rules the workshop runs on BASE

Garage > Configuration > Settings (an Odoo administrator only). The page has four blocks: **On the Ramp**, **Vehicles**, **Chasing Work** and **Courtesy Cars**. The values are kept per company.




BASE **Configuration > Settings.** Every rule the front desk and the ramps are held to sits on this one page.


SETTING	WHAT IT DOES	DEFAULT
Distance Unit	Kilometres or miles. Every odometer, interval and printout uses it.	Kilometres
Signed Authority Before Work	Start Work is refused until the authority is recorded: who authorised it and how (in person, phone, email, message or signed on screen).	On
Second Pair of Eyes on Quality Check	The lead technician cannot pass their own job at the quality check. Turn off only in a one person workshop.	On
Target Efficiency (%)	A job whose sold hours over clocked hours falls under this is flagged as below target.	100
Service Interval (months)	Used for the next service reminder when the operation has no interval of its own.	12
Service Interval (distance)	The distance side of the same interval. The reminder fires on whichever comes first.	15,000
VIN Must Be 17 Characters	Refuse a VIN that is not 17 characters long. Leave off for older vehicles.	Off
Chase Reminders (days ahead)	How far ahead of the due date the daily job emails the owner.	21
Chase Certificates (days ahead)	How far ahead an expiring test certificate is chased, and the window that colours a vehicle as due soon.	30
Chase Estimates After (days)	An estimate left unanswered this long gets a call activity for the workshop manager or the advisor.	3
Courtesy Car Grace (hours)	How late a loan car can be back before it counts as overdue.	2

The workshop BASE

Configuration > Workshops. One record per site. A group with several branches has one workshop each, all in the same company or in different companies.



BASE **Workshops.** One site on the demo, with its bays and open jobs.



BASE **The workshop form.** Rates, products, journal, stock and hours.

FIELD	WHAT IT IS FOR
Code	Prefixes every job card number, for example AQ/JOB/2026/00017. Unique per company.
Labour Rate / Hour	What an hour of labour sells for. Every operation is priced as its flat hours times this rate.
Labour Cost / Hour	What an hour on the ramp costs you (managers only). Used for gross profit when the technician on the line has no cost of their own.


Labour Product	A service product used for a labour line whose operation has no product, so revenue lands in the right account with the right tax.
Sundries Product and Sundries (%)	Consumables recovered as a percentage of chargeable labour, invoiced under this product. Zero turns it off.
Billing Journal	The sales journal the job invoices go to.
Parts Issue Operation and Parts Store	The outgoing stock operation and the shelf used when parts are drawn onto a job.
Opens At / Closes At	A car booked in is promised back at the closing time that day, or the next day if it came in after closing.
Workshop Manager	Receives the call activity when an estimate is left unanswered.

Bays BASE


Configuration > Bays. A bay is a ramp, a pit, a test lane or any place a car stands while it is worked on. Three settings on a bay are rules, checked when a job is put into it:

- **Has a Lift**: a job with an operation marked *Needs a Lift* is refused in a bay without one.
- **Approved Test Lane**: only an approved lane can take a roadworthiness test job.
- **Max Weight (t)**: a vehicle whose kerb weight is over the rating is refused.

A bay also has a kind (general, two post lift, four post lift, pit, test lane, diagnostic, tyre bay, body shop or valet), a colour for the board, and shows the job on the ramp now. Two jobs cannot book the same bay over overlapping *Bay From / Bay Until* windows.



BASE **Bays.** The demo has four ramps and a test lane.




BASE **A bay.** Lift, test lane approval, weight limit and the job on it now.


The labour book: operations BASE

Configuration > Labour Operations. This is your own flat rate book. Each operation has a name, an optional franchise code, one of twelve categories (servicing, engine, brakes, steering and suspension, transmission, electrical, air conditioning, exhaust, tyres, bodywork, diagnostics, roadworthiness), and:

FIELD	WHAT IT DOES
Flat Rate (h)	What the book says the job takes and what the customer pays for.
Labour Product	Invoiced when the job is billed, so servicing and bodywork can post to different accounts.
Needs a Lift	Checked against the bay before work starts.
Skill Level	The lowest technician grade allowed on the line: apprentice, technician, senior or master.
Repeat Every (months / distance)	For scheduled work such as a cambelt. Sets the next reminder; zero uses the company default.



BASE **Labour Operations.** The demo book, grouped by category.




BASE **An operation.** Flat hours, product, lift, skill and interval.


Technicians BASE

Configuration > Technicians. A technician is not the same as an Odoo user. Link the two with **Odoo User** and the technician sees only their own job cards and clocks.

FIELD	WHAT IT DOES
Clock Number	Printed on the job card.
Grade	Apprentice, technician, senior or master. A labour line is refused if the operation needs a higher grade.
Can Sign Off Quality	Only these people can be named at the quality check.
Tester Licence	Managers only. Only a technician with a licence number can be named on a roadworthiness certificate.
Cost / Hour	Managers only. Drives the labour cost side of gross profit and the cost of each time log.
Contracted Hours / Week	The attended hours used for recovery.
Sold, Clocked, Efficiency, Recovery	Worked out over the last 28 days, shown on the form and in the list.




BASE **Technicians.** Four on the demo, with their 28 day figures.




BASE **A technician.** Grade, sign off, licence, cost and contracted hours.

Check sheets BASE

Configuration > Check Sheets. A check sheet is the template an inspection is loaded from. It has a kind (vehicle health check, service check sheet, pre test check, pre delivery inspection, body damage report) and a list of items. Each item sits in one of nine sections (under the bonnet, under the vehicle, brakes, tyres, steering, lights, interior, body and glass, road test), may say what it is **Measured In** (mm of pad, percent of coolant), carries the operation quoted if it comes back red or amber (**Work If Advised**) and a line of guidance. The module installs a 23 item Vehicle Health Check ready to use.




BASE **Check Sheets.** The templates and how many items each holds.




BASE **A check sheet.** Items by section, with the work each one sells.

Makes and models BASE

Configuration > Makes and Models. Twenty common makes are installed (Audi to Volvo, each with a short code). A model belongs to a make and carries a body type, from hatchback to motorcycle. A vehicle's model must belong to its make, and changing the make clears a model that does not.



BASE **Makes.** Installed with the module, each with its models.



BASE **Models.** Make, name and body type.

Products, stock and accounts BASE

The module uses standard Odoo records for everything it sells. Labour operations, sundries and loan car hire are **service products**; parts are **storable products** with a sale price and a cost; taxes come from the products, narrowed to the job's company. Set the sales journal and the outgoing parts operation on the workshop and the rest follows.

PART 5 Vehicles and their history

BASE


The vehicle, not the customer, is what a workshop remembers. One customer can own several vehicles, and each vehicle carries every job, inspection, reading and certificate it has had.

IN THIS PART YOU WILL LEARN


- Every field on the vehicle record, and the ones held behind the advisor group
- The odometer history and why a reading cannot go backwards
- Warranty by date or by distance, whichever ends first
- The vehicle's test status, last service and lifetime spend

TRY IT YOURSELF ON THE DEMO


1. Open Garage > Vehicles > Vehicles and switch to the kanban view
2. Open Dubai A 23417 and look at the smart buttons at the top
3. Open the Odometer tab and then the History tab



BASE **Vehicles, list.** Registration, make and model, owner, reading, test status.



BASE **Vehicles, kanban.** The same vehicles as cards.




1 BASE

Open a vehicle

Vehicles > Vehicles, then a registration. The header holds the registration, make, model, variant and year. Smart buttons open the vehicle's job cards, inspections and open reminders.

A vehicle's name reads as registration, make, model and year, so it is easy to find from any job.




2 BASE

Odometer history

The **Odometer** tab lists every reading with its date and where it came from: a job card, an inspection, a roadworthiness test, a courtesy car or typed in. The latest reading is the vehicle's odometer.


A reading lower than one already on file for an earlier date is refused unless it is ticked as a correction, for example after a cluster swap.



3 BASE

Certificates


The **Certificates** tab lists the roadworthiness tests. The newest pass sets **Test Expires** and the **Test Status**: not on file, valid, due soon (inside the chase window in Settings) or expired.



4 BASE

Inspections


Every health check run on the vehicle, with its result and the value of the work advised.



5 BASE

Reminders

What is due next: service, test, cambelt, brake fluid and the rest, by date and by reading.



6 BASE

History


Every job card on the vehicle, newest first. The job form also shows a short **Seen Before** note with the last four finished visits.

The fields on a vehicle BASE

GROUP	FIELDS
Identity	Registration (required), VIN (no spaces; 17 characters if the setting is on), make, model, variant, year (1900 to two years ahead), first registration, colour, photo
Technical	Body type (from the model), engine code, engine size, fuel (petrol, diesel, LPG, hybrid, plug-in hybrid, electric, hydrogen), transmission (manual, automatic, CVT, dual clutch, semi automatic), gears, drive (front, rear, all wheel), doors, seats, kerb weight, tyre size
Ownership	Owner (required), home workshop, Garage Vehicle (one of yours: a loan car, a recovery truck, the parts van)
Readings	Odometer and its date, both from the odometer history
Warranty	Warranty ends on (date) and at (reading). Under warranty is true until whichever comes first.
Service	Last service date and reading, from the last finished service job

Advisor only	Key / radio code (immobiliser or radio code, held here rather than on the job sheet) and lifetime spend (the untaxed total of invoiced jobs)
Notes	Standing notes about the vehicle

> When a vehicle that is under warranty is picked on a new job card, the job is ticked as warranty work with the reason *Manufacturer Warranty* straight away.



Date	Vehicle	Reading	Unit	Source	Job	Is Correction
Nov 4	Dubai M 83312 BMW 5 Series (2018)	94,558.00	Kilometres	Job Card	AQ/JOB/2026/00154 - Dubai M 83312	
Nov 4	Dubai P 30211 Toyota Hiace (2022)	93,909.00	Kilometres	Job Card	AQ/JOB/2026/00151 - Dubai P 30211	
Nov 4	Dubai M 83312 BMW 5 Series (2018)	91,039.00	Kilometres	Job Card	AQ/JOB/2026/00121 - Dubai M 83312	
Nov 4	Dubai K 15580 Toyota Corolla (2016)	82,268.00	Kilometres	Job Card	AQ/JOB/2026/00142 - Dubai K 15580	
Nov 4	Dubai J 91205 Nissan Patrol (2023)	76,686.00	Kilometres	Job Card	AQ/JOB/2026/00125 - Dubai J 91205	
Nov 4	Dubai J 91205 Nissan Patrol (2023)	75,550.00	Kilometres	Job Card	AQ/JOB/2026/00124 - Dubai J 91205	
Nov 4	Dubai H 37741 Toyota Land Cruiser (2022)	65,287.00	Kilometres	Job Card	AQ/JOB/2026/00120 - Dubai H 37741	
Nov 4	Dubai G 60913 Hyundai Accent (2021)	64,825.00	Kilometres	Job Card	AQ/JOB/2026/00128 - Dubai G 60913	
Nov 4	Dubai F 42156 BMW 5 Series (2020)	58,057.00	Kilometres	Job Card	AQ/JOB/2026/00146 - Dubai F 42156	
Nov 4	Dubai F 42156 BMW 5 Series (2020)	56,624.00	Kilometres	Job Card	AQ/JOB/2026/00122 - Dubai F 42156	
Nov 4	Dubai D 18820 Toyota Hiace (2019)	50,695.00	Kilometres	Job Card	AQ/JOB/2026/00130 - Dubai D 18820	
Nov 4	Dubai D 18820 Toyota Hiace (2019)	47,243.00	Kilometres	Job Card	AQ/JOB/2026/00123 - Dubai D 18820	
Nov 4	Dubai C 70384 Toyota Corolla (2018)	43,239.00	Kilometres	Job Card	AQ/JOB/2026/00127 - Dubai C 70384	
Nov 4	Dubai A 23417 Toyota Land Cruiser (2016)	27,465.00	Kilometres	Job Card	AQ/JOB/2026/00141 - Dubai A 23417	
Nov 4	Dubai Z 19020 Toyota Yaris (2023)	25,535.00	Kilometres	Job Card	AQ/JOB/2026/00137 - Dubai Z 19020	
Nov 4	Dubai Z 19020 Toyota Yaris (2023)	24,225.00	Kilometres	Job Card	AQ/JOB/2026/00135 - Dubai Z 19020	
Nov 4	Dubai Z 19020 Toyota Yaris (2023)	21,161.00	Kilometres	Job Card	AQ/JOB/2026/00086 - Dubai Z 19020	
Nov 2	Dubai B 51209 Nissan Patrol (2017)	31,774.00	Kilometres	Job Card	AQ/JOB/2026/00161 - Dubai B 51209	
Oct 28	Dubai M 83312 BMW 5 Series (2018)	92,060.00	Kilometres	Job Card	AQ/JOB/2026/00154 - Dubai M 83312	

BASE **Vehicles > Odometer Readings** (advisors and above). Every reading on every vehicle in one list, filterable by source.

PART 6 Book the car in and price the job

BASE


A job card is opened as an estimate while the customer is at the desk or on the phone. This part walks every field on the form and how labour, parts and sundries add up to the total.

IN THIS PART YOU WILL LEARN

- Opening a job card: customer, vehicle, reading in, fuel and the reported fault
- What the promised time is and how it is set
- Labour lines from the flat rate book, and why the grade is checked
- Parts lines with availability, supplier reference and warranty
- How sundries, tax and the total are worked out

TRY IT YOURSELF ON THE DEMO

1. Open Workshop > Job Cards and open AQ/JOB/2026/00023, an estimate
2. Open the Labour tab and read the hours and the rate
3. Open the Parts tab and look at On Hand for each part
4. Do not press any button; just read the figures




1 BASE

Open a new job card

Workshop > Job Cards > New. Pick the **Vehicle** first: the **Customer** fills in from the owner and **Reading In** from the last odometer reading. The vehicle list only offers the customer's own vehicles and the garage's own vehicles.

The job is saved as an Estimate with a number from the workshop code. It cannot be created at any later stage.




2 BASE

What was wrong

The **What Was Wrong** tab keeps three texts apart: the **Reported Fault** in the customer's words, the **Diagnosis**, and the **Work Carried Out**. The last one is printed on the invoice and is required before the quality check.

A warranty claim and a comeback are argued on the difference between what was reported and what was found, so keep them separate.




3 BASE

Add the labour

On the **Labour** tab, add a line and pick an **Operation**. The description, the **Sold Hours** (the flat rate) and the **Rate** (the workshop rate) fill in, with the tax from the operation's product. Set the technician, a discount, or untick **Chargeable** for warranty or goodwill work.

A technician whose grade is below the operation's skill level is refused on the line.



4 BASE

Add the parts

On the **Parts** tab, pick a product. The sale price, the cost and the taxes fill in from the product. **On Hand** shows stock now, and the line is flagged if there is not enough. Add the **Supplier Reference** and the **Warranty (months)**, twelve by default.

The warranty end date is counted from the day the job is handed back. It is what tells you whether a comeback is a parts claim.

The fields on the job card BASE

GROUP	FIELD	WHAT IT DOES
Customer and Vehicle	Customer, Vehicle, Registration, VIN	The vehicle must belong to the customer unless it is a garage vehicle.
	Reading In / Reading Out	Reading in is required and logged on the vehicle. Lower than the vehicle's last reading is refused. Reading out defaults to reading in when the job passes.
	Fuel Level	Empty, quarter, half, three quarters or full, recorded on arrival.
The Job	Workshop, Bay	The bay must suit the job: a test lane for a test, a lift for work from underneath, a weight rating above the kerb weight.
	Job Kind	Service, repair, diagnostic, roadworthiness test, tyres, bodywork, recall or sale preparation. A service job rolls the service reminder forward when it passes.
	Priority, Customer Waiting	Urgent jobs and customers sitting in reception jump the queue on the board.
	Service Advisor, Lead Technician	The advisor defaults to you. The lead technician owns the job; others can still clock on.
	Waiting For	Nothing, parts, customer authority, warranty approval, diagnosis or a free bay. The first thing a foreman reads on the board.
Timing	Booked In, Date Promised	Promised defaults to the workshop's closing time that day, or the next day if the car came in after closing. A promise before booking in is refused.
	Bay From / Bay Until	A bay booking window. Two live jobs cannot overlap in the same bay.
Progress	Estimate sent, approved, started, finished, checked, ready, delivered	Stamped by the buttons, read only. The card shows a LATE ribbon once the promised time passes.

HOW IT WORKS

How the total is worked out

Labour	sold hours × rate, less the line discount, through the line taxes. Not chargeable lines count as zero.
+ Parts	quantity × sale price, less the discount, through the line taxes
+ Sundries	the workshop percentage of chargeable labour, taxed like the first chargeable labour line
= Total	**untaxed, tax and total kept separately on the Money tab**

All tax is computed through the Odoo tax engine. Product taxes are narrowed to the job's company, so a group with two trade licences never puts one company's tax on the other's job.

PART 7 The estimate and the customer's authority

BASE


Nothing goes on the ramp until the customer has said yes to a figure, and the job card records who said it and how. This part is the front desk's half of the job.

IN THIS PART YOU WILL LEARN

- Send Estimate: what it sets and what the customer receives
- Record Authority: the name, the method and the signature
- The authority ceiling and the warning when the job grows past it
- Ask for More Authority when extra work is found
- Everything Start Work checks before the car goes on a ramp

TRY IT YOURSELF ON THE DEMO

1. Open AQ/JOB/2026/00021, which is Awaiting Approval
2. Open the Authority tab and read who authorised it and how
3. Open AQ/JOB/2026/00019, which is Approved, and look at the buttons




1 BASE

Send the estimate

Press **Send Estimate** on an estimate that has at least one labour or parts line. The job moves to **Awaiting Approval**, **Waiting For** becomes *Customer Authority*, and if the customer has an email address the *Estimate for Approval* email goes out with the labour, parts and total. **Authorised Up To** is set to the total if it was empty.

Only a service advisor or above can send an estimate, record authority, invoice or cancel. A technician sees the buttons refused.




2 BASE

Record the authority

On the **Authority** tab, type who said yes in **Authorised By**, pick the method (in person, by phone, by email, by message or signed on screen), set **Authorised Up To** and, at the counter, have the customer sign in the **Signature** box. Then press **Record Authority**.

Record Authority is refused without a name and a method. It is the only defence when a bill is disputed.



3 BASE

Approved

The job is now **Approved**, the approval date is stamped and the chatter says who authorised it and up to what amount. **Start Work** and **Draw the Parts** appear.


What Start Work checks BASE

Pressing **Start Work** puts the job **In Progress** and stamps the start time, but only if:

1. the job is **Approved**;
2. with *Signed Authority Before Work* on, the authority has a name and a method, or a signature;
3. the job is not worth more than **Authorised Up To**; a yellow banner on the card already warns when it is;
4. the job has a **Bay**, so the board shows where the car actually is.

Extra work found on the ramp BASE

When the technician finds more, add the labour and parts, then press **Ask for More Authority**. The job goes back to **Awaiting Approval**, the approval date is cleared and the chatter records the new total against the old authority. Ring the customer, raise **Authorised Up To**, record the authority again and carry on.



BASE **A job that grew past its authority.** The yellow banner says the card is worth more than the customer authorised. Start Work would be refused until the authority is raised.

PART 8 On the ramp: clocking, parts and the board

BASE


Once the car is on a ramp, two things matter: the hours the technicians actually spend, and the parts that come off the shelf. Both are recorded against the job card.

IN THIS PART YOU WILL LEARN

- Clocking on and off against a job and against one operation
- The seven time log activities and why waiting and rework are kept apart
- The one clock at a time rule and the overnight clean up
- Draw the Parts: the stock transfer the job raises
- The Workshop Board and what the cards show

TRY IT YOURSELF ON THE DEMO

1. Open Workshop > Workshop Board
2. Find a card marked Late and one marked Comeback
3. Open Workshop > Time Logs and group by technician




1 BASE

Clock on

On the job's **Time** tab, add a line. The technician defaults to the one linked to your user. Pick the **Operation** where you can, and the activity: repair, servicing, diagnostics, road test, waiting on parts, rework or valet. **Clocked On** is now.

A technician can only be on one clock at a time. Clocking on to a second job while the first is running is refused.




2 BASE

Clock off

Press **Clock Off** on the running line, here or in Workshop > Time Logs. The hours are worked out from the two times, and the cost from the technician's cost per hour (managers only).

A single log over 24 hours is refused. Every six hours a job closes any clock left running for twelve hours at eight hours, and notes it on the job.



3 BASE

The Workshop Board

Workshop > Workshop Board shows the open jobs as cards by stage, with the registration, customer, number, bay, lead technician and total, and badges for Late, Customer Waiting, Comeback and the waiting reason.

Dragging a card to another column is refused: a job moves only by its buttons.


Drawing the parts BASE

Press **Draw the Parts** on an approved or in progress job. The module creates one delivery from the workshop's **Parts Store** to the customer location, using the **Parts Issue Operation**, with one move per storable part, then confirms and reserves it. The transfer opens, and a **Parts Issue** smart button stays on the job. Validate it in Inventory when the parts are handed over. Parts can be drawn once per job; a second issue is made from Inventory.

> **Parts available** on the job is true only when every part is on the shelf. A user who cannot read stock still opens the job card; the availability simply shows as not known.

Efficiency on the job BASE

The job adds up its sold hours (labour lines) and its clocked hours (time logs). **Efficiency** is sold over clocked, per line and per job. A job under the company's target efficiency is flagged **below target** and listed under *Took Longer Than the Book*.



BASE **A time log.** Job, operation, technician, activity, clocked on and off, hours and cost.

PART 9 Quality check, ready and the invoice

BASE


The job is not finished when the spanner goes down. It is written up, checked by somebody who did not do it, signed off, and only then billed.

IN THIS PART YOU WILL LEARN

- Finished, Check It: the three things it insists on
- Pass and Send It Back, and the second pair of eyes
- What passing does to the vehicle: reading, reminders and the ready email
- The invoice: labour and parts as sections, sundries, loan car hire
- Cancel and Back to Estimate

TRY IT YOURSELF ON THE DEMO


1. Open AQ/JOB/2026/00018, at Quality Check
2. Open AQ/JOB/2026/00039, which is Ready, then AQ/JOB/2026/00038, Invoiced
3. On the invoiced job, press the Invoice smart button and look at the sections



1 BASE

Finished, check it

Press **Finished, Check It**. It is refused while anybody is still clocked on, while any labour line has no technician, or while **Work Carried Out** is empty. Otherwise the job moves to **Quality Check** and the finish time is stamped.




2 BASE

Pass the check

Put a name in **Signed Off By** and press **Pass**. The job is **Ready**, Reading Out defaults to Reading In, the reading is logged on the vehicle, and the *Vehicle Ready* email goes to the customer.

Refused unless the person can sign off quality, is not the lead technician (with the second pair of eyes on), and, for a technician, is the person signed in.




3 BASE

Invoice

Press **Invoice** on a ready job. One customer invoice is created in the workshop's journal and opens. The job becomes **Invoiced** and the delivery time is stamped. An **Invoice** smart button stays on the job.

Refused while a courtesy car on the job is still out. Book it back in first.



4 BASE

What is on the invoice


A **Labour** section with one line per chargeable operation (hours as quantity, rate as price), a *Workshop sundries* line, a **Parts** section with the supplier reference in brackets, and any chargeable courtesy car hire. The reported fault and the work carried out go in the notes.

Send it back BASE

At the quality check, write what is wrong in **Quality Notes** and press **Send It Back**. The job returns to **In Progress**, the fail count goes up by one and the reason is posted in the chatter. The failure count stays on the job so rework shows up in the numbers.

What passing a service job does BASE


When a **Service** job passes, every open service reminder on the vehicle is closed as done and settled by this job, and a new one is set: due on the date and at the reading worked out from the first operation's interval, or the company default. So the next service is booked in the system the moment this one is signed off.



BASE **The Money tab.** Labour, parts, sundries, untaxed, tax and total, and for managers the cost and profit split: labour profit, parts profit, gross profit and margin, with sold and clocked hours.

Cancel and start again BASE

Cancel is refused while the job has an invoice that is not cancelled, or once parts have actually been issued (return them in Inventory first). A parts transfer that is not done yet is cancelled with the job. **Back to Estimate** brings a cancelled job back as an estimate and lets go of a cancelled invoice so it can be billed again.



BASE **The Notes tab.** Internal notes that never reach the customer.

PART 10 Warranty work and comebacks

BASE


Two kinds of job nobody wants to pay for: work under a warranty, and a car that came back. The module makes both visible as numbers rather than as feelings.

IN THIS PART YOU WILL LEARN

- Marking a job as warranty work and saying who pays
- Raising a comeback from the original job
- The six comeback reasons and the rules that protect the count
- Where rework shows up in the reports

TRY IT YOURSELF ON THE DEMO

1. Open AQ/JOB/2026/00025, a comeback in progress
2. Open its Warranty and Comeback tab and follow the link to the original job
3. Open Reporting > Comebacks and Rework




1 BASE

Warranty work

On the **Warranty and Comeback** tab, tick **Warranty Job** and pick who pays: manufacturer warranty, parts supplier warranty, our own workmanship, goodwill or an extended warranty policy. Add their **Claim Reference**. Untick **Chargeable** on the lines nobody pays for; their cost still counts.

A warranty job without a reason is refused. A vehicle under warranty ticks it for you when it is picked.



2 BASE


Raise a comeback

On a ready or invoiced job, press **Raise a Comeback**. A new estimate opens on the same customer and vehicle, linked back in **Comeback On**, with the reason *Workmanship*, the reading from the vehicle and the complaint *Returned after* the original number.


If a part from the original job is still inside its warranty, the reason suggests Part Failed instead.

COMEBACK REASON	MEANING
Part Failed	A part fitted last time failed. Check its warranty end date.
Work Not Completed	Something on the job was not done.
Wrong Diagnosis	The fault was not what we said it was.
Workmanship	Done, but not done well.
Unrelated Fault	A new fault, counted so the figure stays honest.
Customer Expectation	Nothing wrong with the work, but the customer expected something else.

A comeback must name its original job and a reason, cannot be a comeback on itself, and must be on the same vehicle. The original job shows a **Comebacks** smart button with the count.



BASE **Reporting > Comebacks and Rework.** Every comeback with its reason, technician and original job, also as a pivot by reason and technician.



BASE **A roadworthiness test job.** Job kind *Roadworthiness Test* can only be put in a bay marked as an approved test lane.

PART 11 The vehicle health check

BASE


The check sheet is where a service turns into a repair. Every item gets a colour and a reason, every red or amber item carries a price, and the customer's yes goes straight onto the job.

IN THIS PART YOU WILL LEARN


- Starting an inspection from a job and loading a check sheet
- Green, amber, red and not checked, and the rule on amber and red
- Work advised, accepted value and conversion
- Complete, Send to Customer and Add Accepted Work to the Job
- Advised Work: every item across every sheet

TRY IT YOURSELF ON THE DEMO


1. Open Inspections > Check Sheets and open VHC/2026/00001
2. Count the red and amber items and read the measurements
3. Look at Work Advised against Accepted Value at the top
4. Open Inspections > Advised Work and filter on accepted items




BASE **Check Sheets, list.** Number, vehicle, job, technician, result, work advised and conversion.



BASE **Check Sheets, kanban.** The same sheets as cards.





1 BASE

Start the sheet

From a job card press the **Checks** smart button and New, or go to Inspections > Check Sheets > New and pick the **Job Card**. The vehicle, workshop, reading and technician fill in from the job. Pick a **Check Sheet** and press **Load the Check Sheet**: its items drop onto the inspection, skipping any already there.


A reading lower than the vehicle's last reading is refused on the sheet too.

2 BASE

Mark every item

For each item, set **Green** (passes), **Amber** (will need work before long), **Red** (needs work now) or **Not Checked**. Write the **Measurement** or a **Comment**. The **Work Needed** operation comes from the template; its price at your labour rate fills the **Estimate**.


An amber or red item with neither a measurement nor a comment is refused: an advisory on its own sells nothing.



3 BASE

Summary and result

Write two lines in the **Technician Summary** the advisor can read down the phone. The sheet counts red, amber, green and not checked items, and sets the result: *Work Needed Now* if any red, *Work Advised* if any amber, otherwise *No Work Needed*.



4 BASE

Complete and send

Press **Complete** (refused if any item has no colour). The reading is logged on the vehicle. Then **Send to Customer** emails the *Vehicle Health Check* to the owner and marks the sheet Sent. **Print** gives the same sheet on paper.


From yes to labour on the job BASE

When the customer agrees to an item, tick **Accepted** on it. Only amber or red items can be accepted, and only if they carry an operation. Then press **Add Accepted Work to the Job**: each accepted item becomes a labour line on the job card at the operation's flat hours and the workshop rate, with the inspecting technician, and is marked **On the Job** so it is never added twice. The job must still be open, not invoiced or cancelled.

> After adding work, the job is usually worth more than the customer first authorised. The yellow banner appears, and Ask for More Authority is the next step.

The three figures on every sheet BASE

FIGURE	WHAT IT IS
Work Advised	The estimate of every amber and red item, at your labour rate.
Accepted Value	The estimate of the advised items the customer accepted.
Conversion (%)	Accepted value over work advised. The number a health check exists to raise.



BASE **Inspections > Advised Work** (advisors and above). Every amber and red item across every sheet, with its estimate and whether it was accepted and added. The list to ring customers from.

PART 12 Service reminders and test certificates

BASE

The work that comes back on its own: the next service, the cambelt, the annual test. Each is a record with a due date, a due reading, or both, and a daily job that contacts the owner.


IN THIS PART YOU WILL LEARN

- A reminder that fires on the date or the reading, whichever comes first
- The five reminder states and their buttons
- Roadworthiness certificates: schemes, results and the tester rule
- Setting the next test reminder from a certificate

TRY IT YOURSELF ON THE DEMO

1. Open Vehicles > Service Reminders and look at the Due At and Due Date columns
2. Open Vehicles > Roadworthiness Tests and open RWT/2026/00001
3. Read the advisories, the defects and the expiry date

Service reminders BASE




1 BASE

The reminder list

Vehicles > Service Reminders (advisors and above). Each line is a vehicle, a kind (service, roadworthiness test, cambelt, brake fluid, coolant, air conditioning, tyres, warranty work, other), the due date and the due reading, and how far away each is.

A reminder needs a due date, a due reading, or both. One with neither is refused because it would never fire.



2 BASE

A reminder


The form holds the **Work Due** operation, the interval in months and distance (taken from the operation, else the company default), when it was **Last Done** and at what reading, and the job that settled it. The buttons are **Customer Told**, **Booked In**, **Done** and **Cancel**.

A done reminder cannot be cancelled after the fact.

STATE	MEANING	SET BY
Open	Waiting to come due	Created by a passed service job, a certificate, or by hand
Customer Told	The owner has been contacted	The daily email, or Customer Told
Booked In	A job has been booked for it	Booked In
Done	The work was done	A passed service job (for service reminders) or Done
Cancelled	No longer wanted	Cancel

Every day the *service reminders due* job looks at open reminders. One whose due date falls inside the *Chase Reminders* window, or whose vehicle has already reached the due reading, is emailed to the owner with the *Service Reminder* template and marked Customer Told.


Roadworthiness certificates BASE



3 BASE

The certificates

Vehicles > Roadworthiness Tests. One record per certificate, with the vehicle, scheme, test date, expiry, result and certificate number.



4 BASE

A certificate

Pick the **Scheme**: MOT (United Kingdom), ITV (Spain), Fahes (Qatar), RTA Vehicle Test (UAE), Hauptuntersuchung (Germany), Controle Technique (France), Roadworthy Certificate or other. Set the test date (the expiry defaults to a year less a day), the result (pass, pass with advisories, fail), the certificate number, the tester, the station and the reading at test. Advisories and defects are kept apart.

A pass needs its certificate number. Only a technician with a tester licence can be named. The reading at test is logged on the vehicle.

Press **Set the Next Reminder** on a pass to put the next test on the reminder list, due on the expiry date. A failed test is refused: record the retest first. Every day the *certificates about to expire* job emails the owner of each vehicle whose newest certificate expires inside the *Chase Certificates* window, once per certificate.

PART 13 Courtesy cars

BASE


A handful of loan cars handed out while the customer's own car is in. The module books them out and back with the fuel and the reading, works out the hire charge, and puts it on the job invoice.

IN THIS PART YOU WILL LEARN

- Setting up a loan car: rate, free days, mileage limit, excess and cover
- Booking a loan, handing the keys over and booking it back in
- How the hire charge is worked out
- What stops a car being double booked or sent out uncovered

TRY IT YOURSELF ON THE DEMO

1. Open Courtesy Cars > Courtesy Fleet and open the Toyota Yaris
2. Open Courtesy Cars > Loans and open CCL/2026/0001
3. Read the days, the free days and the hire charge




1 BASE

The loan car

Courtesy Cars > Courtesy Fleet. A loan car is one of your own vehicles (ticked Garage Vehicle) with a status (in service, off the road, off fleet), a product for the hire line, a **Daily Rate**, **Free Days** that come with a job, a daily **Mileage Limit**, an **Excess Rate** per unit of distance and the insurance expiry.

A car cannot go out on or after the day its cover lapses.




2 BASE

Book it out

Courtesy Cars > Loans > New. Pick the car, the job card (the customer fills in), the driver licence, the out and due back times, the reading and fuel out, and walk round the car for the **Damage** note. Press **Hand the Keys Over**: the loan is *With the Customer*.

A car already booked or out over the same period is refused, and so is one marked off the road.



3 BASE

Book it back in

When the car comes back, enter the reading and fuel in and press **Book It Back In**. Both are required. The loan is *Returned*, the return time is stamped and the reading is logged on the loan car.


Came Back Short is ticked when the fuel came back lower than it went out.

HOW IT WORKS

How the hire charge is worked out

Days	from out to returned (or due back), any part of a day counted as a day, at least one
Chargeable days	days less the car's free days
Excess distance	distance driven less the mileage limit times the days
Hire Charge	**chargeable days × daily rate + excess distance × excess rate**

A returned loan with a charge becomes a line on the job invoice. A job cannot be invoiced while its loan car is still out. Every four hours a job posts a note on any loan past its due time plus the grace hours in Settings.



BASE **Courtesy Fleet.** The demo has one loan car, currently out.

PART 14 Reports

BASE


Five reports under Reporting (managers only), plus the pivot and graph views on the job cards. Every one is a standard Odoo list, pivot or graph, so it can be filtered, grouped and exported.

IN THIS PART YOU WILL LEARN


- Gross profit by job, month and workshop
- Labour recovery: sold against clocked, per technician
- Parts used, inspection conversion and comebacks
- Technician efficiency and recovery over 28 days

TRY IT YOURSELF ON THE DEMO


1. Open Reporting > Gross Profit and expand a month
2. Open Reporting > Labour Recovery and switch to the pivot
3. Open Reporting > Inspection Conversion




BASE **Gross Profit, pivot.** Labour, parts and gross profit by month and workshop.




BASE **Gross Profit, graph.** The same figures over time.




BASE **Labour Recovery, list.** Every labour line: technician, sold and clocked hours, efficiency.




BASE **Labour Recovery, pivot.** Sold against clocked by technician.




BASE **Parts Used.** Every part fitted, its quantity, price and cost.



BASE **Inspection Conversion.** Work advised against accepted, per technician and month.



BASE **Job Cards, pivot.** Any measure on the job, grouped any way.



BASE **Job Cards, graph.** Jobs and totals over time.

REPORT	BUILT ON	USE IT FOR
Gross Profit	Job cards (pivot, graph, list)	Labour profit, parts profit and margin per job, month or workshop
Labour Recovery	Labour lines (list, pivot)	Sold against clocked hours per technician and operation
Parts Used	Parts lines (list, pivot)	What went on which cars, at what price and cost
Inspection Conversion	Inspections (pivot, list)	How much advised work the front desk actually sells
Comebacks and Rework	Comeback jobs (list, form, pivot)	Rework by reason and by technician
Time Logs	Time logs (list, pivot)	Hours by activity, including waiting and rework
Technicians	Technician list	Sold, clocked, efficiency and recovery over the last 28 days

Cost and profit figures are held behind the Workshop Manager group. An advisor running the same views sees revenue and hours but not the cost side.

PART 15 Printed documents and emails

BASE

Three printed documents and five emails. Each print is an A4 page in the company's layout; each email is a standard Odoo template you can reword.

The job card BASE



AL QUOZ AUTO CARE

Al Quoz Auto Care LLC
Warehouse 14, Street 8A
Al Quoz Industrial Area 3
Dubai DU
United Arab Emirates
TRN: 1000 0000 0000 003

Job Card AQ/JOB/2026/00017

Customer: Daniel Okonkwo
Phone: +971 56 218 7741
Vehicle: Dubai F 42156 BMW 5 Series (2020)
Registration: Dubai F 42156
VIN: WBA5R000012031676
Engine: B48 (2.0 l)

Booked in: 02/10/2026 02:52:00 PM
Promised: 03/10/2026 12:00:00 AM
Reading in: 49903 Kilometres
Fuel: Half
Bay: Bay 1
Technician: Rajesh Kumar

Reported fault
Service light on the dash.


Work to be carried out

Operation	Hours	Technician	Done
Full service	2.00	Rajesh Kumar	☐
Interim service (Brake fluid moisture content)	1.20	Rajesh Kumar	☐
Interim service (Auxiliary belt and pulleys)	1.20	Rajesh Kumar	☐
Interim service (Tyre, near side front)	1.20	Rajesh Kumar	☐
Interim service (Tyre, near side rear)	1.20	Rajesh Kumar	☐
Interim service (All exterior lights)	1.20	Rajesh Kumar	☐
A/C regas and leak check (Air conditioning output)	1.50	Rajesh Kumar	☐

Parts

BASE **Print Job Card.** Customer, vehicle, registration, VIN, engine, booked in, promised, reading in, fuel, bay and technician; the reported fault; the work to be carried out with hours, technician and a Done box; the parts with supplier reference and a Fitted box; and room for the diagnosis and the work carried out. This is the sheet that goes on the ramp with the car.

The estimate BASE



AL QUOZ AUTO CARE

Al Quoz Auto Care LLC
Warehouse 14, Street 8A
Al Quoz Industrial Area 3
Dubai DU
United Arab Emirates
TRN: 1000 0000 0000 003

Estimate AQ/JOB/2026/00021

James O'Connell
Dubai K 15580 Toyota Corolla (2016)
VIN JTDBR000012063352

Date 03/10/2026
Reading 74583 Kilometres

Reported fault: Grinding noise from the front under braking.

Description	Qty	Unit	Amount
Labour			
Interim service	1.20 h	175.00 AED	210.00 AED
Parts			
Oil filter	1.0	45.00 AED	45.00 AED
Engine oil, 5W30 fully synthetic (litre)	4.0	38.00 AED	152.00 AED


Sundries	6.30 AED
Subtotal	413.30 AED
Tax	20.67 AED
Total	**433.97 AED**

This estimate holds for fourteen days. Prices assume the fault is as described above. If we find something else once the vehicle is stripped we will ring you before going any further.

Al Quoz Auto Care LLC | TRN 1000 0000 0000 003 | +971 4 000 0000 | service@example.com

BASE **Print Estimate.** The reported fault, what we found, and every labour and parts line with quantity, unit price and amount, with the total. Hand it over or attach it to the estimate email.

The vehicle health check BASE



AL QUOZ AUTO CARE

Al Quoz Auto Care LLC
Warehouse 14, Street 8A
Al Quoz Industrial Area 3
Dubai DU
United Arab Emirates
TRN: 1000 0000 0000 003

Vehicle Health Check

Dubai A 23417 Toyota Land Cruiser (2016)
Ahmed Al Falasi
Job card AQ/JOB/2026/00001

VHC/2026/00001
03/10/2026 03:39:32 PM
Reading 24400 Kilometres
Checked by Rajesh Kumar

Now: 3 Soon: 5 Fine: 15

Result	Item	Measured	Comment	To put right
GREEN	Engine oil level and condition			210.00 AED
GREEN	Coolant level and strength			210.00 AED
AMBER	Brake fluid moisture content	1 mm	Advised at this visit.	210.00 AED
GREEN	Battery condition and charge			210.00 AED
RED	Auxiliary belt and pulleys	2 mm	Advised at this visit.	210.00 AED
GREEN	Air filter			210.00 AED
GREEN	Front brake pads			175.00 AED
AMBER	Rear brake pads or shoes	2 mm	Advised at this visit.	175.00 AED
GREEN	Brake discs, lipping and scoring			175.00 AED
GREEN	Parking brake travel			175.00 AED
AMBER	Tyre, near side front	2 mm	Advised at this visit.	210.00 AED
GREEN	Tyre, off side front			210.00 AED

BASE **Print on a check sheet.** Each item with its colour, measurement and comment, what it costs to put right, and the technician's summary.

The five emails BASE

TEMPLATE	SENT WHEN	TO
Garage: Estimate for Approval	Send Estimate	The customer, if they have an email address
Garage: Vehicle Ready	Pass at the quality check	The customer

Garage: Service Reminder	The daily reminder job	The vehicle owner
Garage: Certificate Expiring	The daily certificate job	The vehicle owner
Garage: Vehicle Health Check	Send to Customer on a completed sheet	The vehicle owner

Emails are queued and sent by Odoo's mail server, so set up outgoing mail before going live. The estimate and health check emails can be reworded in Settings > Technical > Email Templates.

PART 16 Rate cards: what each account pays

ENTERPRISE ADD-ON


The counter rate is not what a fleet, a trade customer or an insurer pays. A rate card holds the agreed figures, and a job picks it up by itself.

IN THIS PART YOU WILL LEARN


- The five kinds of card and their labour rate
- Pricing a whole category or one named operation
- The parts discount on a card
- Where a job takes its card from

TRY IT YOURSELF ON THE DEMO

1. Open Configuration > Rate Cards and open Harbourside fleet 2026
2. Read the lines: which operations are named, which are by category
3. Press the Accounts button to see who is on the card



ENTERPRISE ADD-ON **Configuration > Rate Cards.** The demo has a retail card, a fleet card and an insurer card.



1 ENTERPRISE ADD-ON

A rate card

Give the card a name and a kind: retail, trade, fleet, insurer or internal. Set the card's **Labour Rate** for any work it does not price on its own lines, a **Parts Discount** taken off the list price of each part, and the dates it is valid. Each line prices either a whole **Category** or one named **Operation** at its own rate.

A line that names neither a category nor an operation is refused, because it prices nothing.

Which rate wins ENTERPRISE ADD-ON

1. A line naming the operation itself always wins, so a price somebody agreed for one job is never undone by a broader line.
2. Otherwise a line for the operation's category.
3. Otherwise the card's own labour rate.

Where a job takes its card from ENTERPRISE ADD-ON

The job's **Rate Card** is taken from its service plan first, then from the customer (the **Labour Rate Card** field on the contact), provided the card is valid today. A labour line created on the job, from code, an import or the health check, starts at the card's rate. A part added on the job takes the card's parts discount when it has none of its own. Clear the card on the job to fall back to the workshop rate.

> The card also has an **Own Sundries Rate** tick and a sundries percentage. On the job, sundries are still worked out at the workshop's percentage.

PART 17 Service plans, AMCs and extended warranties

ENTERPRISE ADD-ON


A plan is money taken up front against work not yet done. The module sells it once and draws it down job by job, so the customer is never billed twice for a service they already paid for.

IN THIS PART YOU WILL LEARN


- The three kinds of plan and what each covers
- Starting a plan and how a job finds it by itself
- Services sold, used and remaining; drawn down value and margin
- Cover that ends on a date or at a reading
- Renewing a batch of plans with a price change


TRY IT YOURSELF ON THE DEMO

1. Open Plans and Claims > Service Plans
2. Open SP/2026/0002, a fleet AMC, and press the Jobs button
3. Open SP/2026/0005, a package, and read the services remaining



ENTERPRISE ADD-ON **Plans and Claims > Service Plans.** Every plan by state: draft, running, used up, expired, cancelled.





1 ENTERPRISE ADD-ON

A service package

New plan: customer, vehicle (or leave it empty for a fleet agreement that covers whatever they bring in), workshop, kind, start and end, an optional **Mileage Limit** and the price it was **Sold For**. Under **What It Covers**, add each service with **How Many** and its retail value. Press **Start It**.

A plan cannot start without at least one line, and cannot end on or before the day it starts.

2 ENTERPRISE ADD-ON


An annual maintenance contract

An **AMC** is open cover for a period, often for a fleet with no vehicle named, and usually comes with a **Rate Card** for work outside the cover. An **Extended Warranty** pays for failures rather than servicing.

How a job draws down a plan ENTERPRISE ADD-ON

When a job is raised, it looks for the customer's running plans in the same company. A plan covers the job if today is inside its dates, the vehicle matches (when the plan names one), the reading in is not past the mileage limit, and for a

package there are services left. A plan naming the vehicle is tried before a fleet plan. The job's **Service Plan** fills in and **Paid By** reads *A Service Plan*. Clear the field to take the job off the plan and charge it normally.




ENTERPRISE ADD-ON **A job on a plan.** Service Plan and Paid By in the header; the filters *On a Service Plan* and *On a Claim* find these jobs in the list.

FIGURE ON THE PLAN	HOW IT IS WORKED OUT
Services Sold	The sum of How Many on every line
Services Used	The number of jobs drawn against the plan that are not cancelled
Remaining	Sold less used, never below zero
Work Drawn Down	The untaxed value of those jobs
Margin	What the plan was sold for less the work drawn down
Days Left	To the end date

When the job on a plan is invoiced, nothing is billed to the customer for it: the plan was the sale. The job is marked Invoiced and a note goes on both the job and the plan. Every day a job closes running plans past their end date as **Expired**, and packages with nothing left as **Used Up**. A plan with jobs drawn against it cannot be cancelled; let it expire.

Renewals ENTERPRISE ADD-ON



3 ENTERPRISE ADD-ON

Renew plans

Select one or more plans in the list (or open one) and choose **Action > Renew Plans.** Set the new term in months (12 by default), a **price change** in percent across the batch, whether to **carry unused** services over, to **start immediately** and to **close the old plans**. Press **Renew**.

The new plan starts the day the old one ends (or today, if later). Carried services go on their own line, Carried over from the old number.

PART 18 Insurance and warranty claims, and the split bill

ENTERPRISE ADD-ON


A claim is a job somebody else pays for, less the excess the owner pays. The module keeps the excess, the approved amount and the shortfall apart, and invoices both parties.

IN THIS PART YOU WILL LEARN

- Raising a claim from the job card
- The claim states and the rule on the claim number
- Excess, approved amount and shortfall
- The two invoices an approved claim raises


TRY IT YOURSELF ON THE DEMO


1. Open Plans and Claims > Claims and open CLM/2026/0001
2. Read the job value, the excess, the approved amount and the shortfall
3. Open CLM/2026/0003, which is settled



Name	Date Repor...	Kind	Job	Vehicle	Pays the Bill	Claim Nu...	Job Value	Excess Paid by...	Approved Am...	Shortfall	State
CLM/2026/...	Sep 29	Manufactu...	AQ/JOB/2026/00023 - Du...	Dubai M 83312 BMW 5 ...	Gulf Union In...		2,752.50 AED	0.00 AED	0.00 AED	0.00 AED	Submitted
CLM/2026/...	Sep 23	Insurance	AQ/JOB/2026/00027 - Du...	Dubai J 91205 Nissan Pa...	Emirates Shie...	ES-77310	5,711.13 AED	350.00 AED	5,361.13 AED	0.00 AED	Settled
CLM/2026/...	Sep 22	Insurance	AQ/JOB/2026/00026 - Du...	Dubai C 70384 Toyota C...	Gulf Union In...	GU-CLM-9...	6,531.38 AED	500.00 AED	5,281.38 AED	750.00 AED	Approved
							14,995.01 AED	850.00 AED	10,642.51 AED	750.00 AED	

ENTERPRISE ADD-ON **Plans and Claims > Claims.** Draft, submitted, approved, refused and settled claims, with the shortfall on each.





1 ENTERPRISE ADD-ON

Raise the claim

On the job card press **Raise a Claim**. A claim form opens on the job, as a warranty claim if the job is a warranty job, otherwise as insurance. Set who **Pays the Bill** (the insurer, the manufacturer or the warranty company), the policy number, their **Claim Number**, the surveyor, the excess and the damage and cause.


A job holds one live claim at a time. Open the Claim takes you to it.

2 ENTERPRISE ADD-ON

Submit, approve, settle

Press **Submit** when it goes to them. When they agree, enter the **Approved Amount** and press **They Approved It**, or **They Refused**. When they pay, press **Settled**.

A claim cannot be approved without their claim number. Without it nothing gets paid.



3 ENTERPRISE ADD-ON

The shortfall


Once approved, **Shortfall** is the job value less the excess less the approved amount. It is the part somebody still has to agree to pay before the car goes out. On the job, **Paid By** reads *An Insurer or Warranty* and **Owner Pays** is the excess plus the shortfall.

The split bill ENTERPRISE ADD-ON

Invoicing a ready job whose claim is approved or settled raises two invoices instead of one:

INVOICE	TO	AMOUNT
Insurer invoice	Pays the Bill on the claim, with their claim number as the reference	The approved amount, capped at the job value
Owner invoice	The customer	The rest of the job: the excess and anything not covered

The two always add up to the job. Each is one priced line, *Authorised under claim* or *Policy excess and work not covered*, with the labour and parts listed underneath as notes. Both invoices are linked on the job as **Insurer Invoice** and **Owner Invoice**.



ENTERPRISE ADD-ON **The insurer's share** of a settled claim, as raised by the job.

PART 19 Sublet work

ENTERPRISE ADD-ON


Paint, alignment, machining and specialist diagnostics sent to somebody else and sold on. The module tracks what is out, when it is due back, and makes sure it lands on the bill.


IN THIS PART YOU WILL LEARN

- Adding outwork to a job with its cost and markup
- Send Out, Book Back In and the late flag
- Why a job with work still out cannot be invoiced

TRY IT YOURSELF ON THE DEMO

1. Open AQ/JOB/2026/00018 and its Sublet tab
2. Open Plans and Claims > Sublet Work and filter on overdue





1 ENTERPRISE ADD-ON

Add the outwork

On the job's **Sublet** tab, add a line: description, kind (paint and body, wheel alignment, machining, unit rebuild, specialist diagnostics, glass, trim and upholstery, other), the vendor and their job number, the promised back date, their **Cost** and your **Markup** (25% by default). The **Price** is the cost plus the markup.


Untick Chargeable for outwork redone under warranty. The cost still counts against the job.

2 ENTERPRISE ADD-ON

Send it, book it back

Press **Send Out** when it leaves (the line is *With Them*) and **Book Back In** when it returns. A line still out past its promised date is flagged overdue. **Cancel** and **Reset** are there for mistakes.

Chargeable sublet is added to the job total with its own taxes and invoiced in its own **Sublet** section, kept off the parts so the parts margin still means something. Its cost comes off the job's gross profit. **Invoice** is refused while any sublet line is still out.



ENTERPRISE ADD-ON **Plans and Claims > Sublet Work.** Everything out with a vendor, across every job.

PART 20 Technician commission

ENTERPRISE ADD-ON


Most workshops pay an incentive on output. The add-on works it out from the hours the base module already records, one line per technician per month.

IN THIS PART YOU WILL LEARN


- The three ways a rule can pay
- The hours a salary already buys, and the minimum efficiency
- How a month's line is worked out and approved

TRY IT YOURSELF ON THE DEMO

1. Open Configuration > Commission Rules and compare the two rules
2. Open Plans and Claims > Technician Commission and open one line
3. Press the button that lists the jobs behind it




ENTERPRISE ADD-ON **Per hour sold.** An amount for every hour sold above the threshold.



ENTERPRISE ADD-ON **Percent of job margin.** For a foreman who also sells the work.

RULE FIELD	WHAT IT DOES
Basis	Per hour sold, percent of labour sold, or percent of job margin
Per Hour / Percent	The rate for the basis chosen. A rule without it is refused.
Hours Before Paying	Hours the technician must sell in the month before anything is earned
Minimum Efficiency (%)	Below this, nothing is earned that month
Workshop, Technicians	Who the rule applies to. Empty means everybody. The first matching rule wins.




1 ENTERPRISE ADD-ON

The month's lines

Plans and Claims > Technician Commission. One line per technician per month, with hours sold and clocked, efficiency, labour sold, job margin, jobs and the amount.

Only work on jobs that reached Ready or Invoiced in the month counts, so nothing is paid twice.



2 ENTERPRISE ADD-ON

Approve and pay

Open a line, check it, press **Approve**, then **Mark Paid** once payroll has paid it. The button at the top opens the labour lines behind the figure.

A paid line cannot be cancelled, so the payroll and the record never disagree.

HOW IT WORKS

How the amount is worked out

- **Per hour sold:** (hours sold less hours before paying) × per hour.
- **Percent of labour sold:** once hours sold pass the threshold, the percent of the labour value sold.
- **Percent of job margin:** once past the threshold, the percent of the technician's share of each job's gross profit, shared by hours.
- Any basis pays nothing if the month's efficiency is below the minimum.

The lines are drafted by the scheduled job *draft last month's technician commission*, which runs on the first of the month. It ships switched off: switch it on in Settings > Technical > Scheduled Actions when you are ready. Running a month again updates draft lines rather than adding new ones.

PART 21 Account statements and the two boards

ENTERPRISE ADD-ON


Two views for the person who runs the business: a statement for an account that pays monthly, and the boards that show the floor and the money at a glance.

IN THIS PART YOU WILL LEARN

- Printing a statement for a fleet, insurer or trade account
- The Workshop Floor board: what is in the building and whether the hours are earned
- The Trading board: revenue, margin, plans and claims
- Opening the records behind any figure

TRY IT YOURSELF ON THE DEMO

1. Open Dashboards > Workshop Floor and change the period
2. Click the Past the promise figure
3. Open Dashboards > Trading




1 ENTERPRISE ADD-ON

Account statement

Plans and Claims > Account Statement. Pick the account (a fleet operator, an insurer or a trade customer), a workshop or leave it empty for every branch, the period (this month by default) and whether to include finished jobs not yet invoiced. The form shows the job count and totals; **Print** gives one sheet with every job, registration, vehicle, work, reference, net and total.


An insurer's statement follows the claim, not the customer on the job, so it lists every job they are paying for.

The Workshop Floor board ENTERPRISE ADD-ON




ENTERPRISE ADD-ON **Dashboards > Workshop Floor.** Pick a workshop and a period (last 30 days, this month, this quarter, this year). Click any figure to open the jobs behind it.

SECTION	FIGURES
Holding the floor up	Past the promise, waiting for a yes, out today, ready to collect
On the ramps	Jobs open, being worked on, bays in use (distinct bays with a job in progress, against the bays you have), jobs below the target
Are the hours being earned	Hours sold, hours clocked and efficiency on jobs finished in the period with clocked time, with a verdict: beating the book, near the target, losing hours




ENTERPRISE ADD-ON **The lower half of the floor board.** Hours sold, hours clocked, efficiency with its verdict, and the technicians.

The Trading board ENTERPRISE ADD-ON



ENTERPRISE ADD-ON **Dashboards > Trading.** Revenue and margin for the period with a verdict (healthy at 45% or more, thin from 30%, too thin below), jobs invoiced and the average invoice.



ENTERPRISE ADD-ON **The lower half of the trading board.** Plans running, plans running out inside 60 days, services remaining, claims waiting on an insurer, their value, and what approved claims are short by.

> The boards count with full rights, so anybody who can open the menu sees the totals even if they cannot read every record behind them. The menu itself is limited to the Plans and Claims group.

PART 22 Scheduled jobs and access rights

What the system does on its own every day, and the rules on who can see and change what.

Scheduled jobs

JOB	RUNS	WHAT IT DOES	
Garage: service reminders due	Daily	Emails owners whose open reminder is due inside the chase window or whose reading has passed the due reading, and marks it Customer Told	BASE
Garage: certificates about to expire	Daily	Emails the owner once when the newest pass certificate expires inside the chase window	BASE
Garage: chase unanswered estimates	Daily	Puts a call activity on the workshop manager (or the advisor) for every estimate awaiting approval longer than the setting	BASE
Garage: courtesy cars overdue	Every 4 hours	Posts a note on any loan still out past its due time plus the grace hours, and on its job	BASE
Garage: close forgotten clock cards	Every 6 hours	Closes any time log left running for 12 hours at 8 hours and notes it on the job	BASE
Garage: close off plans that have run out	Daily	Running plans past their end date become Expired, packages with nothing left become Used Up	ENTERPRISE ADD-ON
Garage: draft last month's technician commission	Monthly, shipped switched off	Builds or updates the draft commission lines for the month just ended	ENTERPRISE ADD-ON

Each job takes every record on its own, so one bad email address or a deleted user never stops the rest of the day's chasing. They are standard Odoo scheduled actions under Settings > Technical > Scheduled Actions.

Groups BASE

GROUP	INCLUDES	ADDS
Technician	-	The Garage app, own jobs, own clocks, own check sheets
Service Advisor	Technician	Every job, authority, invoicing, odometer readings, reminders, courtesy cars, advised work, key codes and lifetime spend
Workshop Manager	Service Advisor	Costs and gross profit, tester licences and cost per hour, Reporting, Configuration, and with the add-on the Plans and Claims group
Plans and Claims ENTERPRISE ADD-ON	Service Advisor	Service plans, claims, sublet work, statements, commission and the boards

Record rules BASE

- Every garage record is limited to the companies the user is allowed in, so a group with several trade licences keeps them apart.
- A technician sees a job card only if they lead it or have clocked on to it, and only their own time logs and check sheets.
- Advisors and managers see every job, clock and sheet.
- The stage of a job can only be moved by its buttons, and the authority fields can only be written by an advisor or above.

PART 23 A 15 minute demo

A route through the live demo that shows the whole workshop in a quarter of an hour. Sign in to garage-pro.way4tech.com as w4demo / Demo2026 and follow the rows. Nothing here needs a button that changes data.

MIN	OPEN	SAY
0	Workshop > Workshop Board	*Every car in the building, by stage. Late, waiting and comeback at a glance.*
1	Job AQ/JOB/2026/00023 (Estimate)	*Labour from our own flat rate book at the workshop rate, parts with stock on hand.*
3	Job AQ/JOB/2026/00021, Authority tab	*The customer authorised an amount, by a named person, by a recorded method.*
4	Job AQ/JOB/2026/00017	*The yellow banner: the job grew past the authority, so work cannot carry on until we ring.*
5	Inspections > VHC/2026/00001	*Red, amber, green with measurements. Advised against accepted, added to the job in one click.*
7	Job AQ/JOB/2026/00018 (Quality Check)	*Nobody passes their own work, and work out at a body shop blocks the invoice.*
8	Job AQ/JOB/2026/00038, Money tab, then the invoice	*Labour and parts as sections, sundries, gross profit split for the manager.*
9	Vehicles > Dubai A 23417	*Odometer history, certificates, reminders and every visit on one record.*
10	Courtesy Cars > Loans	*Out with the customer, overdue, the hire charge worked out.*
11	Plans and Claims > Claims > CLM/2026/0001	*Excess, approved and the shortfall somebody still has to pay. Two invoices.*
12	Plans and Claims > Service Plans > SP/2026/0002	*A fleet AMC drawn down job by job, with its margin.*
13	Dashboards > Workshop Floor, then Trading	*Click a figure and the jobs behind it open.*
14	Reporting > Labour Recovery	*Sold against clocked, per technician.*

> On garage-demo.way4tech.com the same route works. The job numbers differ slightly between the two copies.

PART 24 Questions people ask

Does it need Odoo Enterprise?

No. Both modules are built on Odoo 19 Community and need only Inventory and Invoicing (Accounting). *Enterprise* in the add-on's name is the edition of our module, not of Odoo.

Can a customer approve the estimate online?

The estimate is emailed, and the customer replies or rings. The advisor records the authority. A customer can sign on screen at the counter in the Signature box on the Authority tab. There is no customer portal or online booking page.

Can it decode a VIN or look up labour times?

No. Make, model and engine are typed or picked from your lists, and flat rate hours come from your own Labour Operations.

Can I drag a job card to the next stage?

No. Dragging is refused on purpose. Each stage has a button with its own checks, which is what makes the stage mean something.

Does it work with miles?

Yes. Set the Distance Unit in Settings once; every reading, interval and printout follows.

Several branches?

Yes. One workshop per site, each with its own code, rates, bays, journal and parts store. Companies are kept apart by the multi-company rules.

How are parts taken off stock?

Draw the Parts raises a standard Odoo delivery from the workshop's parts store. Validate it in Inventory when the parts are handed over.

What happens to warranty work?

Untick Chargeable on the lines nobody pays for. They are left off the invoice but their cost still counts, so warranty work shows as a cost, not as nothing.

Who pays when there is an insurance claim?

With the add-on, the approved claim raises one invoice to the insurer for the approved amount and one to the owner for the rest. The two always add up to the job.

Can technicians use a tablet on the ramp?

Yes, through the normal Odoo web client in a browser. A technician linked to a user sees only their own jobs, clocks and check sheets.

PART 25 Menu map

Every menu the two modules add, with the badge for the module that brings it.

Dashboards

Workshop Floor ENTERPRISE ADD-ON	Open jobs, approvals, ramps, ready, late, bays and hours
Trading ENTERPRISE ADD-ON	Revenue, margin, average invoice, plans and claims

Workshop

Job Cards BASE	Every job from estimate to invoice
Workshop Board BASE	The same jobs as cards by stage
Time Logs BASE	Every clock on and clock off

Inspections

Check Sheets BASE	Red, amber and green health checks
Advised Work BASE	Every red or amber item and whether it was sold

Plans and Claims

Service Plans ENTERPRISE ADD-ON	Packages, AMCs and extended warranties
Claims ENTERPRISE ADD-ON	Insurance and warranty claims with the shortfall
Sublet Work ENTERPRISE ADD-ON	Outwork sent to a specialist and sold on
Account Statement ENTERPRISE ADD-ON	A period of work for one account on one sheet
Technician Commission ENTERPRISE ADD-ON	One line per technician per month

Vehicles

Vehicles BASE	Every vehicle with its history
Odometer Readings BASE	Every reading, from every source
Roadworthiness Tests BASE	Test certificates and their expiry
Service Reminders BASE	What is due, by date or by reading

Courtesy Cars

Loans BASE	Who has which loan car and until when
Courtesy Fleet BASE	The loan cars, rates and cover

Reporting

Gross Profit BASE	Labour and parts profit per job
Labour Recovery BASE	Sold against clocked, per line
Parts Used BASE	Every part fitted
Inspection Conversion BASE	Advised against accepted
Comebacks and Rework BASE	Rework by reason

Configuration

Settings BASE	The eleven workshop rules
Workshops BASE	Rates, products, journal, hours
Bays BASE	Lifts, test lanes, weight limits
Labour Operations BASE	Your flat rate book
Technicians BASE	Grades, sign off, cost, hours
Check Sheets BASE	Inspection templates
Makes / Models BASE	The vehicle lists
Rate Cards ENTERPRISE ADD-ON	What each kind of account pays
Commission Rules ENTERPRISE ADD-ON	How technicians are paid on output

Want this for your workshop?

We set it up with your bays, your labour book and rates, your technicians and check sheets, load your customers and vehicles, connect your stock and accounts, and train the front desk and the workshop. One site or a group of branches, with or without the Enterprise add-on for plans, claims and fleet accounts.

way4tech.com · info@way4tech.com