
RTI Connext DDS

Core Libraries

XML-Based Application Creation

Getting Started Guide

Version 5.2.3





© 2012-2016 Real-Time Innovations, Inc. All rights reserved. Printed in U.S.A. First printing. April 2016.

Trademarks

Real-Time Innovations, RTI, NDDS, RTI Data Distribution Service, DataBus, Connext, Micro DDS, the RTI logo, 1RTI and the phrase, "Your Systems. Working as one," are registered trademarks, trademarks or service marks of Real-Time Innovations, Inc. All other trademarks belong to their respective owners.

Copy and Use Restrictions

No part of this publication may be reproduced, stored in a retrieval system, or transmitted in any form (including electronic, mechanical, photocopy, and facsimile) without the prior written permission of Real-Time Innovations, Inc. The software described in this document is furnished under and subject to the RTI software license agreement. The software may be used or copied only under the terms of the license agreement.

Technical Support

Real-Time Innovations, Inc. 232 E. Java Drive Sunnyvale, CA 94089

Phone: (408) 990-7444 Email: support@rti.com

Website: https://support.rti.com/

Contents

1	In	troduction	1-1
	1.1	Paths Mentioned in Documentation	1-2
2	Α	'Hello, World' Example	2-1
	2.1	Hello World using XML and Dynamic Data	
		2.1.1 Build the Application	
		2.1.2 Run the Application	
		2.1.3 Examine the XML Configuration Files Definition	
		2.1.4 Publisher Application	2-6
		2.1.5 Subscriber Application	
		2.1.6 Subscribing with a Content Filter	
	2.2	Hello World using XML and Compiled Types	
		2.2.1 Define the Data Types using IDL or XML	
		2.2.2 Generate Type-Support Code from the Type Definition	
		2.2.3 Build the Application	
		2.2.4 Run the Application2.2.5 Examine the XML Configuration Files Definition	
		2.2.6 Publisher Application	
		2.2.7 Subscriber Application	
^		**	
3	US	sing Connext Prototyper	3-1
4	Ur	nderstanding XML-Based Application Creation	4-1
	4.1	Important Points	4-1
	4.2	Loading XML Configuration Files	4-2
	4.3	XML Syntax and Validation	4-2
		4.3.1 Validation at Run-Time	4-2
		4.3.2 Validation during Editing	4-3
	4.4	Accessing Entities Defined in XML Configuration from an Application	4-3
	4.5	XML Tags for Configuring Entities	4-3
		4.5.1 Domain Library	4-4
		4.5.2 Participant Library	4-8
	4.6	Names Assigned to Entities	4-13
		4.6.1 Referring to Entities and Other Elements within XML Files	4-14
	4.7	Creating and Retrieving Entities Configured in an XML File	4-16
		4.7.1 Creating and Retrieving a DomainParticipant Configured in an XML File	
		4.7.2 Creating and Retrieving Publishers and Subscribers	
		4.7.3 Creating and Retrieving DataWriters and DataReaders	
		4.7.4 Creating Content Filters	
		4.7.5 Using User-Generated Types	4-19

Chapter 1 Introduction

This document assumes you have a basic understanding of RTI ConnextTM DDS application development and concepts such as *Domains, DomainParticipants, Topics, DataWriters* and DataReaders. For an overview of these concepts, please read Introduction to Connext DDS, Section 3.3 in the RTI Connext DDS Core Libraries Getting Started Guide, which is part of your distribution, or you can find it online at http://community.rti.com/documentation.

XML-Based Application Creation is a mechanism to simplify the development and programming of *Connext DDS* applications. *Connext DDS* supports the use of XML for the complete system definition. This includes not only the definition of the data types and Quality of Service settings (as was possible in previous versions of the product), **but also the definition of the Topics, DomainParticipants, and all the Entities they contain (***Publishers, Subscribers, DataWriters* **and** *DataReaders***).**

With the traditional approach an application developer must program explicitly into the code the actions needed to join a domain, register the data types it will use, create the *Topics* and all the Entities (*Publishers*, *Subscribers*, *DataReaders* and *DataWriters*) that the application uses. Even for simple applications this "system creation" code can result in hundreds of lines of boiler-plate code. Beyond being error prone, the traditional approach results in larger code-bases that are harder to understand and maintain. Using XML-Based Application Creation can significantly simplify this process.

XML-Based Application Creation is a simple layer that builds on top of the standard APIs. Everything that you do with the XML configuration can also be done with the underlying APIs. In this manner, an application can be initially developed using XML-Based Application Creation and transitioned to the traditional API at a later time. This would be useful in case the application has to be deployed on a platform without a file system or needs to be ported to a DDS-compliant library that does not support XML-based configuration such as *RTI Connext Micro*.

Using XML-Based Application Creation is easy: simply edit USER_QOS_PROFILE.xml to define:

The data types that will be used to communicate information in the system
The <i>Topics</i> that will be used in the domain, associating each <i>Topic</i> with a data type
The <i>DomainParticipants</i> that can potentially be used, giving each a participant name
The <i>DataWriters</i> and <i>DataReaders</i> present within each <i>DomainParticipant</i> , each associated with its corresponding <i>Tonic</i>

The application code simply indicates the **participant configuration name** of the *DomainParticipant* that the application wants to create. The XML-Based Application Creation infrastructure takes care of the rest: creating the *DomainParticipant*, registering the types and *Topics*, and populating all the configured Entities.

When the application needs to read or write data, register listeners, or perform any other action, it simply looks up the appropriate Entity by name and uses it.

XML-Based Application Creation enables several powerful new work flows:

Developers can describe all the Entities that a <i>Connext DDS</i> application will need in an XML file and then create that application with a single function call, saving many hundreds of lines of setup code.
Application descriptions written in XML are usable from all programming languages.
The complete domain (including the data types and <i>Topics</i> that can be in the domain) may be defined in an XML file and shared amongst all the developers and applications.
The Quality of Service (QoS) that should be used for each <i>DomainParticipant</i> , <i>Topic</i> , <i>DataReader</i> , and <i>DataWriter</i> can be fully specified in the XML and shared amongst a group of developers and applications.
The XML description of the application can be used in combination with <i>RTI Prototyper</i> to design and prototype application deployment scenarios, allowing quick testing and validation without the need for programming.

To use the companion RTI Connext DDS Prototyper, see Chapter 3.

1.1 Paths Mentioned in Documentation

The documentation refers to:

□ <NDDSHOME>

This refers to the installation directory for *Connext DDS*.

The default installation paths are:

• Mac OS X systems:

/Applications/rti_connext_dds-version

• UNIX-based systems, non-root user:

/home/your user name/rti_connext_dds-version

• UNIX-based systems, root user:

/opt/rti_connext_dds-version

• Windows systems, user without Administrator privileges:

<your home directory>\rti_connext_dds-version

• Windows systems, user with Administrator privileges:

C:\Program Files\rti_connext_dds-version (for 64-bits machines) or

C:\Program Files (x86)\rti_connext_dds-version (for 32-bit machines)

You may also see \$NDDSHOME or %NDDSHOME%, which refers to an environment variable set to the installation path.

Wherever you see <NDDSHOME> used in a path, replace it with your installation path.

Note for Windows Users: When using a command prompt to enter a command that includes the path **C:\Program Files** (or any directory name that has a space), enclose the path in quotation marks. For example:

"C:\Program Files\rti connext dds-version\bin\rtiddsgen"

or if you have defined the NDDSHOME environment variable:

"%NDDSHOME%\bin\rtiddsgen"

☐ RTI Workspace directory, rti_workspace

The RTI Workspace is where all configuration files for the applications and example files are located. All configuration files and examples are copied here the first time you run RTI Launcher or any script in **<NDDSHOME>/bin**. The default path to the RTI Workspace directory is:

• Mac OS X systems:

/Users/your user name/rti_workspace

• UNIX-based systems:

/home/your user name/rti_workspace

• Windows systems:

your Windows documents folder\rti_workspace

Note: 'your Windows documents folder' depends on your version of Windows. For example, on Windows 7, the folder is C:\Users\your user name\Documents; on Windows Server 2003, the folder is C:\Documents and Settings\your user name\Documents.

You can specify a different location for the **rti_workspace** directory. See the *RTI Connext DDS Core Libraries Getting Started Guide* for instructions.

cpath to examples>

Examples are copied into your home directory the first time you run *RTI Launcher* or any script in **<NDDSHOME>/bin**. This document refers to the location of these examples as **<path to examples>.** Wherever you see **<path to examples>**, replace it with the appropriate path.

By default, the examples are copied to rti_workspace/version/examples

So the paths are:

• Mac OS X systems:

/Users/your user name/rti_workspace/version/examples

• UNIX-based systems:

/home/your user name/rti_workspace/version/examples

• Windows systems:

your Windows documents folder\rti_workspace\version\examples

Note: 'your Windows documents folder' is described above.

You can specify that you do not want the examples copied to the workspace. See the *RTI Connext DDS Core Libraries Getting Started Guide* for instructions.


Chapter 2 A 'Hello, World' Example

This chapter assumes that you have installed *RTI Connext DDS* and configured your environment correctly. If you have not done so, please follow the steps in the *RTI Connext DDS Core Libraries Getting Started Guide*, specifically Chapter 2 "Installing RTI Connext" and Section 3.1 "Building and running Hello World" in Chapter 3. The guide is part of your distribution; you can also find it online at http://community.rti.com/content/page/documentation. The guide will assist you in the correct setting of both your environment variable NDDSHOME and, depending on your architecture, the environment variable PATH (on Windows Systems), LD_LIBRARY_PATH (on Linux systems), or DYLD_LIBRARY_PATH (on MacOS Systems).

2.1 Hello World using XML and Dynamic Data

The files for this example are located in the directory **<path to examples located in the directory <path to examples located in the directory <path to examples located in the directory directory <path to examples located in the directory directory the lowerld_xml_dynamic.** This simple scenario consists of two applications, illustrated in the figure below: **HelloWorld_publisher.exe**, which writes the *Topic*, **HelloWorldTopic**, and **HelloWorld_subscriber.exe**, which subscribes to that *Topic*.

Figure 2.1 Hello World Domain



^{1.} See Paths Mentioned in Documentation (Section 1.1)

First we will run the application, then we will examine the configuration file and source code.

2.1.1 Build the Application

The example code is provided in C++, C#, and Java. The following instructions describe how to build it on Windows and UNIX-based systems. If you will be using an embedded platform, see the RTI Connext DDS Core Libraries Getting Started Guide Addendum for Embedded Systems for instructions specific to these platforms.

To build the example C++ applications on a Windows System:

- 1. In Windows Explorer, go to <path to examples>\connext_dds\c++\hello_world_xml_dynamic\win32 and open the Microsoft® Visual Studio® solution file for your architecture. For example, the file for Visual Studio 2012 32-bit platforms is HelloWorld-vs2012.sln.
- 2. The Solution Configuration combo box in the toolbar indicates whether you are building debug or release executables; select **Release**. Then select **Build Solution** from the Build menu.

To build the example C++ applications on a UNIX-based System:

- 1. From your command shell, change directory to cpath to examples>/connext_dds/c++/
 hello_world_xml_dynamic.
- 2. Type:

```
gmake -f make/Makefile.<architecture>
```

where *<architecture>* is one of the supported architectures (e.g., **Makefile.i86Linux2.6gcc4.4.5**); see the contents of the **make** directory for a list of available architectures. This command will build a *release* executable. To build a *debug* version instead, type:

```
qmake -f make/Makefile.<architecture> DEBUG=1
```

2.1.2 Run the Application

The previous step should have built two executables: **HelloWorld_subscriber** and **HelloWorld_publisher**. These applications should be in proper architecture subdirectory under the **objs** directory (for example, **objs\i86Win32VS2012** in the Windows example cited below and **objs/i86Linux2.6gcc4.4.5** in the Linux example).

To start the subscribing application on a Windows system:

From your command shell, go to <path to examples>\connext_dds\c++\hello_world_xml_dynamic and type:

```
objs\<architecture>\HelloWorld subscriber.exe
```

where *<architecture>* is the architecture you just built; look in the **objs** directory to see the name of the architecture you built. For example, the Windows architecture name corresponding to 32-bit Visual Studio 2012 is i86Win32VS2012.

To start the subscribing application on a UNIX-based systems:

From your command shell, change directory to <path to examples>/connext_dds/c++/hello_world_xml_dynamic and type:

```
objs/<architecture>/HelloWorld_subscriber
```

where *<architecture>* is the architecture you just built; look in the **objs** directory to see the name of the architecture you built. For example, **i86Linux2.6gcc4.4.5**.

You should immediately see some messages from the publishing application showing that it is writing data and messages from the subscribing application showing the data it receives. Do not worry about the contents of the messages. They are generated automatically for this example. The important thing is to understand how the application is defined, which will be explained in the following sections.

2.1.3 Examine the XML Configuration Files Definition

A *Connext DDS* application is defined in the file **USER_QOS_PROFILES.xml** found in the directory **<path to examples>/connext_dds/c++/ hello_world_xml_dynamic**. Let's review its content to see how this scenario was constructed. The main sections in the file are:

- ☐ QoS definition section
- ☐ Type definition section
- ☐ Domain definition section
- ☐ Participant definition section

The entire file is shown below. The we will examine the file section-by-section.

```
<?xml version="1.0"?>
-<dds version="5.2.0" xsi:noNamespaceSchemaLocation="http://community.rti.com/
schema/5.2.0/rti dds profiles.xsd" xmlns:xsi="http://www.w3.org/2001/XMLSchema-
instance">
<!-- Qos Library -->
<qos library name="qosLibrary">
    <qos profile name="DefaultProfile"> </qos profile>
</gos library>
<!-- types -->
<types>
    <const name="MAX_NAME_LEN" value="64" type="long"/>
    <const name="MAX MSG LEN" value="128" type="long"/>
    <struct name="HelloWorld">
        <member name="sender" type="string"</pre>
         stringMaxLength="MAX_NAME_LEN" key="true"/>
        <member name="message" type="string" stringMaxLength="MAX MSG LEN"/>
        <member name="count" type="long"/>
    </struct>
</types>
<!-- Domain Library -->
<domain_library name="MyDomainLibrary">
    <domain name="HelloWorldDomain" domain id="0">
        <register type name="HelloWorldType" type ref="HelloWorld"
        kind="dynamicData"/>
        <topic name="HelloWorldTopic" register type ref="HelloWorldType">
            <topic gos name="HelloWorld gos"</pre>
             base name="gosLibrary::DefaultProfile"/>
        </topic>
    </domain>
</domain library>
```

```
<!-- Participant library -->
<participant library name="MyParticipantLibrary">
    <domain participant name="PublicationParticipant"</pre>
     domain ref="MyDomainLibrary::HelloWorldDomain">
        <publisher name="MyPublisher">
            <data writer name="HelloWorldWriter" topic ref="HelloWorldTopic"/>
        </publisher>
    </domain participant>
    <domain participant name="SubscriptionParticipant"</p>
     domain ref="MyDomainLibrary::HelloWorldDomain">
        <subscriber name="MySubscriber">
            <data reader name="HelloWorldReader" topic ref="HelloWorldTopic">
                <datareader qos name="HelloWorld reader qos"</pre>
                 base_name="qosLibrary::DefaultProfile"/>
            </data reader>
        </subscriber>
    </domain participant>
</participant_library>
</dds>
```

2.1.3.1 QoS Definition

The DDS Entities that are defined have an associated QoS. The QoS section of the XML file provides the means to define QoS libraries and profiles that can be used to configure the QoS of the defined Entities.

The syntax of the QoS libraries and profiles section is described in the RTI Connext DDS Core Libraries User's Manual, Chapter 17 "Configuring QoS with XML."

In this example, the QoS library and profile are empty, just to provide a placeholder where the QoS can be specified. Using this empty profile results in the default DDS QoS being used:

2.1.3.2 Type Definition

The data associated with the HelloWorld *Topic* consists of two strings and a numeric counter:

- ☐ The first string contains the name of the sender of the message. This field is marked as "key" as signals the identity of the data-object.
- ☐ The second string contains a message.
- ☐ The third field is a simple counter which the application increments with each message.

This example uses the dynamic data API, so the data type must be defined in the XML configuration. This is accomplished by adding the type definition within the <types> tag:

```
</struct>
</types>
```

The <types> tag may be used to define a library containing the types that the different applications will need. However, for this simple example just one data-type, the HelloWord type seen above, is included.

2.1.3.3 Domain Definition

The domain section is used to define the system's *Topics* and the corresponding data types associated with each *Topic*. To define a *Topic*, the associated data type must be registered with the domain giving it a registered type name. The registered type name is used to refer to that data type within the domain at the time the *Topic* is defined.

In this example, the configuration file registers the previously defined HelloWorld type under the name HelloWorldType and then defines a topic with name HelloWorldTopic associated with the registered type, referring to it by its registered name HelloWorldType:

Note that attribute **type_ref** in the <register_type> element refers to the same HelloWorld type defined in the <types> section.

A domain definition may register as many data types and define as many *Topics* as it needs. In this example a single data type and *Topic* suffices.

Note that **domain_library** can be used to define multiple domains. However in this example only one domain is used.

2.1.3.4 Participant Definition

The participant section is used to define the *DomainParticipants* in the system and the *DataWriters* and *DataReaders* that each participant has. *DomainParticipants* are defined within the <participant_library> tag.

Each *DomainParticipant*:

Has a unique name (within the library) which will be used later by the application that creates it.
Is associated with a domain, which defines the domain_id , <i>Topics</i> and data types the <i>DomainParticipant</i> will use.
Defines the <i>Publishers</i> and <i>Subscribers</i> within the <i>DomainParticipant</i> . <i>Publishers</i> contain <i>DataWriters</i> and <i>Subscribers</i> contain <i>DataReaders</i> .
Defines the set of <i>DataReaders</i> it will use to write data. Each <i>DataReader</i> has a QoS and a unique name which can be used from application code to retrieve it.
Defines the set of <i>DataWriters</i> it will use to write data. Each <i>DataWriter</i> has a QoS and a unique name which can be used from application code to retrieve it.

• Optionally the *Participants, Publishers, Subscribers, DataWriters* and *DataReaders* can specify a QoS profile that will be used to configure them.

The example below defines two *DomainParticipant* entities called **PublicationParticipant** and **SubscriptionParticipant**:

```
<participant library name="MyParticipantLibrary">
   <domain participant name="PublicationParticipant"</pre>
       domain ref="MyDomainLibrary::HelloWorldDomain">
       <publisher name="MyPublisher">
            <data writer name="HelloWorldWriter"</pre>
                topic ref="HelloWorldTopic"/>
       </publisher>
   </domain participant>
   <domain participant name="SubscriptionParticipant"</pre>
       domain ref="MyDomainLibrary::HelloWorldDomain">
       <subscriber name="MySubscriber">
            <data_reader name="HelloWorldReader"</pre>
                topic ref="HelloWorldTopic">
            <datareader qos name="HelloWorld reader qos"</pre>
                base name="qosLibrary::DefaultProfile"/>
            </data reader>
       </subscriber>
   </domain participant
</participant library>
```

Examining the XML we see that:

- ☐ The PublicationParticipant bound to the domain MyDomainLibrary::HelloWorldDomain.
- ☐ The participant contains a single Publisher (with name **MyPublisher** which itself contains a single *DataWriter* named **HelloWorldWriter**.
- The *DataWriter* writes the *Topic* **HelloWorldTopic** which is defined in the domain **MyDomainLibrary::HelloWorldDomain**.

Similarly:

- ☐ The SubscriptionParticipant is also bound to the domain MyDomainLibrary::Hello-WorldDomain.
- ☐ The participant contains a single *Subscriber* (with name **MySubscriber** which itself contains a single *DataReader* named **HelloWorldReader**.
- ☐ The *DataReader* reads the topic **HelloWorldTopic** which is defined in the domain **MyDomainLibrary::HelloWorldDomain**.

Since both participants are in the same domain and the HelloWorldWriter *DataWriter* writes the same *Topic* that the HelloWorldReader *DataReader* reads the two participants will communicate as was illustrated in Figure 2.1, "Hello World Domain," on page 2-1.

2.1.4 Publisher Application

Open the file <path to examples>/connext_dds/c++/hello_world_xml_dynamic/ HelloWorld_publisher.cxx and look at the source code.

The logic of this simple application is contained in the **publisher_main()** function. The logic can be seen as composed of two parts:

Entity	Creation
Little	Creation

☐ Use of the Entities

Entity Creation: The application first creates a *DomainParticipant* using the function **create_participant_from_config()** this function takes the configuration name of the participant **MyParticipantLibrary::PublicationParticipant** which is the same name that was specified in the XML file. Note that the name in the XML file **PublicationParticipant** has been qualified with the name of the library it belongs to **MyParticipantLibrary**.

This single function call registers all the necessary data types and creates and the *Topics* and Entities that were specified in the XML file. In this simple case the participant only contains a *Publisher* **MyPublisher** with a single *DataWriter* **HelloDataWriter**. However, in more realistic scenarios this single call can create hundreds of entities (both readers and writers).

Use of the Entities: The remaining part of the function uses the created Entities to perform the logic of the program.

This example writes data using the single *DataWriter*. So the application looks up the **Hello-WorldWriter** *DataWriter* using the fully qualified name **MyPublisher::HelloWorldWriter** and narrows it to be a **DynamicDataWriter**:

Once the *DataWriter* is available, some data objects need to be created and used to send the data. As this example uses dynamic data, and the type code is internally created, you can use the operations **create_data()** and **delete_data()** in a *DataWriter* to create and delete a data object. This is achieved with the calls seen below:

```
/* Create data */
DDS DynamicData *dynamicData = dynamicWriter->create data(
                                     DDS DYNAMIC DATA PROPERTY_DEFAULT);
/* Main loop to repeatedly send data */
for (count=0; count < 100; ++count) {
   /* Set the data fields */
   retcode = dynamicData->set string(
                                     "sender",
                                     DDS_DYNAMIC_DATA_MEMBER_ID_UNSPECIFIED,
                                     "John Smith");
   retcode = dynamicData->set string(
                                     "message",
                                     DDS DYNAMIC DATA MEMBER ID UNSPECIFIED,
                                     "Hello World!");
   retcode = dynamicData->set long(
                                     "count",
                                     DDS DYNAMIC DATA MEMBER ID UNSPECIFIED,
                                     count);
   /* Write the data */
   retcode = dynamicWriter->write(*dynamicData, DDS_HANDLE_NIL);
}
/* Delete data sample */
dynamicWriter->delete_data(dynamicData
```

Note that the operations, such as **set_long()** are used to set the different attributes of the dynamicData object. These operations refer to the attribute names (e.g., "count") that were defined as part of the data type.

2.1.5 Subscriber Application

Open the file <path to examples>/connext_dds/c++/hello_world_xml_dynamic/HelloWorld_subscriber.cxx and look at the source code.

The logic of this simple application is contained in the **subscriber_main()** function. Similar to the publisher application, the logic is composed of two parts:

```
☐ Entity Creation
```

☐ Use of the Entities

Entity Creation: The application first creates a *DomainParticipant* using the function create_participant_from_config(). This function takes the configuration name of the participant MyParticipantLibrary::SubscriptionParticipant which is the same name that was specified in the XML file. Notice that the name in the XML file SubscriptionParticipant has been qualified with the name of the library it belongs to MyParticipantLibrary.

This single function call registers all the necessary data types and creates and the *Topics* and Entities that were specified in the XML file. In this simple case the participant only contains a subscriber **MySubscriber** with a single *DataReader* **HelloDataReader**. However in more realistic scenarios this single call can create hundreds of Entities (both *DataReaders* and *DataWriters*).

Use of the Entities: The remaining part of the function uses the entities that were created to perform the logic of the program.

This example only needs to read data using the single *DataReader*. So the application looks up the **HelloWorldReader** *DataReader* using the fully qualified name **MySubscriber::HelloWorldReader** and narrows it to be a DynamicDataReader:

To process the data, the application installs a Listener on the *DataReader*. The **HelloWorldListener**, defined on the same file implements the DataReaderListener interface, which the *DataReader* uses to notify the application of relevant events, such as the reception of data.

The last part is the implementation of the listener functions. In this case, we only implement the **on_data_available()** operation which is the one called when data is received.

The **on_data_available()** function receives all the data into a sequence and then uses the **DDS_DynamicData::print()** function to print each data item received.

```
void HelloWorldListener::on_data_available(DDSDataReader* reader)
{
    DDSDynamicDataReader * ddDataReader = NULL;
    DDS_DynamicDataSeq dataSeq;
    DDS_SampleInfoSeq infoSeq;
    DDS_ReturnCode_t retcode = DDS_RETCODE_ERROR;
    DDS_Long i = 0;

ddDataReader = DDSDynamicDataReader::narrow(reader);
```

2.1.6 Subscribing with a Content Filter

To use a content filter, modify the **SubscriptionParticipant** configuration to look like this:

The extra XML within the <filter> tag adds a SQL content filter which only accepts samples with the field count greater than two.

Now run **HelloWorld_subscriber** without recompiling and check the expected that the behavior.

2.2 Hello World using XML and Compiled Types

The files for this example are in the directory <path to examples¹>/connext_dds/c++/hello_world_xml_compiled. This simple scenario consists of two applications identical in purpose to the one illustrated in Figure 2.1, "Hello World Domain," on page 2-1: HelloWorld_publisher.exe, which writes to the *Topic* "HelloWorldTopic," and HelloWorld_subscriber.exe which subscribes to that same *Topic*.

In contrast with previous example, which uses the DynamicData API, this example uses compiled types.

^{1.} See Paths Mentioned in Documentation (Section 1.1)

Compiled types are syntactically nicer to use from application code and provide better performance. The drawback is that there is an extra step of code-generation involved to create that supporting infrastructure to marshal and unmarshal the types into a format suitable for network communications.

2.2.1 Define the Data Types using IDL or XML

The first step is to describe the data-type in a programming-language neutral manner. Two languages are supported by the *Connext DDS* tools: XML and IDL. These languages (XML and IDL) provide equivalent type-definition capabilities so you can choose either one depending on your personal preference. You can even transform between one and the other with the RTI tools. That said, as the rest of the configuration files use XML, it is often more convenient to also use XML to describe the data types so they can be shared or moved to other XML configuration files.

The directory **<path to examples>/connext_dds/c++/hello_world_xml_compiled** contains the XML description of the data type in the file **HelloWorld.xml** and it also contains the equivalent IDL description in **HelloWorld.idl**.

Let's examine the contents of the XML file:

The file defines a structure type called "HelloWorld" consisting of a string (the sender), a string (the message), and an integer count. Note that the type-declaration syntax is identical the one used within the **USER_QOS_PROFILES.xml** file that we used for the dynamic example (section Type Definition (Section 2.1.3.2)).

2.2.2 Generate Type-Support Code from the Type Definition

This step produces code to support the direct use of the structure 'HelloWorld' from application code. The code is generated using the provided tool named *rtiddsgen*.

The code-generation supports many programming languages. The XML-Based Application Creation currently supports C, C++, Java, and C#. We will use C++ in this example.

To generate code, follow these steps (replacing *<architecture>* as needed for your system; e.g., **i86Win32VS2012** or **i86Linux2.6gcc4.4.5**):

On a Windows system:

From your command shell, change directory to <path to examples>\connext_dds\c++\hello_world_xml_compiled and type:

```
<NDDSHOME>\bin\rtiddsgen -language C++ -example <architecture> Hello-
World.xml
```

On a UNIX-based system:

From your command shell, change directory to cpath to examples>/connext_dds/c++/
hello_world_xml_compiled and type:

```
\verb| <NDDSHOME>| bin/rtiddsgen - language C++ - example <| architecture> | Hello-World.xml| \\
```

As a result of this step you will see the following files appear in the directory HelloWorld_xml_dynamic: HelloWorld.h, HelloWorld.cxx, HelloWorldPlugin.h, HelloWorldSupport.h, and HelloWorldSupport.cxx

The most notable thing at this point is the fact that the **HelloWorld.h** file contains the declaration of the C++ structure, built according to the specification in the XML file:

```
static const DDS_Long MAX_NAME_LEN = 64;
static const DDS_Long MAX_MSG_LEN = 128;
typedef struct HelloWorld
{
    char* sender; /* maximum length = ((MAX_NAME_LEN)) */
    char* message; /* maximum length = ((MAX_MSG_LEN)) */
    DDS_Long count;
} HelloWorld;
```

2.2.3 Build the Application

The example code is provided in C++, C#, and Java. The following instructions describe how to build it on Windows and UNIX-based systems. If you will be using an embedded platform, see the RTI Connext DDS Core Libraries Getting Started Guide Addendum for Embedded Systems for instructions specific to these platforms.

C++ on Windows Systems:

- 1. In the Windows Explorer, go to <path to examples>\connext_dds\c++\hello_world_xml_compiled and open the Microsoft Visual Studio solution file for your architecture. For example, the file for Visual Studio 2012 for 32-bit platforms is HelloWorld-vs2012.sln.
- **2.** The Solution Configuration combo box in the toolbar indicates whether you are building debug or release executables; select **Release**. Select **Build Solution** from the Build menu.

C++ on UNIX-based Systems:

- From your command shell, change directory to path to examples>/connext_dds/c++/
 hello_world_xml_compiled.
- 2. Type:

```
gmake -f Makefile.<architecture>
```

where *<architecture>* is one of the supported architectures (e.g., **Makefile.i86Linux2.6gcc4.4.5**). This command will build a release executable. To build a debug version instead, type:

```
gmake -f Makefile.<architecture> DEBUG=1
```

2.2.4 Run the Application

The previous step built two executables: HelloWorld_subscriber and HelloWorld_publisher. These applications should be in proper architecture subdirectory under the **objs** directory (for

example, **objs\i86Win32VS2012** in the Windows example cited below and **objs/i86Linux2.6gcc4.4.5** in the Linux example).

1. Start the subscribing application:

On a Windows system:

From your command shell, go to **<path to examples>\connext_dds\c++\hello_world_xml_compiled** and type:

```
objs\<architecture>\HelloWorld subscriber.exe
```

where *<architecture*> is the architecture you just built; see the contents of the **objs** directory to see the name of the architecture you built. For example, the Windows architecture name corresponding to 32-bit Visual Studio 2012 is i86Win32VS2012.

On a UNIX-based system:

From your command shell, change directory to <path to examples>/connext_dds/c++/hello_world_xml_compiled and type:

```
objs/<architecture>/HelloWorld_subscriber
```

where *<architecture>* is the architecture you just built of the supported architectures; examine the contents of the **objs** directory to see the name of the architecture you built

2. Start the publishing application:

On a Windows system:

From your command shell, go to **<path** to **examples>\connext_dds\c++\hello_world_xml_compiled** and type:

```
objs\<architecture>\HelloWorld publisher.exe
```

where *<architecture>* is the architecture you just built; see the contents of the **objs** directory to see the name of the architecture you built.

On a UNIX-based system:

From your command shell, change directory to c++/hello_world_xml_compiled and type:

```
objs/<architecture>/HelloWorld_publisher
```

You should immediately see some messages on the publishing application showing that it is writing data and messages in the subscribing application indicating the data it receives. Do not worry about the contents of the messages. They are generated automatically for this example. The important thing is to understand how the application is defined which will be explained in the following subsections.

2.2.5 Examine the XML Configuration Files Definition

This system is defined in the file USER_QOS_PROFILES.xml found in the directory <path to examples>/connext_dds/c++/hello_world_xml_compiled. Let's look at its content and what are the elements defined to construct this scenario.

```
<?xml version="1.0"?>
<dds version="5.2.0" xsi:noNamespaceSchemaLocation="http://community.rti.com/
schema/5.2.0/rti_dds_profiles.xsd" xmlns:xsi="http://www.w3.org/2001/XMLSchema-
instance">
```

```
<!-- Qos Library -->
<qos library name="qosLibrary">
    <qos profile name="DefaultProfile"> </qos profile>
</qos library>
<!-- Domain Library -->
<domain library name="MyDomainLibrary">
    <domain name="HelloWorldDomain" domain id="0">
        <register type name="HelloWorldType" kind="userGenerated"/>
        <topic name="HelloWorldTopic" register_type_ref="HelloWorldType">
            <topic gos name="HelloWorld gos"</pre>
             base name="qosLibrary::DefaultProfile"/>
        </topic>
    </domain>
</domain_library>
<!-- Participant library -->
<participant_library name="MyParticipantLibrary">
    <domain_participant name="PublicationParticipant"</pre>
     domain ref="MyDomainLibrary::HelloWorldDomain">
        <publisher name="MyPublisher">
            <data_writer name="HelloWorldWriter" topic_ref="HelloWorldTopic"/>
        </publisher>
    </domain participant>
    <domain participant name="SubscriptionParticipant"</pre>
     domain ref="MyDomainLibrary::HelloWorldDomain">
        <subscriber name="MySubscriber">
            <data reader name="HelloWorldReader" topic ref="HelloWorldTopic">
                <datareader_qos name="HelloWorld_reader_qos"</pre>
                 base name="qosLibrary::DefaultProfile"/>
            </data reader>
        </subscriber>
    </domain_participant>
</participant library>
</dds>
```

Notice that this file contains virtually the same information found in the hello_world_xml_dynamic example. This is no surprise, since we are essentially trying to define the same system. Please revisit Examine the XML Configuration Files Definition (Section 2.1.3) for a description of what each section in the XML does.

There are only two differences in the configuration file for the **hello_world_xml_compiled** compared to **hello_world_xml_dynamic**:

- ☐ The type definition "<types>" section does not appear in the configuration of the HelloWorld_xml_compiled example.
- ☐ The registration of the data types within the domain is slightly different

The type-definition section that appears between the tags "<types>" and "</types>" is not there because in this case the data types are compiled in. So the type-definition has been moved to an external file to facilitate the code generation described in Section Generate Type-Support Code from the Type Definition (Section 2.2.2).

The registration of the data-type inside the domain uses the syntax:

```
<register_type name="HelloWorldType" kind="userGenerated" />
```

This contrasts with what was used in the HelloWorld_xml_dynamic example:

```
<register_type name="HelloWorldType" kind="dynamicData" type_ref="HelloWorld" />
```

The modified syntax indicates a **kind="userGenerated"** which means that the type will be defined via code generation and not use the DynamicData API. Since the type is defined via code generation there is no need to provide a reference to the type-definition so the **type_ref** attribute is not present.

To sum it up, the XML configuration file is essentially the same except that the type definitions of the data types that will be compiled in are not present and that is indicated at the time the data type is registered in the domain by means of the attribute **kind="userGenerated"**.

2.2.6 Publisher Application

Open the file <path to examples>/connext_dds/c++/hello_world_xml_compiled/ HelloWorld_publisher.cxx and look at the source code.

The logic of this simple application is contained in the **publisher_main()** function. The logic can be seen as composed of three parts:

Type registration (this step is new compared to the HelloWorld_xml_dynamic)
Entity creation
Use of the Entities

Type Registration: The first thing the application does is register the data-types that were defined in the code-generation step. This is accomplished by calling the **register_type_support()** function on the DomainParticipantFactory.

The function **register_type_support()** must be called for each code-generated data type that will be associated with the *Topics* published and subscribed by the application. In this example there is only one *Topic* and one data type, so only one call to this function is required.

The function **register_type_support()** takes as a parameter the TypeSupport function that defines the data type in compile code. In this case it is **HelloWorldTypeSupport::register_type** this function is declared in the **HelloWorldSupport.h**. However you cannot see it directly there because it is defined using macros. Instead you will find the line:

```
DDS_TYPESUPPORT_CPP(HelloWorldTypeSupport, HelloWorld);
```

This line defines the **HelloWorldTypeSupport::register_type()** function.

In general if you include multiple data-type definitions in a single XML (or IDL) file called <code>MyFile.xml</code> (or <code>MyFile.idl</code>) you will have multiple TypeSupport types defines within the generated file <code>MyFileTypeSupport.h</code>. You can identify them searching for the <code>DDS_TYPESUPPORT_CPP()</code> macro and you should register each of them (the ones the application uses) using the operation <code>register_type_support()</code> as was shown earlier.

Entity Creation: The steps needed to create the entities are the same as for the **HelloWorld_xml_dynamic** example. The application first creates a *DomainParticipant* using the function **create_participant_from_config()** this function takes the configuration name of the participant "**MyParticipantLibrary::PublicationParticipant**" which is the same name that was specified in the XML file. Note that the name in the XML file "**PublicationParticipant**" has been qualified with the name of the library it belongs to "**MyParticipantLibrary**".

This single function call registers all the necessary data types and creates and the *Topics* and Entities that were specified in the XML file. In this simple case the participant only contains a publisher "MyPublisher" with a single *DataWriter* "HelloDataWriter". However in more realistic scenarios this single call can create hundreds of entities (both readers and writers).

Use of the Entities: The remaining part of the function uses the entities that were created to perform the logic of the program.

This example only needs to write data using the single data writer. So the application looks-up the "HelloWorldWriter" DataWriter using the fully qualified name "MyPublisher::HelloWorld-Writer" and narrows it to be a HelloWorldDataWriter. Note the difference with the HelloWorld_xml_dynamic example. Rather than the generic "DynamicDataWriter" used in the example here we use a DataWriter specific to the HelloWorld data type.

```
HelloWorldDataWriter * helloWorldWriter = HelloWorldDataWriter::narrow(
                          participant->lookup datawriter by name(
                         "MyPublisher::HelloWorldWriter"));
/* Create data */
HelloWorld * helloWorldData = HelloWorldTypeSupport::create_data();
/* Main loop */
   for (count=0; (sample_count == 0) || (count < sample_count); ++count)</pre>
       printf("Writing HelloWorld, count: %d\n", count);
       /* Set the data fields */
       helloWorldData->sender = "John Smith";
       helloWorldData->message = "Hello World!";
       helloWorldData->count = count;
       retcode = helloWorldWriter->write(*helloWorldData, DDS HANDLE NIL);
       if (retcode != DDS RETCODE OK) {
           printf("write error %d\n", retcode);
           publisher shutdown(participant);
           return -1;
       NDDSUtility::sleep(send_period);
}
```

Note that the data object helloWorldData can be manipulated directly as a plain-language object. This means that in order to set a field in the object the application can refer to it directly as in:

```
helloWorldData->count = count;
```

This "plain language object" API is both higher performance and friendlier to the programmer than the DynamicData API.

2.2.7 Subscriber Application

Open the file <path to examples>/connext_dds/c++/hello_world_xml_compiled/ HelloWorld_subscriber.cxx and look at the source code.

The logic of this simple application is in the **subscriber_main()** function. Similar to the publisher application the logic can be seen as composed of three parts:

- ☐ Type registration (this step is new compared to the HelloWorld_xml_dynamic)
- ☐ Entity creation
- ☐ Use of the Entities

Type Registration: This step is identical to the one for the publisher application. The first thing the application does is register the data-types that were defined in the code-generation step.

This is accomplished calling the **register_type_support()** function on the DomainParticipantFactory.

Please refer to the explanation of the publishing application for more details as this step us regardless of whether the application uses a type to publish or subscribe.

Entity Creation: The steps needed to create the entities are the same as for the HelloWorld_xml_dynamic example. The application first creates a *DomainParticipant* using the function **create_participant_from_config()** this function takes the configuration name of the participant "MyParticipantLibrary::SubscriptionParticipant" which is the same name that was specified in the XML file. Note that the name in the XML file "SubscriptionParticipant" has been qualified with the name of the library it belongs to "MyParticipantLibrary".

This single function call registers all the necessary data-types and creates and the *Topics* and Entities that were specified in the XML file. In this simple case the participant only contains a *Subscriber* "MySubscriber" with a single *DataReader* "HelloDataReader". However in more realistic scenarios this single call can create hundreds of entities (both *DataReaders* and *DataWriters*).

Use of the Entities: The remaining part of the function uses the entities that were created to perform the logic of the program.

This example only needs to read data using the single *DataReader* So the application looks-up the "HelloWorldReader" *DataReader* using the fully qualified name "MyPublisher::HelloWorldReader" and narrows it to be a HelloWorldDataReader:

To process the data, the application installs a Listener on the *DataReader*. The HelloWorldListener, defined on the same file implements the DataReaderListener interface, which the *DataReader* uses to notify the application of relevant events, such as the reception of data.

The last part is the implementation of the listener functions. In this case we only implement the **on_data_available()** operation, which is called when data is received.

The **on_data_available()** function receives all the data into a sequence and then uses the Hello-WorldTypeSupport::print() function to print each data item received.

```
void HelloWorldListener::on_data_available(DDSDataReader* reader)
{
    HelloWorldDataReader *helloWorldReader = NULL;
    HelloWorldSeq dataSeq;
    DDS_SampleInfoSeq infoSeq;
    DDS_ReturnCode_t retcode = DDS_RETCODE_ERROR;
    DDS_Long i = 0;
```

Note that the sequence received is of type **HelloWorldSeq** which contains the native plain language objects of type **HelloWorld**. This can be manipulated directly by the application. For example the fields can be dereferenced as shown in the code snippet below:

```
HelloWorld *helloWorldData = &dataSeq[i];
    printf("count= %s\n", helloWorldData->count);
```

Chapter 3 Using Connext Prototyper

RTI Connext DDS Prototyper is a companion tool for use with the XML-Based Application Creation feature. This tool allows application developers to quickly try out scenarios directly from their XML descriptions, without writing any code.

On a Windows system:

From your command shell, go to **<path** to **examples>\connext_dds\c++\hello_world_xml_dynamic**. Open two console windows.

In one window, type (all on one line):

```
$NDDSHOME\bin\rtiddsprototyper -cfgName PublicationParticipant
"MyParticipantLibrary::PublicationParticipant"
```

In the other window, type (all on one line):

```
$NDDSHOME\bin\rtiddsprototyper -cfgName SubscriptionParticipant
"MyParticipantLibrary::SubscriptionParticipant"
```

On a UNIX-based system:

From your command shell, go to <path to examples>/connext_dds/c++/hello_world_xml_dynamic. Open two console windows.

In one window, type (all on one line):

```
${NDDSHOME}/bin/rtiddsprototyper -cfgName PublicationParticipant "MyParticipantLibrary::PublicationParticipant"
```

In the other window, type (all on one line):

```
${NDDSHOME}/bin/rtiddsprototyper -cfgName SubscriptionParticipant "MyParticipantLibrary::SubscriptionParticipant"
```

You can run both of these on the same computer or on separate computers within the same (multicast enabled) network. You should immediately see the subscribing application receive and print the information from the publishing side.


For more information, please read the *RTI Connext DDS Prototyper Getting Started Guide* (in <**NDDSHOME>/doc/manuals/connext_dds/prototyper**).

Chapter 4 Understanding XML-Based Application Creation

Figure 4.1 depicts a *Connext DDS* application built with the aid of both the *Connext DDS* API and an XML configuration file. Using the XML configuration file in combination with the XML-Based Application Creation feature simplifies and accelerates application development.

The Entities defined in the XML configuration file can be created by a single call to the API. Once created, all Entities can be retrieved from application code using standard "lookup" operations so they can be used to read and write data.

Figure 4.1 Using both Connext API and XML Configuration File to Develop an Application



4.1 Important Points

- Applications can instantiate a *DomainParticipant* from a participant configuration described in the XML Configuration file. All the *Entities* defined by such a participant configuration are created automatically as part of *DomainParticipant* creation. In addition, multiple participant configurations may be defined within a single XML configuration file.
- ☐ All the Entities created from a participant configuration are automatically assigned an entity name. Entities can be retrieved via "lookup" operations specifying their name. Each Entity stores its own name in the QoS policies of the Entity so that they can be retrieved locally (via a lookup) up and communicated via discovery. This is described in

Creating and Retrieving Entities Configured in an XML File (Section 4.7). □ An XML configuration file is not tied to the application that uses it. Different applications may run using the same configuration file. A single file may define multiple participant configurations. A single application can instantiate as many *DomainParticipants* as desired. □ Changes in the XML configuration file do not require recompilation, even if Entities are

added or removed, unless the logic that uses the entities also needs to change.

4.2 Loading XML Configuration Files

Connext DDS loads its XML configuration from multiple locations. This section presents the various approaches, listed in load order.

The following locations contain QoS Profiles (see Chapter 17 in the RTI Connext DDS Core Libraries User's Manual) and may also contain Entity configurations.

This file is loaded automatically if it exists (not the default case) and

This file is loaded automatically if it exists (not the default case) and ignore_resource_profile in the PROFILE QosPolicy is FALSE (the default). NDDS_QOS_PROFILES.xml does not exist by default. However, NDDS_QOS_PROFILES.example.xml is shipped with the host bundle of the product; you can copy it to NDDS_QOS_PROFILES.xml and modify it for your own use. The file contains the default QoS values that will be used for all entity kinds. (First to be loaded)

☐ File specified in NDDS_QOS_PROFILES Environment Variable

The files (or XML strings) separated by semicolons referenced in this environment variable, if any, are loaded automatically. These files are loaded after the NDDS_QOS_PROFILES.xml and they are loaded in the order they appear listed in the environment variable.

☐ <working directory>/USER_QOS_PROFILES.xml

This file is loaded automatically if it exists in the 'working directory' of the application, that is, the directory from which the application is run. (Last to be loaded)

4.3 XML Syntax and Validation

The configuration files uses XML format. Please see Examine the XML Configuration Files Definition (Section 2.1.3) for an example XML file and a description of its contents.

4.3.1 Validation at Run-Time

Connext DDS validates the input XML files using a built-in Document Type Definition (DTD). You can find a copy of the builtin DTD in **\$NDDSHOME/resource/schema/rti_dds_profiles.dtd**.

This is only a copy of the DTD that *Connext DDS* uses. Changing this file has no effect unless you specify its path with the DOCTYPE tag, described below.

You can overwrite the built-in DTD by using the XML tag, <!DOCTYPE>. For example, the following indicates that *Connext DDS* must use a different DTD file to perform validation:

```
<!DOCTYPE dds SYSTEM
"/local/usr/rti/dds/modified_rti_dds_profiles.dtd">
```

If you do not specify the DOCTYPE tag in the XML file, the built-in DTD is used. The DTD path can be absolute or relative to the application's current working directory.

4.3.2 Validation during Editing

Connext DDS provides DTD and XSD files that describe the format of the XML content. We highly recommend including a reference to the XSD in the XML file. This provides helpful features in code editors such as Visual Studio, Eclipse, or Netbeans, including validation and autocompletion while you are editing the XML file.

To include a reference to the XSD file, use the noNamespaceSchemaLocation attribute inside the opening <dds> tag, as illustrated below (replace '5.x.y' with the current version number and replace <NDDSHOME> as described in Paths Mentioned in Documentation (Section 1.1)):

```
<?xml version="1.0" encoding="UTF-8"?>
<dds xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance"
    xsi:noNamespaceSchemaLocation="<NDDSHOME>/resource/schema/
    rti_dds_profiles.xsd"
    version="5.x.y">
```

You may use relative or absolute paths to the schema files. These files are provided as part of your distribution in the following location (replace <NDDSHOME> as described in Paths Mentioned in Documentation (Section 1.1)):

- ☐ <NDDSHOME>/resource/schema/rti_dds_profiles.xsd
- <NDDSHOME>/resource/schema/rti_dds_profiles.dtd

If you want to use the DTD for syntax validation instead of the XSD, use the <!DOCTYPE> tag. Note, however, that this validation is less strict and will offer far less help in terms of auto-completion. The use of <!DOCTYPE> is shown below. Simply replace \$NDDSHOME with your *Connext DDS* installation directory:

```
<?xml version="1.0" encoding="UTF-8"?>
<!DOCTYPE dds SYSTEM
    $NDDSHOME/resource/schema/rti_dds_profiles.dtd">
<dds>
    ...
</dds>
```

4.4 Accessing Entities Defined in XML Configuration from an Application

You can use the operations listed in Table 4.1 to retrieve and then use the *Entities* defined in your XML configuration files.

4.5 XML Tags for Configuring Entities

There are two top-level tags to configure Entities in the XML configuration files:


Table 4.1	Operations Intended for Use with XML-Based Configuration
-----------	--

Working with Configuration-Related Operations		Reference	
	create_participant_from_config		
Domain Pauti sin ant Eastowy	create_participant_from_config_w_params	Section 4.7.1	
DomainParticipantFactory	lookup_participant_by_name		
	register_type_support	Section 4.7.5	
	lookup_publisher_by_name	Section 4.7.2	
DomainParticipant	lookup_subscriber_by_name		
DomainParticipant	lookup_datawriter_by_name		
	lookup_datareader_by_name		
Publisher	lookup_datawriter_by_name	Section 4.7.3	
Subscriber	lookup_datareader_by_name	Section 4.7.5	

- <domain_library>: Defines a collection of domains. A domain defines a global data-space where applications can publish and subscribe to data by referring to the same *Topic* name. Each domain within the domain library defines the *Topics* and associated data-types that can be used within that domain. Note that this list is not necessarily exhaustive. The participants defined within the participant_library> might add *Topics* beyond the ones listed in the domain library.

Figure 4.2 and Table 4.2 describe the top-level tags that are allowed within the root <dds> tag.

Figure 4.2 **Top-Level Tags in Configuration File**



4.5.1 Domain Library

A domain library provides a way to organize a set of domains that belong to the same system. A domain represents a data space where data can be shared by means of reading and writing the same *Topics*, each *Topic* having an associated data-type. Therefore, in a <domain> tag you can specify *Topics* and their data types.

Table 4.2 **Top-Level Tags in Configuration File**

Tags within <dds></dds>	Description		Number of Tags Allowed
	Specifies a	a domain library. Set of <domain> definitions.</domain>	
<domain_library></domain_library>	Attributes:		0 or more
	name	Domain library name	
<pre><participant_library></participant_library></pre>	Specifies	a participant library. Set of <domain_participant> definitions.</domain_participant>	0 or more
<pre><participant_norary></participant_norary></pre>	name	Participant library name	o or more
	Specifies	a QoS library and profiles.	
<qos_library></qos_library>	The contents of this tag are specified in the same manner as for a <i>Connext DDS</i> QoS profile file—see Chapter 17 in the <i>RTI Connext DDS Core Libraries User's Manual</i> .		0 or more
<types></types>	Defines ty	0 or 1	

Figure 4.3 **Domain Library Tag**




Figure 4.3, Table 4.3, and Table 4.4 describe what tags can be in a <domain_library>.

- The <register_type> tag specifies a type definition that will be registered in the *Domain-Participants* whenever they specify a *Topic* associated with that data type.
- ☐ The <topic> tag specifies a *Topic* by associating it with a <register_type> that contains the type information.

In a domain, you can also specify the domain ID to which the *DomainParticipant* associated with this domain will be bound.

Note that a domain may inherit from another "base domain" definition by using the **base_name** attribute. A domain that declares a "base domain" might still override some of the properties in the base domain. Overriding is done simply by including elements in the derived domain with the same name as in the base domain.

The <register_type> tag, described in Figure 4.4 and Table 4.5, determines how a type is registered by specifying the type definition and the name with which it is registered.


Table 4.3 **Domain Library Tags**

Tags within <domain_library></domain_library>	Description		Number of Tags allowed
	Specifies a domain.		
<domain></domain>	Attributes:		
	name	Domain name	
	domain_id (optional)	Domain ID (default id=0)	1 or more
	base_name (optional)	Base domain name. Specifies another domain from which properties will be inherited.	

Table 4.4 **Domain Tags**

Tags within <domain></domain>	Description		Number of Tags allowed	
	Specifies how a type is registered			
	Attributes:			
<register_type></register_type>	name	Name used to refer to this registered type within the XML file. This is also the name under which the type is registered with the <i>DomainParticipants</i> unless overridden by the <registered_name> tag.</registered_name>	1 or more	
	kind	Specifies whether the type is built-in, dynamic data or generated by the user.		
	type_ref (optional)	Reference (fully qualified name) to a defined type within <types>. Required when kind is dynamic data.</types>		
	Specifies a topic as	sociating its data-type and optionally QoS.		
	Attributes:		1 or more 1 or more	
<topic></topic>	name	Name of the topic if no <registered_name> is specified.</registered_name>		
	register_type_ref	Reference (name) to a register_type within this domain with which this topic is associated.		

Figure 4.4 Register Type Tag



The <topic> tag, described in Figure 4.5 and Table 4.6, describes a *Topic* by specifying the name and type of the *Topic*. It may also contain the QoS configuration for that *Topic*.

Table 4.5 Register Type Tag

Tags within <register_type></register_type>	Description	Number of tags allowed
<pre><registered_name> Name with which the type is registered.</registered_name></pre>		0 or 1

Figure 4.5 **Topic Tag**




Table 4.6 Topic Tag

Tags within <topic></topic>	Description	Number of tags allowed
<registered_name></registered_name>	Name of the <i>Topic</i> .	0 or 1
<topic_qos></topic_qos>	Topic QoS configuration.	0 or 1

Some elements may refer to already specified types and QoS tags. The definitions of these referenced tags may appear either in the same configuration file or in a different one—as long as it is one of the ones loaded by *Connext DDS* as described in Section 4.2.

If a QoS is not specified for an Entity, then the QoS will be set to a default value that is either the default configured in the XML files, or if such default does not exist, then the *Connext DDS* QoS defaults. Please see Chapter 17 "Configuring QoS with XML" in the *RTI Connext DDS Core Libraries User's Manual* for additional details in configuring QoS via XML.

For example:

```
<!-- types -->
<types>
    <struct name="MyType">
           <member name="message" type="string"/>
           <member name="count" type="long"/>
    </struct>
</types>
<!-- Domain Library -->
<domain library name="MyDomainLibrary" >
    <domain name="MyDomain" domain_id="10">
           <register type name="MyRegisteredType"
kind="dynamicData" type ref="MyType"/>
           <topic name="MyTopic" register_type_ref="MyType">
                  <topic_qos base_name="qosLibrary::DefaultProfile"/>
           </topic>
    </domain>
</domain_library>
```

The above configuration defines a domain with name "MyDomain" and domain_id "10" containing a *Topic* called "MyTopic" with type "MyType" registered with the name "MyRegistered-Type":

- <register_type>: It defines the registration of a dynamic data type with name "MyRegisteredType" and definition "MyType"—defined in the same file.

Note that the *DomainParticipant* created from a configuration profile bound this domain will be crated with domain_id=10, unless the domain_id is overridden in the participant configuration.

4.5.2 Participant Library

A participant library provides a way to organize a set of participants belonging to the same system. A participant configuration specifies all the entities that a *DomainParticipant* created from this configuration will contain.

Figure 4.6 Participant Library Tag




Figure 4.6, Table 4.7, and Table 4.8 shows the description of a <participant_library> and the tags it contains.

A <domain_participant> can be associated with a domain where topics and their associated types are already defined. The elements <register_type> and <topic> may also be defined in a <domain_participant>—the same way it is done in a <domain>. This makes it possible to add Topics, data-types, etc. beyond the ones defined in the domain, or alternatively redefine the elements that are already in the <domain>.

A <domain_participant> is defined by specifying the set of Entities it contains. This is done using tags such as <publisher>, <subscriber>, <data_writer> and <data_reader>, which specify a Entity of their corresponding type. These Entities are created within the *DomainParticipant* instantiated from the configuration profile that contains the definitions.

Table 4.7 Participant Library Tag


Tags within <participant_library></participant_library>	Description		
	Specifies a participant configuration.		
	Attributes:		
	name	Participant configuration name.	
<domain_participant></domain_participant>	base_name (optional)	Base participant name. It specifies another participant from which to inherit the configuration.	
	domain_ref (optional) Reference (fully qualified name) to a defined <domain> in the domain library.</domain>		1 or more
		Domain ID. If specified, overrides the id in the domain it refers to.	
	domain_id (optional)	If no domain_id is specified directly or in the referenced domain then the default domain_id is 0.	


A <domain_participant> may inherit its configuration from another "base participant" specified using the **base_name** attribute. In this case, overriding applies to the base <domain_participant> as well as to the referred <domain>.

Note that in *DataWriters* always belong to a *Publisher* and *DataReaders* to a *Subscriber*. For this reason the <data_writer> and <data_reader> typically appear nested inside the corresponding <publisher> and <subscriber> tags. However, for convenience, it is possible to define <data_writer> and <data_reader> tags directly under the <domain_participant> tag. In this case, the *DataWriters* and *DataReaders* are created inside the implicit *Publisher* and *Subscriber*, respectively.

The <publisher>, <subscriber>, <data_writer>, and <data_reader> tags are described in Figure 4.7, Table 4.9, Table 4.10, Table 4.11 and Table 4.12.

Figure 4.7 **Publisher and Subscriber Tags**





The <publisher> tag defines by default a *Publisher*. It may contain a QoS configuration and a several *DataWriters*. Likewise, the <subscriber> tag defines by default a *Subscriber*. It may contain a QoS configuration and a several *DataReaders*.

Table 4.8 **Domain Participant Tag**

Tags within <domain_participant></domain_participant>	Description		
<memory_management></memory_management>	Configures certain aspects of how Connext DDS allocates internal memory. The configuration is per DomainParticipant and therefore affects all the contained DataReaders and DataWriters. For example: <domain_participant name="test"> <memory_management> <memory_management} <memory_management_<="" td=""><td></td></memory_management}></memory_management></memory_management></memory_management></memory_management></memory_management></memory_management></memory_management></memory_management></memory_management></memory_management></memory_management></memory_management></memory_management></memory_management></memory_management></memory_management></memory_management></memory_management></memory_management></memory_management></memory_management></memory_management></memory_management></memory_management></memory_management></memory_management></memory_management></memory_management></memory_management></memory_management></memory_management></memory_management></memory_management></memory_management></memory_management></memory_management></memory_management></memory_management></memory_management></memory_management></memory_management></memory_management></memory_management></memory_management></memory_management></memory_management></memory_management></memory_management></memory_management></memory_management></memory_management></memory_management></memory_management></memory_management></memory_management></memory_management></memory_management></memory_management></memory_management></memory_management></memory_management></memory_management></memory_management></memory_management></memory_management></memory_management></memory_management></memory_management></memory_management></memory_management></memory_management></memory_management></memory_management></memory_management></memory_management></domain_participant>		
<register_type></register_type>	Specifies how a type is reg tag	0 or more	
<topic></topic>	Specifies a topic. Same as within the <domain> tag</domain>		0 or more
	Specifies a configuration. Attributes:		
<publisher></publisher>	name	Publisher configuration name.	0 or more
	multiplicity (optional)	Number of <i>Publishers</i> that are created with this configuration. Default is 1.	

Table 4.8 **Domain Participant Tag**

Tags within <domain_participant></domain_participant>	Description			
	Specifies a Subscriber confi			
	Attributes:			
<subscriber></subscriber>	name	Subscriber configuration name.	0 or more	
Coupering	multiplicity (optional)	Number of <i>Subscribers</i> that are created with this configuration.	o or more	
		Default is 1.		
	Specifies a <i>DataWriter</i> cor ated inside the implicit <i>Pu</i> Attributes:	afiguration. The <i>DataWriter</i> will be cre-blisher.		
	name	DataWriter configuration name.		
<data_writer></data_writer>	topic_ref	Reference (name) a <topic> within the <domain> referenced by its <participant> parent.</participant></domain></topic>	0 or more	
	multiplicity (optional)	Number of <i>DataWriters</i> that are created with this configuration. Default is 1.		
	Specifies a data reader con ated inside the implicit sul Attributes:	nfiguration. The <i>DataReader</i> will be crebscriber.		
	name	Data reader configuration name.		
<data_reader></data_reader>	topic_ref	Reference (name) a <topic> within the <domain> referenced by its <participant> parent.</participant></domain></topic>	0 or more	
	multiplicity (optional) Number of DataReaders that are created with this configuration.			
	Default is 1.			
<pre><participant_qos></participant_qos></pre>	DomainParticipant QoS cor	0 or 1		

Table 4.9 **Publisher Tag**

Tags within <publisher></publisher>	Description	Number of Tags Allowed
Specifies a <i>DataWriter</i> configuration. Same as within the <participant> tag. Output Output Description: O</participant>		0 or more
<publisher_qos></publisher_qos>	Publisher QoS configuration.	0 or 1

Table 4.10 **Subscriber Tag**

Tags within <subscriber></subscriber>	Description	Number of Tags Allowed
<data_reader></data_reader>	Specifies a <i>DataReader</i> configuration. Same as within the <participant> tag.</participant>	0 or more
<subscriber_qos></subscriber_qos>	Subscriber QoS configuration.	0 or 1

Table 4.11 DataWriter Tag

Tags within <data_writer></data_writer>	Description	Number of Tags Allowed
<datawriter_qos></datawriter_qos>	DataWriter QoS configuration	0 or 1

Table 4.12 DataReader Tags

Tags within <data_reader></data_reader>		Number of Tags Allowed	
<datareader_qos></datareader_qos>	DataReader Qo	S configuration.	0 or more
		Enables the creation of <i>DataReader</i> with this configuration from a ContentFilteredTopic. Attributes:	
<filter></filter>	name	Name of the ContentFilteredTopic. The ContentFilteredTopic will be associated with the same <i>Topic</i> referenced by the containing <data_reader></data_reader>	0 or 1
	filter_kind	Specifies which ContentFilter to use. It defaults to the builtin.sql filter.	

The <filter> tag within a <data_reader> enables content filtering. It causes the corresponding <code>DataReader</code> to be created from a ContentFilteredTopic with the specified filter characteristics.

Table 4.13 Filter Tag

Tags within <filter></filter>	Description	Number of Tags Allowed
<expression></expression>	Filter expression	0 or 1
<pre><parameter_list></parameter_list></pre>	List of parameters. Parameters are specified using <param/> tags. The maximum number of parameters is 100. <parameter_list></parameter_list>	0 or 1

For example:

The above configuration defines a <domain_participant> that is bound to the <domain> "MyDomain".

A *DomainParticipant* created from this configuration will contain:

- ☐ A Publisher which has a *DataWriter* created from the *Topic* "MyTopic".
- ☐ A Subscriber which has *DataReader* created from a ContentFilteredTopic whose related *Topic*, "MyTopic", uses a SQL filter.

4.6 Names Assigned to Entities

Each Entity configured in a XML file is given a unique name. This name is used to refer to them from other parts of the XML configuration and also to retrieve them at run-time using the *Connext DDS* API.

In the context of XML-based configuration we should distinguish between two kinds of names:

- ☐ **Configuration name**: The name of a specific Entity's configuration. It is given by the name attribute of the corresponding XML element.
- ☐ Entity name: The actual name of the Entity within the run-time system. In most cases, the Entity name is the same as the configuration name. However there are two exceptions:
 - *DomainParticipants* may be given their Entity names explicitly when they are created using **create_participant_from_config_w_params()**. If no explicit name is given, as occurs with **create_participant_from_config()**, a name will be generated automatically (see Creating and Retrieving a DomainParticipant Configured in an XML File (Section 4.7.1)).
 - Whenever the attribute **multiplicity** is set to a value greater than one. This setting indicates that a set of Entities should be all from the same configuration. As each Entity must have a unique name the system will automatically append a number to the configuration name to obtain the Entity name. For example, if we specified a multiplicity of "N", then for each index "i" between 0 and N-1 the system will assign entity names according to the table below:

Entity Name	Index: i
"configuration_name"	0
"configuration_name#i"	[1,N-1]

That is, the Entity name followed by the token "#" and an index.

For example:

For the above XML	configuration.	the name	assignment is:
I OI tile above mil	commandation	die ilaiie	abbiginitelle ib.

Configuration	Entity	Multiplicity	Entity Names
"MyPublisher"	Publisher	1	"MyPublisher"
			"MyWriter"
"MyWriter"	DataWriter	3	"MyWriter#1"
			"MyWriter#2"

The entity name is stored by *Connext DDS* using the EntityNameQosPolicy QoS policy for *DomainParticipants, Publishers, Subscribers, DataWriters* and *DataReaders*. The policy is represented by the following C structure:

```
Struct DDS_EntityNameQosPolicy {
   char * name;
   char * role_name
}
```

The mapping is:

Field	Value
name	Entity name
role_name	Configuration name

For example, for the following configuration:

The corresponding QoS policies for each entity are:

Entity	QoS Policy	Field Values
DomainParticipant	EntityNameQosPolicy	name = [participant_name]
Domain articipant	EntityNameQosf oncy	role_name = "MyParticipant"
Dealaltala au	Entite-Name Oce Daline	name = "MyPublisher"
Publisher	EntityNameQosPolicy	role_name = "MyPublisher"
DataMuitou	EntityNameQosPolicy	name = "MyWriter"
DataWriter		role_name = "MyWriter"

Where [participant_name] represents the value of the participant entity name specified at creation time

4.6.1 Referring to Entities and Other Elements within XML Files

Entities and other elements within the XML file are addressed using a hierarchical name that matches their declaration hierarchy. This is summarized in the table below.

Entity or Element	Hierarchical Name	Example Use
type	[type_name]	type_ref="MyType"
qos	[qos_library_name]::[qos_profile_name]	base_name="qosLibrary::DefaultProfile"

Entity or Element	Hierarchical Name	Example Use
domain	[domain_libary_name]::[domain_name]	domain_ref= "MyDomainLibrary::MyDomain"
participant	[participant_library_name]:: [participant_name]	base_name= "MyParticipantLibrary::PublicationParticipant"
topic	[topic_name] Must be defined within the scope of the Domain or the Participant that refer to it	topic_ref="MyTopic"
publisher	[subscriber_name] Must be defined within the scope of the Participant that refers to it	base_name="MyPublisher"
subscriber	[subscriber_name] Must be defined within the scope of the Participant that refers to it	base_name="MySubscriber"
data_writer	[publisher_name]::[datawriter_name] If addressing from within the same Publisher the "publisher_name::" prefix may be omitted	base_name="MyPublisher::MyWriter" base_name="MyWriter"
data_reader	[subscriber_name]::[datareader_name] If addressing from within the same Subscriber the "subscriber_name::" prefix may be omitted	base_name="MySubscriber::MyReader" base_name="MyReader"

The example above corresponds to a configuration such as the one following:

```
<dds xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance"</pre>
xsi:noNamespaceSchemaLocation="../../resource/schema/
rti dds profiles.xsd"
version="5.x.y">
    <types>
           <struct name="MyType">
                  <member name="mylong" type="long"/>
           </struct>
    </types>
    <domain library name="MyDomainLibrary" >
           <domain name="MyDomain" domain id="0">
                  <register_type name="MyRegisteredType"
                         kind="dynamicData" type ref="MyType" />
                  <topic name="MyTopic"
                         register type ref="MyRegisteredType"/>
           </domain>
    </domain library>
    <participant_library name="MyParticipantLibrary">
    <domain participant name="MyParticipant"</pre>
           domain_ref="MyDomainLibrary::MyDomain">
                  <publisher name="MyPublisher">
                         <data_writer name="MyWriter" topic_ref="MyTopic"/>
                  </publisher>
```

4.7 Creating and Retrieving Entities Configured in an XML File

There are two kinds of operations that affect *Entities* configured in an XML file:

- ☐ Create the defined entities. Only the operation **create_participant_from_config()** in the DomainParticipantFactory triggers the creation of a *DomainParticipant* and all its contained Entities given a configuration name.
- □ Retrieve the defined entities: After creation, you can retrieve the defined Entities by using the lookup_by_name() operations available in the DomainParticipantFactory, DomainParticipant, Publisher and Subscriber.

4.7.1 Creating and Retrieving a DomainParticipant Configured in an XML File

To create a *DomainParticipant* from a configuration profile in XML, use the function **create_participant_from_config()**, which receives the configuration name and creates all the entities defined by that configuration.

For example:

Given the above configuration, a DomainParticipant is created as follows:

The *DomainParticipant* is bound to the domain_id specified in either the <domain_participant> tag—this has precedence—or the <domain> tag. In this example the domain_id is set to one.

When the *DomainParticipant* is created by means of **create_participant_from_config()**, a name will be generated automatically based on the configuration name and the number of existing participants created from the same configuration. The generation follows the same strategy explained in Names Assigned to Entities (Section 4.6) for the domain entities where the multiplicity is replaced by the number of existing participants. If this is number is identified by "N", the participant name for a new participant will be assigned as follows:

Participant Name	N
"configuration_name"	0
"configuration_name#N"	[1,N-1]

For example, if we create three participants from the configuration "lib::participant", the names assigned as the participants are created will be:

- -participant
- -participant#1
- -participant#2

Once a participant is created, it can be retrieved by its name at any other place in your program as follows, based on the previous example and assuming that only one participant was created:

```
participant =
    DDSTheParticipantFactory->lookup_participant_by_name("MyParticipant");
if (participant == NULL) {
    //handle error
}
```

To provide more flexibility, **create_participant_from_config_w_params()** allows you to specify the participant name. You can also override the specification in the configuration for the domain ID and QoS profile for the participant and entites in the domain.

4.7.2 Creating and Retrieving Publishers and Subscribers

Publishers and *Subscribers* configured in XML are created automatically when a *DomainParticipant* is created from the <domain_participant> that contains the <publisher> and <subscriber> configurations.

Given the following example:

Once a *DomainParticipant* is created as explained in Creating and Retrieving a DomainParticipant Configured in an XML File (Section 4.7.1), *Publishers* and *Subscribers* can be retrieved from the created *DomainParticipant* using their name as follows:

```
DDSPublisher * publisher =
    participant->lookup_publisher_by_name("MyPublisher");
if (publisher == NULL) {
    //handle error
}

DDSPublisher * publisher_1 =
    participant->lookup_publisher_by_name("MyPublisher#1");
if (publisher == NULL) {
    //handle error
```

```
DDSSubscriber * subscriber =
    participant->lookup_subscriber_by_name("MySubscriber");
if (subscriber == NULL) {
    //handle error
}
```

4.7.3 Creating and Retrieving DataWriters and DataReaders

DataWriters and DataReaders configured in XML are created automatically when a DomainParticipant is created from the <domain_participant> that contains the <data_writer> and <data_reader> configurations.

Given the following example:

Once a *DomainParticipant* is created as explained in Section 4.7.1, *DataWriters* and *DataReaders* can be retrieved from the created *DomainParticipant* using their fully-qualified name as shown below:

```
DDSDataWriter * dataWriter =
   participant->lookup_dataWriter_by_name("MyPublisher::MyWriter");

if (dataWriter == NULL) {
    //handle error
}

DDSDataReader * dataReader =
   participant->lookup_datareader_by_name("MySubscriber::MyReader");

if (dataReader == NULL) {
    //handle error
}
```

Or from the created Publisher and Subscriber using their 'unqualified' name as shown below:

```
DDSDataWriter * dataWriter =
    publisher->lookup_dataWriter_by_name("MyWriter");

if (dataWriter == NULL) {
    //handle error
}

DDSDataReader * dataReader =
    subscriber->lookup_datareader_by_name("MyReader");
```

4.7.4 Creating Content Filters

To use a content filter, modify the "SubscriptionParticipant" configuration to look like this:

It adds a SQL content filter, which only accepts samples with the field count greater than two.

Now run the HelloWorld_subscriber application without recompiling and check that it only receives data when counter less than 20 as expected.

4.7.5 Using User-Generated Types

If a user-generated type by means of *rtiddsgen* is desired rather than dynamic data, the corresponding type support must be registered with the DomainParticipantFactory before creating a *DomainParticipant*. To register the type support, use the function **register_type_support()** in the DomainParticipantFactory, which takes (a) a pointer to a function that registers a type and (b) the type name it is registered with. Then the specified function will be called automatically by the middleware whenever the type registration is needed.

The definition of this function is given by:

This "register type function" should be generated using the *rtiddsgen* command-line tool from the IDL or XML definition of the data type. See Hello World using XML and Compiled Types (Section 2.2) for a simple example of how to follow this process.

For example, the following XML snippet defines a data type registered under the name **MyType** with a TypeSupport that is user-generated. To use this data type, the application must also generate the TypeSupport code for the appropriate language binding using *rtiddsgen* and associate the generated TypeSupport with the name **MyType**. This association is made by calling the operation **register_type_support()** on the DomainParticipantFactory:

Continuing the example above, assume that the structure of "MyType" is described in the IDL file MyType.idl. Also assume that you are using the C++ language API and you have already run rtiddsgen and generated the type-support files: MyTypeSupport.h and MyTypeSupport.cxx. These files will contain the declaration and implementation of the function MyTypeSupport::register_type(). In this situation, you must associate the MyTypeSupport::register_type() operation with the type name MyType by calling DDSTheParticipantFactory->register_type_support() from your application code prior to creating the DomainParticipant as shown in the C++ snippet below:

You can find an example of using a user-generated type in path to examples>/connext_dds/
c++/hello_world_xml_compiled. Also refer to the description of this example in Hello World
using XML and Compiled Types (Section 2.2).