### The Harmonic Oscillator

Adam Wilson

Salt Lake Community College

#### Newton's Dot Notation

Scientists and Engineers who work with many variables where the independent variables is always t commonly use the notation:

$$\dot{x} = \frac{dx}{dt}$$
 and  $\ddot{x} = \frac{dx^2}{d^2t}$  and  $\ddot{x} = \frac{dx^3}{d^3t}$  and  $\ddot{x} = \frac{dx^4}{d^4t}$ 

#### Newton's Dot Notation

Scientists and Engineers who work with many variables where the independent variables is always t commonly use the notation:

$$\dot{x} = \frac{dx}{dt}$$
 and  $\ddot{x} = \frac{dx^2}{d^2t}$  and  $\ddot{\ddot{x}} = \frac{dx^3}{d^3t}$  and  $\ddot{\ddot{x}} = \frac{dx^4}{d^4t}$ 

#### Definition


A very important DE is the second-order homogeneous equation

$$m\ddot{x} + b\dot{x} + kx = 0$$

where m > 0, b, and k are constants.


This models a class of phenomena called damped harmonic oscillators.

### The Mass-Spring System



We will model the Mass-Sprint system using Newton's Second Law of Motion,  $F=m\ddot{x}$ , where F is the sum of the following forces:


### The Mass-Spring System



We will model the Mass-Sprint system using Newton's Second Law of Motion,  $F = m\ddot{x}$ , where F is the sum of the following forces:

• The restoring force of the spring.  $F_{\text{restoring}} = -kz$  where k > 0


### The Mass-Spring System



We will model the Mass-Sprint system using Newton's Second Law of Motion,  $F = m\ddot{x}$ , where F is the sum of the following forces:

- The restoring force of the spring.  $F_{\text{restoring}} = -kz$  where k > 0
- The damping force.  $F_{\text{damping}} = -bx$  where  $b \ge 0$


### The Mass-Spring System



We will model the Mass-Sprint system using Newton's Second Law of Motion,  $F = m\ddot{x}$ , where F is the sum of the following forces:

- The restoring force of the spring.  $F_{\text{restoring}} = -kz$  where k > 0
- The damping force.  $F_{\text{damping}} = -bx$  where  $b \ge 0$
- Any external "driving" forces.  $F_{\text{external}} = f(t)$  where f(t) is the sum of all external forces.

### The Mass-Spring System



We will model the Mass-Sprint system using Newton's Second Law of Motion,  $F = m\ddot{x}$ , where F is the sum of the following forces:

- The restoring force of the spring.  $F_{\text{restoring}} = -kz$  where k > 0
- The damping force.  $F_{\text{damping}} = -bx$  where  $b \ge 0$
- Any external "driving" forces.  $F_{\text{external}} = f(t)$  where f(t) is the sum of all external forces.

Summing these forces gives:  
mass × acceleration = 
$$F_{\text{restoring}}$$
 +  $F_{\text{damping}}$  +  $F_{\text{external}}$   
 $m\ddot{x} = -kx$  -  $b\dot{x}$  +  $f(t)$ 

#### Simple Harmonic Oscillator

The simple harmonic oscillator equation is

$$m\ddot{x} + b\dot{x} + kx = f(t)$$

with constant coefficients m > 0, k > 0, and  $b \ge 0$ .

#### Simple Harmonic Oscillator

The simple harmonic oscillator equation is

$$m\ddot{x} + b\dot{x} + kx = f(t)$$

with constant coefficients m > 0, k > 0, and  $b \ge 0$ .

 When b = 0, the motion is called undamped; otherwise it is damped.

### Simple Harmonic Oscillator

The simple harmonic oscillator equation is

$$m\ddot{x} + b\dot{x} + kx = f(t)$$

with constant coefficients m > 0, k > 0, and  $b \ge 0$ .

- When b = 0, the motion is called undamped; otherwise it is damped.
- If f(t) = 0 for all t, then the equation is homogeneous:

$$m\ddot{x} + b\dot{x} + kx = 0$$

and the motion is called **unforced**, **undriven**, or **free**; otherwise it is called **forced** or **driven**.

### Example

Let us consider a mass of 1kg resting on a table that is attached to the wall by a spring.

#### Example

Let us consider a mass of 1kg resting on a table that is attached to the wall by a spring.

We discover that it takes a force of 1 newton to push the mass 0.25 meters from it's resting position.

$$k = \frac{1 \text{ newton}}{0.25 \text{ meter}} = 4 \frac{\text{newton}}{\text{meter}}$$

#### Example

Let us consider a mass of 1kg resting on a table that is attached to the wall by a spring.

We discover that it takes a force of 1 newton to push the mass 0.25 meters from it's resting position.

$$k = \frac{1 \text{ newton}}{0.25 \text{ meter}} = 4 \frac{\text{newton}}{\text{meter}}$$

We also measure the damping force of the object sliding on the table to be 0.5 newtons when the velocity is 0.25 meters per second.

$$b = \frac{0.5 \text{ newton}}{0.25 \frac{\text{meter}}{\text{second}}} = 2 \frac{\text{newton second}}{\text{meter}}$$

### Example

The object is pulled to the right until the spring is stretched 0.5 meters and then released. (The motion is unforced.)

### Example

The object is pulled to the right until the spring is stretched 0.5 meters and then released. (The motion is unforced.) So, the initial conditions are

$$x(0) = 0.5$$
 meters and  $\dot{x}(0) = 0 \frac{\text{meter}}{\text{second}}$ 

### Example

The object is pulled to the right until the spring is stretched 0.5 meters and then released. (The motion is unforced.) So, the initial conditions are

$$x(0) = 0.5$$
 meters and  $\dot{x}(0) = 0 \frac{\text{meter}}{\text{second}}$ 

We can now formulate the IVP that describes this system

$$m\ddot{x} + b\dot{x} + kx = f(t)$$

### Example

The object is pulled to the right until the spring is stretched 0.5 meters and then released. (The motion is unforced.) So, the initial conditions are

$$x(0) = 0.5$$
 meters and  $\dot{x}(0) = 0 \frac{\text{meter}}{\text{second}}$ 

We can now formulate the IVP that describes this system

$$m\ddot{x} + b\dot{x} + kx = f(t)$$
  
 $\ddot{x} + 2\dot{x} + 4x = 0$   $x(0) = 0.5, \dot{x}(0) = 0$ 

### Example

The object is pulled to the right until the spring is stretched 0.5 meters and then released. (The motion is unforced.) So, the initial conditions are

$$x(0) = 0.5$$
 meters and  $\dot{x}(0) = 0 \frac{\text{meter}}{\text{second}}$ 

We can now formulate the IVP that describes this system

$$m\ddot{x} + b\dot{x} + kx = f(t)$$
  
 $\ddot{x} + 2\dot{x} + 4x = 0$   $x(0) = 0.5, \dot{x}(0) = 0$ 

Notice that a second-order DE requires **two** initial conditions.

### Systems of Units

There are three systems of units you are likely to encounter:

### Systems of Units

There are three systems of units you are likely to encounter:

• International System of Units (SI).

### Systems of Units

There are three systems of units you are likely to encounter:

- International System of Units (SI).
- Centimetre-Gram-Second system of units, a precursor to SI.

### Systems of Units

There are three systems of units you are likely to encounter:

- International System of Units (SI).
- Centimetre-Gram-Second system of units, a precursor to SI.
- United States customary units, the variant of Imperial Units that the United States uses.

### Systems of Units

There are three systems of units you are likely to encounter:

- International System of Units (SI).
- Centimetre-Gram-Second system of units, a precursor to SI.
- United States customary units, the variant of Imperial Units that the United States uses.

Quantity	SI	CGS	<b>US Customary</b>
Force	newton (N)	dyne	pound (lb)

### Systems of Units

There are three systems of units you are likely to encounter:

- International System of Units (SI).
- Centimetre-Gram-Second system of units, a precursor to SI.
- **United States customary units**, the variant of Imperial Units that the United States uses.

Quantity	SI	CGS	<b>US Customary</b>
Force	newton (N)	dyne	pound (lb)
Mass	kilogram (kg)	gram (gm)	slug (lb sec^2/ft)

### Systems of Units

There are three systems of units you are likely to encounter:

- International System of Units (SI).
- Centimetre-Gram-Second system of units, a precursor to SI.
- **United States customary units**, the variant of Imperial Units that the United States uses.

Quantity	SI	CGS	<b>US Customary</b>
Force	newton (N)	dyne	pound (lb)
Mass	kilogram (kg)	gram (gm)	slug (lb sec^2/ft)
Length	meter (m)	centimeter (cm)	foot (ft)

### Systems of Units

There are three systems of units you are likely to encounter:

- International System of Units (SI).
- Centimetre-Gram-Second system of units, a precursor to SI.
- United States customary units, the variant of Imperial Units that the United States uses.

Quantity	SI	CGS	<b>US Customary</b>
Force	newton (N)	dyne	pound (lb)
Mass	kilogram (kg)	gram (gm)	slug (lb sec^2/ft)
Length	meter (m)	centimeter (cm)	foot (ft)
Energy	joule	erg	foot-pound (ft-lb)

### Systems of Units

There are three systems of units you are likely to encounter:

- International System of Units (SI).
- Centimetre-Gram-Second system of units, a precursor to SI.
- United States customary units, the variant of Imperial Units that the United States uses.

Quantity	SI	CGS	<b>US Customary</b>
Force	newton (N)	dyne	pound (lb)
Mass	kilogram (kg)	gram (gm)	slug (lb sec^2/ft)
Length	meter (m)	centimeter (cm)	foot (ft)
Energy	joule	erg	foot-pound (ft-lb)
Gravity (Earth)	9.8 $\frac{m}{s^2}$	980.665 $\frac{\text{cm}}{\text{s}^2}$	$32 \frac{ft}{s^2}$

We can easily guess a solution to

$$m\ddot{x} + kx = 0$$

We can easily guess a solution to

$$m\ddot{x} + kx = 0$$

We know that  $(\sin(t))'' = -\sin(t)$  and  $(\cos(t))'' = -\cos(t)$ . So, a solution to the DE is probably going to contain sines and cosines.

We can easily guess a solution to

$$m\ddot{x} + kx = 0$$

We know that  $(\sin(t))'' = -\sin(t)$  and  $(\cos(t))'' = -\cos(t)$ . So, a solution to the DE is probably going to contain sines and cosines. Comparing

$$(\sin(\omega_0 t))'' = -\omega_0^2 \sin(\omega_0 t)$$
 and  $\ddot{x} = -\frac{k}{m}x$ 

we see that if  $\omega_0 = \sqrt{\frac{k}{m}}$ , then  $x(t) = \sin(\omega_0 t)$  is a solution.

We can easily guess a solution to

$$m\ddot{x} + kx = 0$$

We know that  $(\sin(t))'' = -\sin(t)$  and  $(\cos(t))'' = -\cos(t)$ . So, a solution to the DE is probably going to contain sines and cosines. Comparing

$$(\sin(\omega_0 t))'' = -\omega_0^2 \sin(\omega_0 t)$$
 and  $\ddot{x} = -\frac{k}{m}x$ 

we see that if  $\omega_0 = \sqrt{\frac{k}{m}}$ , then  $x(t) = \sin(\omega_0 t)$  is a solution.

Another solutions is  $x(t) = \cos(\omega_0 t)$ .

### Solution of the Undamped Unforced Oscillator

For the undamped unforced oscillator

$$m\ddot{x} + kx = 0$$

we know two solutions:

$$x(t)=\cos{(\omega_0 t)}$$
 and  $x(t)=\sin{(\omega_0 t)}$  where  $\omega_0=\sqrt{\frac{k}{m}}$ 

### Solution of the Undamped Unforced Oscillator

For the undamped unforced oscillator

$$m\ddot{x} + kx = 0$$

we know two solutions:

$$x(t)=\cos{(\omega_0 t)}$$
 and  $x(t)=\sin{(\omega_0 t)}$  where  $\omega_0=\sqrt{\frac{k}{m}}$ 

The Superposition Principle tells us that any linear combination of these two solutions is itself a solution. Thus, for  $c_1,c_2\in\mathbb{R}$ , the family of solutions is

$$x(t) = c_1 \cos(\omega_0 t) + c_2 \sin(\omega_0 t)$$

### Solution of the Undamped Unforced Oscillator

For the undamped unforced oscillator

$$m\ddot{x} + kx = 0$$

we know two solutions:

$$x(t)=\cos{(\omega_0 t)}$$
 and  $x(t)=\sin{(\omega_0 t)}$  where  $\omega_0=\sqrt{\frac{k}{m}}$ 

The Superposition Principle tells us that any linear combination of these two solutions is itself a solution. Thus, for  $c_1,c_2\in\mathbb{R}$ , the family of solutions is

$$x(t) = c_1 \cos(\omega_0 t) + c_2 \sin(\omega_0 t)$$

We will see next section that these are all of the solutions.

### Alternate Form of the Undamped Unforced Oscillator Solution

Solutions to the undamped unforced oscillator may also be expressed as

$$x(t) = A\cos\left(\omega_0 t - \delta\right)$$

- *A* is the **amplitude**
- ullet  $\delta$  is the **phase angle**, measured in radians.

• The motion has **circular frequency** 
$$\omega_o = \sqrt{\frac{k}{m}}$$
, measured in  $\frac{\text{radians}}{\text{second}}$ 

- The natural frequency is  $f_0 = \frac{\omega_0}{2\pi}$
- The **period** is  $\frac{1}{f_0} = \frac{2\pi}{\omega_0} = 2\pi \sqrt{\frac{m}{k}}$ , measured in seconds.
- This is a horizontal translation of  $A\cos{(\omega_o t)}$  with **phase shift**  $\frac{\partial}{\partial t}$

## Alternate Form of the Undamped Unforced Oscillator Solution

$$x(t) = A\cos\left(\omega_0 t - \delta\right)$$

- *A* is the **amplitude**.
- ullet  $\delta$  is the **phase angle**, measured in radians.
- The motion has **circular frequency**  $\omega_o = \sqrt{\frac{k}{m}}$ , measured in  $\frac{\text{radians}}{\text{second}}$
- The natural frequency is  $f_0 = \frac{\omega_0}{2\pi}$
- The **period** is  $\frac{1}{f_0} = \frac{2\pi}{\omega_0} = 2\pi \sqrt{\frac{m}{k}}$ , measured in seconds.
- This is a horizontal translation of  $A\cos{(\omega_o t)}$  with **phase shift**  $\frac{c}{\omega}$

## Alternate Form of the Undamped Unforced Oscillator Solution

$$x(t) = A\cos\left(\omega_0 t - \delta\right)$$

- A is the amplitude.
- $\bullet~\delta$  is the **phase angle**, measured in radians.
- The motion has **circular frequency**  $\omega_o = \sqrt{\frac{k}{m}}$ , measured in  $\frac{\text{radians}}{\text{second}}$
- The natural frequency is  $f_0 = \frac{\omega_0}{2\pi}$
- The **period** is  $\frac{1}{f_0} = \frac{2\pi}{\omega_0} = 2\pi \sqrt{\frac{m}{k}}$ , measured in seconds.
- This is a horizontal translation of  $A\cos{(\omega_o t)}$  with **phase shift**  $\frac{c}{\omega}$

## Alternate Form of the Undamped Unforced Oscillator Solution

$$x(t) = A\cos\left(\omega_0 t - \delta\right)$$

- *A* is the **amplitude**.
- $\delta$  is the **phase angle**, measured in radians.
- The motion has **circular frequency**  $\omega_o = \sqrt{\frac{k}{m}}$ , measured in  $\frac{\text{radians}}{\text{second}}$ .
- The natural frequency is  $f_0 = \frac{\omega_0}{2\pi}$
- The **period** is  $\frac{1}{f_0} = \frac{2\pi}{\omega_0} = 2\pi \sqrt{\frac{m}{k}}$ , measured in seconds.
- This is a horizontal translation of  $A\cos(\omega_o t)$  with **phase shift**  $\frac{\sigma}{\omega}$

## Alternate Form of the Undamped Unforced Oscillator Solution

$$x(t) = A\cos\left(\omega_0 t - \delta\right)$$

- A is the amplitude.
- $\delta$  is the **phase angle**, measured in radians.
- The motion has **circular frequency**  $\omega_o = \sqrt{\frac{k}{m}}$ , measured in  $\frac{\text{radians}}{\text{second}}$ .
- The **natural frequency** is  $f_0 = \frac{\omega_0}{2\pi}$ .
- The **period** is  $\frac{1}{f_0} = \frac{2\pi}{\omega_0} = 2\pi \sqrt{\frac{m}{k}}$ , measured in seconds.
- This is a horizontal translation of  $A\cos(\omega_o t)$  with **phase shift**  $\frac{\partial}{\partial t}$

## Alternate Form of the Undamped Unforced Oscillator Solution

$$x(t) = A\cos(\omega_0 t - \delta)$$

- A is the amplitude.
- $\delta$  is the **phase angle**, measured in radians.
- The motion has **circular frequency**  $\omega_o = \sqrt{\frac{k}{m}}$ , measured in  $\frac{\text{radians}}{\text{second}}$ .
- The **natural frequency** is  $f_0 = \frac{\omega_0}{2\pi}$ .
- The **period** is  $\frac{1}{f_0} = \frac{2\pi}{\omega_0} = 2\pi\sqrt{\frac{m}{k}}$ , measured in seconds.
- This is a horizontal translation of  $A\cos(\omega_o t)$  with **phase shift**  $\frac{\partial}{\partial t}$

#### Alternate Form of the Undamped Unforced Oscillator Solution

$$x(t) = A\cos(\omega_0 t - \delta)$$

- A is the amplitude.
- $\delta$  is the **phase angle**, measured in radians.
- The motion has **circular frequency**  $\omega_o = \sqrt{\frac{k}{m}}$ , measured in  $\frac{\text{radians}}{\text{second}}$ .
- The **natural frequency** is  $f_0 = \frac{\omega_0}{2\pi}$ .
- The **period** is  $\frac{1}{f_0} = \frac{2\pi}{\omega_0} = 2\pi\sqrt{\frac{m}{k}}$ , measured in seconds.
- This is a horizontal translation of  $A\cos(\omega_o t)$  with **phase shift**  $\frac{\delta}{\omega_0}$ .

#### Converting from one form to the other

The translation is given by

$$A=\sqrt{c_1^2+c_2^2}, \qquad an\left(\delta
ight)=rac{c_2}{c_1}$$

and

$$c_1 = A\cos(\delta), \qquad c_2 = A\sin(\delta)$$

## Example

Let us solve the following second-order IVP.

$$\ddot{x} + x = 0$$
,  $x(0) = 0$ ,  $\dot{x}(0) = 1$ 

## Example

Let us solve the following second-order IVP.

$$\ddot{x} + x = 0$$
,  $x(0) = 0$ ,  $\dot{x}(0) = 1$ 

So, 
$$m = 1$$
,  $k = 1$ , and  $\omega_0 = \sqrt{\frac{1}{1}} = 1$ .

## Example

Let us solve the following second-order IVP.

$$\ddot{x} + x = 0$$
,  $x(0) = 0$ ,  $\dot{x}(0) = 1$ 

So, 
$$m = 1$$
,  $k = 1$ , and  $\omega_0 = \sqrt{\frac{1}{1}} = 1$ .

The general solution is

$$x(t) = c_1 \cos(t) + c_2 \sin(t)$$

and differentitating gives

$$\dot{x} = -c_1 \sin(t) + c_2 \cos(t)$$

#### Example

Let us solve the following second-order IVP.

$$\ddot{x} + x = 0$$
,  $x(0) = 0$ ,  $\dot{x}(0) = 1$ 

So, 
$$m = 1$$
,  $k = 1$ , and  $\omega_0 = \sqrt{\frac{1}{1}} = 1$ .

The general solution is

$$x(t) = c_1 \cos(t) + c_2 \sin(t)$$


and differentitating gives

$$\dot{x} = -c_1 \sin(t) + c_2 \cos(t)$$

Substituting t = 0, x(0) = 0, and  $\dot{x}(0) = 1$  into this system gives the solution  $c_1 = 0$  and  $c_2 = 1$ .

## Example

Let us look at some plots concerning  $\ddot{x} + 0.25x = 0$ :



#### Phase Portraits

For any autonomous second-order differential equation

$$\ddot{x} = F(x, \dot{x})$$

the **phase plane** is the two-dimensional graph with x and  $\dot{x}$  axes.

#### Phase Portraits

For any autonomous second-order differential equation

$$\ddot{x} = F(x, \dot{x})$$

the **phase plane** is the two-dimensional graph with x and  $\dot{x}$  axes. The phase plane has a **vector field** specified by the DE, which at any point in the phase plane gives a direction vector with

horizontal component  $dx/dt = \dot{x}$ vertical component  $d\dot{x}/dt = \ddot{x}$ 

#### Phase Portraits

For any autonomous second-order differential equation

$$\ddot{x} = F(x, \dot{x})$$

the **phase plane** is the two-dimensional graph with x and  $\dot{x}$  axes. The phase plane has a **vector field** specified by the DE, which at any point in the phase plane gives a direction vector with

horizontal component  $dx/dt = \dot{x}$ vertical component  $d\dot{x}/dt = \ddot{x}$ 

A **trajectory** is a path formed parametrically by the DE solutions x(t) and  $\dot{x}(t)$  as they follow the vector field. A graph showing phase plane trajectories is called a **phase portrait**.

#### Phase Portraits

For any autonomous second-order differential equation

$$\ddot{x} = F(x, \dot{x})$$

the **phase plane** is the two-dimensional graph with x and  $\dot{x}$  axes. The phase plane has a **vector field** specified by the DE, which at any point in the phase plane gives a direction vector with

horizontal component 
$$dx/dt = \dot{x}$$
  
vertical component  $d\dot{x}/dt = \ddot{x}$ 

A **trajectory** is a path formed parametrically by the DE solutions x(t) and  $\dot{x}(t)$  as they follow the vector field. A graph showing phase plane trajectories is called a **phase portrait**.

Note: Phase portraits can be graphed without solving the DE.

#### **Definition**

The second-order differential equation

$$m\ddot{x} + b\dot{x} + kx = f(t)$$

is equivalent to the system of first-order equations:

$$\dot{x} = y$$
 $\dot{y} = \ddot{x} = \frac{f(t)}{m} - \frac{k}{m}x - \frac{b}{m}y$ 

#### **Definition**

The second-order differential equation

$$m\ddot{x} + b\dot{x} + kx = f(t)$$

is equivalent to the system of first-order equations:

$$\dot{x} = y$$

$$\dot{y} = \ddot{x} = \frac{f(t)}{m} - \frac{k}{m}x - \frac{b}{m}y$$

#### Example

To draw the vector field for  $\ddot{x} + 0.25x = 0$  we can build the system:

#### **Definition**

The second-order differential equation

$$m\ddot{x} + b\dot{x} + kx = f(t)$$

is equivalent to the system of first-order equations:

$$\dot{x} = y$$
 $\dot{y} = \ddot{x} = \frac{f(t)}{m} - \frac{k}{m}x - \frac{b}{m}y$ 

#### Example

To draw the vector field for  $\ddot{x} + 0.25x = 0$  we can build the system:

$$\dot{x} = y 
\dot{y} = 0.25x$$

#### **Definition**

The second-order differential equation

$$m\ddot{x} + b\dot{x} + kx = f(t)$$

is equivalent to the system of first-order equations:

$$\dot{x} = y$$
 $\dot{y} = \ddot{x} = \frac{f(t)}{m} - \frac{k}{m}x - \frac{b}{m}y$ 


#### Example

To draw the vector field for  $\ddot{x} + 0.25x = 0$  we can build the system:

$$\dot{x} = y$$
 $\dot{y} = 0.25x$ 

Then, pplane may be used to plot the phase portrait.


#### **Electrical Circuits**



The current I in a wire, measured in amperes, is the flow of charge Q. That is, the current is the rate of change of the charge

$$I(t) = \dot{Q}(t)$$

#### **Electrical Circuits**




The current I in a wire, measured in amperes, is the flow of charge Q. That is, the current is the rate of change of the charge

$$I(t) = \dot{Q}(t)$$

**Kirchoff's Voltage Law** tell us that the input voltage V(t) is the sum of voltage drops around the circuit. In our circuit, we have three such voltage drops.

#### **Electrical Circuits**




**Drop across a Resistor:** By **Ohm's Law**, the voltage drop across a resistor is proportional to the current passing through it.

$$V_R(t) = RI(t)$$

Where *R* is the **resistance** of the resistor and is measured in *ohms*.

#### **Electrical Circuits**




**Drop across an Inductor:** By Faraday's Law, the voltage drop across an inductor is proportional to the time rate of change of the current passing through it.

$$V_L(t) = L\dot{I}(t)$$

where *L* is the **inductance** and is measured in *henries*.

#### **Electrical Circuits**




**Drop across a Capacitor:** The voltage drop across a capacitor is proportional to the charge Q(t) on the capacitor.

$$V_C(t) = rac{1}{C}Q(t) = rac{1}{C}\int I(t)dt$$

where *C* is the **capacitance** of the capacitor and is measured in *farads*.

#### **Electrical Circuits**



Thus, the voltage drop across the circuit is

$$V(t) = RI + L\dot{I} + \frac{1}{C}\int I(t)dt$$

This is called an **integro-differential equation** because it contains both a derivative and an integral.

Using the fact that  $I(t) = \dot{Q}(t)$  we can build the following equations.

Using the fact that  $I(t) = \dot{Q}(t)$  we can build the following equations.

## Series Circuit Equation (Charge)

$$L\ddot{Q} + R\dot{Q} + \frac{1}{C}Q = V(t)$$

If there is no voltage source (V(t) = 0), then

$$L\ddot{Q} + R\dot{Q} + \frac{1}{C}Q = 0$$

Using the fact that  $I(t) = \dot{Q}(t)$  we can build the following equations.

## Series Circuit Equation (Charge)

$$L\ddot{Q} + R\dot{Q} + \frac{1}{C}Q = V(t)$$

If there is no voltage source (V(t) = 0), then

$$L\ddot{Q} + R\dot{Q} + \frac{1}{C}Q = 0$$


## Series Circuit Equation (Current)

$$L\ddot{I} + R\dot{I} + \frac{1}{C}I = \dot{V}(t)$$

If there is no voltage source (V(t) = 0), then


$$L\ddot{I} + R\dot{I} + \frac{1}{6}I = 0$$

## Example



Consider a circuit composed of a capacitor and inductor hooked up in series. Suppose that at t=0 a charge  $Q_0$  is put on the capacitor.

## Example




Consider a circuit composed of a capacitor and inductor hooked up in series. Suppose that at t=0 a charge  $Q_0$  is put on the capacitor.

The IVP is

$$L\ddot{Q} + \frac{1}{C} = 0, \quad Q(0) = Q_0, \quad \dot{Q}(0) = 0$$

#### Example



Consider a circuit composed of a capacitor and inductor hooked up in series. Suppose that at t=0 a charge  $Q_0$  is put on the capacitor.

The IVP is

$$L\ddot{Q} + \frac{1}{C} = 0, \quad Q(0) = Q_0, \quad \dot{Q}(0) = 0$$

Thus, the solution is

$$Q(t) = c_1 \cos(\omega_0 t) + c_2 \sin(\omega_0 t)$$

where

$$\omega_0 = \sqrt{\frac{1}{LC}}$$