

[CS 225] Advanced C/C++

Lecture 13: Bit manipulation

Agenda

- Bit manipulation
- Bitwise operators review
 - ~ not
 - | or
 - & and
 - ^ xor
 - << shift left
 - >> shift right

Motivation

- Not all data is byte-aligned (compression, encryption)
- Not all addresses point to RAM, some may be used by memory-mapped I/O in embedded devices with individual bits for separate devices (single I/O pins).
- Some operations are faster when we shuffle bits.
- Some storage methods are more efficient.
- Makes us look smart...

<u>Terminology</u>


Bit – binary digit capable of storing a value 0 or 1.

- Not directly addressable; this would be inefficient.
- In memory stored always within some byte.

Terminology

Byte – addressable unit of data storage large enough to hold any member of the basic character set of the execution environment.

- Represented by unsigned char for raw memory.
- Represented by char for efficient processing (i.e. text).
- By definition: sizeof(char) == 1.
- 8 or more bits (CHAR BIT macro in <climits>):
- Windows, POSIX (Linux, Android), consoles mandate 8 bits.



Terminology


Mask – one or more bytes with predefined bits for selecting which bits of input to include or omit in an operation.

Flag – one of bits in a byte where individual bits have distinct business meaning.

<u>Terminology</u>

Endianness – sequencing of multibyte data in memory

- **Little-endian** least significant byte at the smallest address (x86, x64, ARM, RISC-V)
- Big-endian most significant byte at the smallest address (TCP/IP, ancient Motorola-based Macintosh)



p r0 11 0

Operators

Bitwise NOT (unary)

- One's complement after promotion.
- Used for unconditional bitwise negation (toggling).

p q r 0 0 0 0 1 1 1 0 1 1 1 1

Bitwise OR (binary)

$$r = p \mid q$$
;

- Setting a bit to 1 if any of input bits is 1; 0 otherwise.
- Used for setting masked or remaining bits to 1.

```
#include <iostream>
int main()
{
    unsigned short p = 0x0105;
    unsigned char q = 3; // mask
    std::cout << (p | q) << std::endl;
    // 0b1`0000`0101 |
    // 0b0`0000`0011 =
    // 0b1`0000`0111 = 263
}</pre>
```

Bitwise AND (binary)

$$r = p \& q$$
;

- Setting a bit to 1 if both of input bits is 1; 0 otherwise.
- Used for clearing masked or remaining bits to 0.


```
#include <iostream>
int main()
{
    unsigned short p = 0x0105;
    unsigned char q = 3; // mask
    std::cout << (p & ~q) << std::endl;
    // 0b1`0000`0101 &
    //~0b0`0000`0011 =
    // 0b1`0000`0100 = 260
}</pre>
```

Bitwise XOR (binary)

$$r = p \wedge q$$
;

- Setting a bit to 1 if input bits differ; 0 otherwise.
- Used for toggling masked bits (selective negation).
- Used for comparisons and unary clearing (r = p ^ p).

```
#include <iostream>
int main()
{
    unsigned short p = 0b1111'0000;
    unsigned short q = 0b0001'0001;
    std::cout << (p ^ q) << std::endl;
    // 0b1111`0000 ^
    // 0b0001`0001 =
    // 0b1110`0001 = 225
}</pre>
```





Bitwise << (binary)</pre>

$$r = p \ll q$$
;

- Left shift of bits after promotion (MSB is discarded).
- Used for positioning a mask.
- Used for integral multiplication by powers of 2.

```
#include <iostream>
int main()
{
    unsigned short p = 0xF0;
    unsigned short q = 1 << 2; // mask
    std::cout << (p ^ q) << std::endl;
    // 0b1111`0000 ^
    // 0b0000`0100 =
    // 0b1111`0100 = 244
}</pre>
```



Bitwise >> (binary)

$$r = p \gg q$$
;

- Right shift of bits after promotion (LSB is discarded).
- Used for integral division by powers of 2.
- Used for printing masks and binary values.

```
#include <iostream>
void print_bin(unsigned int p)
{
    if (p) print_bin(p >> 1); // MSBs
    std::cout << (p & 1); // LSB
}
int main()
{
    print_bin(0b0011'0101);
}</pre>
```