

# 1.7 互斥量 mutex 的實現

## 1.7.1 mutex 的內核結構體

mutex 的定義及操作函數都在 Linux 內核檔 include \linux \mutex. h 中定義,如下:

```
// include/linux/mutex.h
struct mutex {
    /* 1: unlocked, 0: locked, negative: locked, possible waiters */atomic_t count; 1.count要么等于1要么等于0
                                    2.mutex的实现要借助spinlock
    spinlock t
                     wait_lock;
    struct list head
                         wait list;3.等待mutex的进程放在这里
#if defined(CONFIG_DEBUG_MUTEXES) || defined(CONFIG_MUTEX_SPIN_ON_OWNER)
    struct task_struct *owner;
                                    4.owner只是用于调试或优化性能,
#endif
                                      并不是用来实现: 谁获得mutex就由谁释放mutex
#ifdef CONFIG_MUTEX_SPIN_ON_OWNER
    struct optimistic_spin_queue osq; /* Spinner MCS lock */
#endif
#ifdef CONFIG DEBUG MUTEXES
    void
#endif
#ifdef CONFIG_DEBUG_LOCK_ALLOC
    struct lockdep_map dep_map;
#endif
};
```

初始化 mutex 之後,就可以使用 mutex\_lock 函數或其他衍生版本來獲取信號量,使用 mutex\_unlock 函數釋放信號量。我們只分析 mutex lock、mutex unlock 函數的實現。

這裡要堪誤一下:前面的視頻裡我們說 mutex 中的 owner 是用來記錄獲得 mutex 的進程,以後必須由它來釋放 mutex。這是錯的!

從上面的代碼可知, owner 並不一定存在!

owner 有 2 個用途: debug(CONFIG\_DEBUG\_MUTEXES)或 spin\_on\_owner(CONFIG\_MUTEX\_SPIN\_ON\_OWNER)。 什麼叫 spin on owner?

我們使用mutex的目的一般是用來保護一小段代碼,這段代碼運行的時間很快。這意味著一個獲得mutex的進程,可能很快就會釋放掉mutex。

針對這點可以進行優化,特別是當前獲得 mutex 的進程是在別的 CPU 上運行、並且"我"是唯一等待這個 mutex 的進程。在這種情況下,那"我"就原地 spin 等待吧:懶得去休眠了,休眠又喚醒就太慢了。

所以,mutex 是做了特殊的優化,比 semaphore 效率更高。但是在代碼上,並沒有要求"誰獲得 mutex,就必須由誰釋放 mutex",只是在使用慣例上是"誰獲得 mutex,就必須由誰釋放 mutex"。



## 1.7.2 mutex lock 函數的實現

### 1.7.2.1 fastpath

mutex 的設計非常精巧,比 semaphore 複雜,但是更高效。

首先要知道 mutex 的操作函數中有 fastpath、slowpath 兩條路徑(快速、慢速):如果 fastpath 成功,就不必使用 slowpath。

怎麼理解?

這需要把 metex 中的 count 值再擴展一下,之前說它只有  $1 \cdot 0$  兩個取值,1 表示 unlocked,0 表示 locked,還有一類值"負數"表示"locked,並且可能有其他程式在等待"。

代碼如下:

```
// kernel/locking/mutex.c

void __sched mutex_lock(struct mutex *lock)
{
    might_sleep();
    /*
    * The locking fastpath is the 1->0 transition from
    * 'unlocked' into 'locked' state.
    */1.先尝试fastpath
    __mutex_fastpath_lock(&lock->count, __mutex_lock_slowpath);
    mutex_set_owner(lock);3.执行到这肯定是成功了,设置owner
}
```

先看看 fastpath 的函數: mutex fastpath lock,這個函數在下面 2 個檔中都有定義:

```
include/asm-generic/mutex-xchg.h
include/asm-generic/mutex-dec.h
```

使用哪一個檔呢?看看 arch/arm/include/asm/mutex.h,內容如下:

```
#if __LINUX_ARM_ARCH__ < 6
#include <asm-generic/mutex-xchg.h>
#else
#include <asm-generic/mutex-dec.h>
#endif
```

所以,對於 ARMv6 以下的架構,使用 include/asm-generic/mutex-xchg.h 中的\_\_mutex\_fastpath\_lock 函數;對於 ARMv6 及以上的架構,使用 include/asm-generic/mutex-dec.h 中的\_\_mutex\_fastpath\_lock 函數。這 2 個檔中的\_\_mutex\_fastpath\_lock 函數是類似的, mutex-dec.h 中的代碼如下:

大部分情況下, mutex 當前值都是1, 所以通過 fastpath 函數可以非常快速地獲得 mutex。



### 1.7.2.2 slowpath

如果 mutex 當前值是 0 或負數,則需要調用\_\_mutex\_lock\_slowpath 慢慢處理:可能會休眠等待。

\_\_mutex\_lock\_common 函數也是在內核檔 kernel/locking/mutex.c 中實現的,下麵分段講解。

① 分析第一段代碼:

```
504: static __always_inline int __sched
505: __mutex_lock_common(struct mutex *lock, long state, unsigned int subclass,
                struct lockdep_map *nest_lock, unsigned long ip,
506:
                struct ww_acquire_ctx *ww_ctx, const bool use_ww_ctx)
508: {
509:
        struct task_struct *task = current;
        struct mutex waiter waiter;
510:
511:
        unsigned long flags;
512:
        int ret;
                            use_ww_ctx等于0,不走这分支
513:
514:
        if (use_ww_ctx) {
515:
            struct ww_mutex *ww = container_of(lock, struct ww_mutex, base);
516:
            if (unlikely(ww_ctx == READ_ONCE(ww->ctx)))
517:
                return - EALREADY;
518:
519:
        preempt_disable(); 先禁止preempt
520:
        mutex_acquire_nest(&lock->dep_map, subclass, 0, nest_lock, ip);
522:
523:
        if (mutex_optimistic_spin(lock, ww_ctx, use_ww_ctx)) {
                                                               这个函数不是重点,
524:
             /* got the lock,yay! */optimistic乐观的,
                                                               这是一个优化而已
525:
            preempt_enable();
                                    也许其他CPU获得了mutex,
            return 0;
527:
                                    它会很快释放,可能不需要休眠
528:
```

## ② 分析第二段代碼:

```
528:
529:
         spin lock mutex(&lock->wait lock, flags); 获得spinlock
530:
531:
          * Once more, try to acquire the lock. Only try-lock the mutex if
532:
          * it is unlocked to reduce unnecessary xchg() operations.
533:
534:
         if (!mutex_is_locked(lock) &&
535:
                                                           如果count==1,
             (atomic_xchg_acquire(&lock->count, 0) == 1))
536:
                                                           那就不需要等待了
             goto ↓skip_wait;
537:
538:
```



### ③ 分析第三段代碼:

```
539:
         debug_mutex_lock_common(lock, &waiter);
540:
         debug mutex_add_waiter(lock, &waiter, task);
541:
         /* add waiting tasks to the end of the waitqueue (FIFO): ^{*}/
542:
543:
         list_add_tail(&waiter.list, &lock->wait_list);
                                把当前进程放入mutex的wait_list
544:
         waiter.task = task;
545:
546:
         lock_contended(&lock->dep_map, ip);
547:
```

這個 wait list 是 FIFO(Firt In Firs Out),誰先排隊,誰就可以先得到 mutex。

## ④ 分析第四段代碼: for 迴圈, 這是重點

```
for (;;) {
548:
549:
             *
550:
               Lets try to take the lock again - this is needed even if
551:
             * we get here for the first time (shortly after failing to
552:
             st acquire the lock), to make sure that we get a wakeup once
553:
             * it's unlocked. Later on, if we sleep, this is the
             * operation that gives us the lock. We xchg it to -1, so
554:
555:
             * that when we release the lock, we properly wake up the
             * other waiters. We only attempt the xchg if the count is
556:
557:
             * non-negative in order to avoid unnecessary xchg operations:
558:
559:
            if (atomic read(&lock->count) >= 0 &&
560:
                 (atomic_xchg_acquire(&lock->count, -1) == 1))
561:
                        如果count==1, 把它设为-1(被我lock了),break退出循环(成功了);
562:
                        如果count==0,把它设为-1(被别人lock了),继续往下走;
563:
                        如果count<0,它表示本来就被别人lock了,不用再设为-1,继续往下走
564:
               got a signal? (This code gets eliminated in the
               TASK UNINTERRUPTIBLE case.)
565:
566:
567:
            if (unlikely(signal_pending_state(state, task))) {
568:
                ret = -EINTR;
                               有信号? 那就退出吧
569:
                goto ↓err;
570:
571:
572:
            if (use_ww_ctx && ww_ctx->acquired > 0) {
                ret = __ww_mutex_lock_check_stamp(lock, ww_ctx);
if (ret)
573:
574:
575:
                    goto ↓err;
            }
576:
577:
578:
              579:
580:
            /* didn't get the lock, go to sleep: */
581:
            spin_unlock_mutex(&lock->wait_lock, flags);释放spinlock
            schedule_preempt_disabled(); 主动发起调度
582:
583:
            spin_lock_mutex(&lock->wait_lock, flags);再次获得spinlock
584:
        } « end for ;; » 能运行到这里,是被信号或者mutex_unlock唤醒的,在for循环里的再次判断
```



### ⑤ 分析第五段代碼:收尾工作

```
__set_task_state(task, TASK_RUNNING); 能执行到这里,表示获得了mutex
                                             <u>设置</u>当前进程为RUNNING
        mutex_remove_waiter(lock, &waiter,
587:
                                         task);
        /* set it to 0 if there are no waiters left:
588:
                                                       ➤ 从mutex的wait_list中
        if (likely(list_empty(&lock->wait_list)))
                                                         删除本进程
589:
590:
            atomic_set(&lock->count, 0);
591:
        debug mutex free waiter(&waiter);
                                             如果wait list为空,表示无人等待mutex,
592:
                                             把count设为0
593: skip wait:
594:
        /* got the lock - cleanup and rejoice! */
595:
        lock_acquired(&lock->dep_map, ip);
596:
        mutex_set_owner(lock); 设置owner为当前进程
597:
        598:
599:
600:
            ww_mutex_set_context_slowpath(ww, ww_ctx);
601:
602:
        spin_unlock_mutex(&lock->wait_lock, flags); 释放spinlock
603:
        preempt_enable(); 使能preempt
604:
        return 0;
606:
```

## 1.7.3 mutex\_unlock 函數的實現

mutex\_unlock 函數中也有 fastpath、slowpath 兩條路徑(快速、慢速):如果 fastpath 成功,就不必使用 slowpath。

代碼如下:

```
// kernel/locking/mutex.c
```



### 1.7.3.1 fastpath

先看看 fastpath 的函數: mutex fastpath lock,這個函數在下面 2 個檔中都有定義:

```
include/asm-generic/mutex-xchg.h
include/asm-generic/mutex-dec.h
```

使用哪一個檔呢?看看 arch/arm/include/asm/mutex.h,內容如下:

```
#if _LINUX_ARM_ARCH__ < 6
#include <asm-generic/mutex-xchg.h>
#else
#include <asm-generic/mutex-dec.h>
#endif
```

所以,對於 ARMv6 以下的架構,使用 include/asm-generic/mutex-xchg.h 中的\_\_mutex\_fastpath\_lock 函數;對於 ARMv6 及以上的架構,使用 include/asm-generic/mutex-dec.h 中的\_\_mutex\_fastpath\_lock 函數。這 2 個檔中的\_\_mutex\_fastpath\_lock 函數是類似的, mutex-dec.h 中的代碼如下:

大部分情況下,加 1 後 mutex 的值都是 1,表示無人等待 mutex,所以通過 fastpath 函數直接增加 mutex 的 count 值為 1 就可以了。

如果 mutex 的值加 1 後還是小於等於 0,就表示有人在等待 mutex,需要去 wait\_list 把它取出喚醒,這需要用到 slowpath 的函數: mutex unlock slowpath。

### 1.7.3.2 slowpath

如果 mutex 當前值是 0 或負數,則需要調用\_\_mutex\_unlock\_slowpath 慢慢處理:需要喚醒其他進程。

```
// kernel/locking/mutex.c
/*
    * Release the lock, slowpath:
    */
    __visible void
    __mutex_unlock_slowpath(atomic_t *lock_count)
{
    struct mutex *lock = container_of(lock_count, struct mutex, count);
    __mutex_unlock_common_slowpath(lock, 1);
}
```

\_\_mutex\_unlock\_common\_slowpath 函數代碼如下,主要工作就是從 wait\_list 中取出並喚醒第 1 個進程:



```
// kernel/locking/mutex.c
static inline void
  mutex_unlock_common_slowpath(struct mutex *lock, int nested)
   unsigned long flags;
   WAKE_Q(wake_q);
    st As a performance measurement, release the lock before doing other
    * wakeup related duties to follow. This allows other tasks to acquire
    * the lock sooner, while still handling cleanups in past unlock calls.
    * This can be done as we do not enforce strict equivalence between the
    * mutex counter and wait_list.
    * Some architectures leave the lock unlocked in the fastpath failure
    * case, others need to leave it locked. In the later case we have to
    * unlock it here - as the lock counter is currently 0 or negative.
   if ( mutex slowpath needs to unlock())
                                        执行到这里count被设为1了
       atomic set(&lock->count, 1);
   mutex_release(&lock->dep_map, nested, _RET_IP_);
   debug mutex unlock(lock);
   if (!list_empty(&lock->wait list)) {
                                                 从wait list中
       /* get the first entry from the wait-list:
                                                 取出第一个进程
       struct mutex_waiter *waiter =
              list_entry(lock->wait_list.next,
                    struct mutex waiter, list);
       debug_mutex_wake_waiter(lock, waiter);
       wake_q_add(&wake_q, waiter->task);
  spin_unlock_mutex(&lock->wait_lock, flags); 释放pinlock
```